

Hortonworks Data Platform

Hadoop Security Guide

(March 1, 2016)

Hortonworks Data Platform: Hadoop Security Guide

Copyright © 2012-2016 Hortonworks, Inc. Some rights reserved.

The Hortonworks Data Platform, powered by Apache Hadoop, is a massively scalable and 100% open source platform for storing, processing and analyzing large volumes of data. It is designed to deal with data from many sources and formats in a very quick, easy and cost-effective manner. The Hortonworks Data Platform consists of the essential set of Apache Hadoop projects including MapReduce, Hadoop Distributed File System (HDFS), HCatalog, Pig, Hive, HBase, ZooKeeper and Ambari. Hortonworks is the major contributor of code and patches to many of these projects. These projects have been integrated and tested as part of the Hortonworks Data Platform release process and installation and configuration tools have also been included.

Unlike other providers of platforms built using Apache Hadoop, Hortonworks contributes 100% of our code back to the Apache Software Foundation. The Hortonworks Data Platform is Apache-licensed and completely open source. We sell only expert technical support, [training](#) and partner-enablement services. All of our technology is, and will remain free and open source.

Please visit the [Hortonworks Data Platform](#) page for more information on Hortonworks technology. For more information on Hortonworks services, please visit either the [Support](#) or [Training](#) page. Feel free to [Contact Us](#) directly to discuss your specific needs.



Except where otherwise noted, this document is licensed under **Creative Commons Attribution ShareAlike 4.0 License**.
<http://creativecommons.org/licenses/by-sa/4.0/legalcode>

Table of Contents

1. HDP Security Overview	1
1.1. Understanding Data Lake Security	1
1.2. HDP Security Features	3
1.2.1. Administration	4
1.2.2. Authentication and Perimeter Security	4
1.2.3. Authorization	5
1.2.4. Audit	7
1.2.5. Data Protection	7
2. Authentication	8
2.1. Enabling Kerberos Authentication Using Ambari	8
2.1.1. Kerberos Overview	8
2.1.2. Hadoop and Kerberos Principals	9
2.1.3. Installing and Configuring the KDC	10
2.1.4. Enabling Kerberos Security	15
2.1.5. Kerberos Client Packages	19
2.1.6. Disabling Kerberos Security	19
2.1.7. Customizing the Attribute Template	20
2.1.8. Managing Admin Credentials	20
2.2. Configuring Ambari Authentication with LDAP or AD	21
2.2.1. Configuring Ambari for LDAP or Active Directory Authentication	21
2.2.2. Configuring Ranger Authentication with UNIX, LDAP, or AD	26
2.2.3. Encrypting Database and LDAP Passwords in Ambari	35
2.3. Configuring LDAP Authentication in Hue	37
2.3.1. Enabling the LDAP Backend	37
2.3.2. Enabling User Authentication with Search Bind	37
2.3.3. Setting the Search Base to Find Users and Groups	38
2.3.4. Specifying the URL of the LDAP Server	39
2.3.5. Specifying LDAPS and StartTLS Support	39
2.3.6. Specifying Bind Credentials for LDAP Searches	39
2.3.7. Synchronizing Users and Groups	39
2.3.8. Setting Search Bind Authentication and Importing Users and Groups	40
2.3.9. Setting LDAP Users' Filter	40
2.3.10. Setting an LDAP Groups Filter	41
2.3.11. Setting Multiple LDAP Servers	41
2.4. Advanced Security Options for Ambari	42
2.4.1. Configuring Ambari for Non-Root	42
2.4.2. Optional: Ambari Web Inactivity Timeout	45
2.4.3. Set Up Kerberos for Ambari Server	46
2.4.4. Optional: Set Up Two-Way SSL Between Ambari Server and Ambari Agents	47
2.4.5. Optional: Configure Ciphers and Protocols for Ambari Server	47
2.4.6. Optional: HTTP Cookie Persistence	47
2.5. Enabling SPNEGO Authentication for Hadoop	48
2.5.1. Configure Ambari Server for Authenticated HTTP	48
2.5.2. Configuring HTTP Authentication for HDFS, YARN, MapReduce2, HBase, Oozie, Falcon and Storm	48
2.6. Setting Up Kerberos Authentication for Non-Ambari Clusters	49

2.6.1. Preparing Kerberos	49
2.6.2. Configuring HDP for Kerberos	55
2.6.3. Setting up One-Way Trust with Active Directory	81
2.6.4. Configuring Proxy Users	83
2.7. Perimeter Security with Apache Knox	83
2.7.1. Apache Knox Gateway Overview	83
2.7.2. Configuring the Knox Gateway	86
2.7.3. Defining Cluster Topologies	90
2.7.4. Configuring a Hadoop Server for Knox	91
2.7.5. Mapping the Internal Nodes to External URLs	96
2.7.6. Configuring Authentication	99
2.7.7. Configuring Identity Assertion	110
2.7.8. Configuring Service Level Authorization	114
2.7.9. Audit Gateway Activity	118
2.7.10. Gateway Security	119
2.7.11. Setting Up Knox for WebHDFS HA	123
2.7.12. Knox CLI Testing Tools	125
3. Configuring Authorization in Hadoop	127
3.1. Installing Ranger Using Ambari	127
3.1.1. Overview	127
3.1.2. Installation Prerequisites	127
3.1.3. Ranger Installation	133
3.1.4. Enabling Ranger Plugins	170
3.1.5. Ranger Plugins - Kerberos Overview	195
3.2. Using Ranger to Provide Authorization in Hadoop	199
3.2.1. Opening and Closing the Ranger Console	199
3.2.2. Console Operations Summary	200
3.2.3. Configuring Services	201
3.2.4. Policy Management	218
3.2.5. Users/Groups and Permissions Administration	236
3.2.6. Reports Administration	246
3.2.7. Special Requirements for High Availability Environments	249
3.2.8. Adding a New Component to Apache Ranger	250
3.2.9. Developing a Custom Authorization Module	253
3.2.10. Apache Ranger Public REST API	253
4. Data Protection: Wire Encryption	288
4.1. Enabling RPC Encryption	288
4.2. Enabling Data Transfer Protocol	289
4.3. Enabling SSL: Understanding the Hadoop SSL Keystore Factory	289
4.4. Creating and Managing SSL Certificates	291
4.4.1. Obtain a Certificate from a Trusted Third-Party Certification Authority (CA)	291
4.4.2. Create and Set Up an Internal CA (OpenSSL)	292
4.4.3. Installing Certificates in the Hadoop SSL Keystore Factory (HDFS, MapReduce, and YARN)	296
4.4.4. Using a CA-Signed Certificate	297
4.5. Enabling SSL for HDP Components	298
4.6. Enable SSL for WebHDFS, MapReduce Shuffle, and YARN	298
4.7. Enable SSL for HttpFS	301
4.8. Enable SSL on Oozie	302
4.8.1. Configure Oozie HCatalogJob Properties	303

4.9. Enable SSL on the HBase REST Server	303
4.10. Enable SSL on the HBase Web UI	305
4.11. Enable SSL on HiveServer2	306
4.12. Enable SSL for Kafka Clients	307
4.12.1. Configuring the Kafka Broker	307
4.12.2. Configuring Kafka Producer and Kafka Consumer	309
4.13. Enable SSL for Accumulo	310
4.13.1. Generate a Certificate Authority	310
4.13.2. Generate a Certificate/Keystore Per Host	311
4.13.3. Configure Accumulo Servers	312
4.13.4. Configure Accumulo Clients	313
4.14. SPNEGO setup for WebHCat	313
4.15. Configure SSL for Hue	314
4.15.1. Enabling SSL on Hue by Using a Private Key	314
4.15.2. Enabling SSL on Hue Without Using a Private Key	314
4.16. Configure SSL for Knox	315
4.16.1. Self-Signed Certificate with Specific Hostname for Evaluations	315
4.16.2. CA-Signed Certificates for Production	315
4.16.3. Setting Up Trust for the Knox Gateway Clients	316
4.17. Securing Phoenix	316
4.18. Set Up SSL for Ambari	316
4.18.1. Set Up Truststore for Ambari Server	317
4.19. Configure Ambari Ranger SSL	318
4.19.1. Configuring Ambari Ranger SSL Using Public CA Certificates	318
4.19.2. Configuring Ambari Ranger SSL Using a Self-Signed Certificate	331
4.20. Configure Non-Ambari Ranger SSL	346
4.20.1. Configuring Non-Ambari Ranger SSL Using Public CA Certificates	346
4.20.2. Configuring Non-Ambari Ranger SSL Using a Self Signed Certificate	349
4.21. Connecting to SSL-Enabled Components	353
4.21.1. Connect to SSL Enabled HiveServer2 using JDBC	354
4.21.2. Connect to SSL Enabled Oozie Server	354
5. Auditing in Hadoop	356
5.1. Using Apache Solr for Ranger Audits	356
5.1.1. Prerequisites	356
5.1.2. Installing Solr	357
5.1.3. Configuring Solr Standalone	357
5.1.4. Configuring SolrCloud	358
5.2. Manually Enabling Audit Settings in Ambari Clusters	360
5.2.1. Manually Updating Ambari Solr Audit Settings	360
5.2.2. Manually Updating Ambari HDFS Audit Settings	361
5.3. Enabling Audit Logging in Non-Ambari Clusters	362
5.4. Manging Auditing in Ranger	363
5.4.1. View Operation Details	364
5.4.2. Access	365
5.4.3. Admin	366
5.4.4. Login Sessions	367
5.4.5. Plugins	368
6. Data Protection: HDFS Encryption	369
6.1. Ranger KMS Administration Guide	369
6.1.1. Installing the Ranger Key Management Service	369

6.1.2. Enable Ranger KMS Audit	377
6.1.3. Enabling SSL for Ranger KMS	380
6.1.4. Install Multiple Ranger KMS	385
6.1.5. Using the Ranger Key Management Service	386
6.1.6. Ranger KMS Properties	391
6.1.7. Troubleshooting Ranger KMS	395
6.2. HDFS "Data at Rest" Encryption	395
6.2.1. HDFS Encryption Overview	395
6.2.2. Configuring and Starting the Ranger Key Management Service (Ranger KMS)	397
6.2.3. Configuring and Using HDFS Data at Rest Encryption	398
6.2.4. Configuring HDP Services for HDFS Encryption	406
6.2.5. Appendix: Creating an HDFS Admin User	413

List of Figures

3.1. Installing Ranger - Main Dashboard View	134
3.2. Installing Ranger - Add Service	135
3.3. Installing Ranger - Choose Service	136
3.4. Installing Ranger - Ranger Requirements	137
3.5. Installing Ranger Assign Masters	138
3.6. Knox Service Manager	198
3.7. Knox Service Edit	198
6.1. HDFS Encryption Components	397

List of Tables

2.1. UNIX Authentication Settings	27
2.2. Active Directory Authentication Settings	28
2.3. Active Directory Custom ranger-admin-site Settings	30
2.4. LDAP Authentication Settings	32
2.5. LDAP Custom ranger-admin-site Settings	34
2.6. Active Directory Authentication Settings	35
2.7. Service Principals	53
2.8. Service Keytab File Names	54
2.9. General core-site.xml, Knox, and Hue	57
2.10. core-site.xml Master Node Settings – Knox Gateway	58
2.11. core-site.xml Master Node Settings – Hue	58
2.12. hdfs-site.xml File Property Settings	60
2.13. yarn-site.xml Property Settings	64
2.14. mapred-site.xml Property Settings	66
2.15. hbase-site.xml Property Settings – HBase Server	67
2.16. hive-site.xml Property Settings	70
2.17. oozie-site.xml Property Settings	70
2.18. webhcat-site.xml Property Settings	71
2.19. Supported Hadoop Services	85
2.20. Apache Service Gateway Directores	86
2.21. Cluster Topology Provider and Service Roles	90
2.22. gateway-site.xml Configuration Elements	109
2.23. LDAP Authentication and Authorization Arguments	126
3.1. Ranger DB Host	139
3.2. Driver Class Name	140
3.3. Ranger DB Username Settings	140
3.4. JDBC Connect String	140
3.5. DBA Credential Settings	141
3.6. UNIX User Sync Properties	150
3.7. LDAP/AD Common Configs	152
3.8. LDAP/AD User Configs	153
3.9. LDAP/AD Group Configs	155
3.10. UNIX Authentication Settings	157
3.11. LDAP Authentication Settings	158
3.12. AD Settings	162
3.13. LDAP Advanced ranger-ugsync-site Settings	167
3.14. AD Advanced ranger-ugsync-site Settings	167
3.15. Advanced ranger-ugsync-site Settings for LDAP and AD	167
3.16. HDFS Plugin Properties	196
3.17. Hive Plugin Properties	196
3.18. HBase Plugin Properties	197
3.19. Knox Plugin Properties	197
3.20. Knox Configuration Properties	198
3.21. Service Details	203
3.22. Config Properties	204
3.23. Service Details	205
3.24. Config Properties	206
3.25. Service Details	207

3.26. Config Properties	208
3.27. Service Details	209
3.28. Config Properties	209
3.29. Service Details	211
3.30. Config Properties	211
3.31. Service Details	213
3.32. Config Properties	213
3.33. Service Details	215
3.34. Config Properties	215
3.35. Service Details	217
3.36. Config Properties	217
3.37. Policy Details	220
3.38. User and Group Permissions	220
3.39. Policy Details	223
3.40. User and Group Permissions	223
3.41. Policy Details	225
3.42. User and Group Permissions	225
3.43. Policy Details	228
3.44. User and Group Permissions	228
3.45. Policy Details	229
3.46. User and Group Permissions	230
3.47. Policy Details	231
3.48. User and Group Permissions	231
3.49. Policy Details	233
3.50. User and Group Permissions	233
3.51. Knox User and Group Permissions	234
3.52. Policy Details	235
3.53. User and Group Permissions	236
4.1. Components that Support SSL	289
4.2. Configure SSL Data Protection for HDP Components	298
4.3. Configuration Properties in ssl-server.xml	300
5.1. Solr install.properties Values	357
5.2. Solr install.properties Values	359
5.3. Search Criteria	365
5.4. Search Criteria	366
5.5. Search Criteria	367
5.6. Agents Search Criteria	368
6.1. Properties in Advanced dbks-site Menu (dbks-site.xml)	391
6.2. Properties in Advanced kms-env	391
6.3. Properties in Advanced kms-properties (install.properties)	391
6.4. Properties in Advanced kms-site (kms-site.xml)	392
6.5. Properties in Advanced ranger-kms-audit (ranger-kms-audit.xml)	393
6.6. Properties in Advanced ranger-kms-policymgr-ssl	394
6.7. Properties in Advanced ranger-kms-security	394
6.8. Troubleshooting Suggestions	395

1. HDP Security Overview

Security is essential for organizations that store and process sensitive data in the Hadoop ecosystem. Many organizations must adhere to strict corporate security policies.

Hadoop is a distributed framework used for data storage and large-scale processing on clusters using commodity servers. Adding security to Hadoop is challenging because all the interactions do not follow the classic client-server pattern. In Hadoop the file system is partitioned and distributed, requiring authorization checks at multiple points; a submitted job is executed at a later time on nodes different than the node on which the client authenticated and submitted the job; secondary services such as a workflow system access Hadoop on behalf of users; and the system scales to thousands of servers and tens of thousands of concurrent tasks.

A Hadoop-powered "Data Lake" can provide a robust foundation for a new generation of Big Data analytics and insight, but can also increase the number of access points to an organization's data. As diverse types of enterprise data are pulled together into a central repository, the inherent security risks must be understood and addressed.

Hortonworks understands the importance of security and governance for every business. To ensure effective protection for our customers, we use a holistic approach based on five core security features:

- Administration
- Authentication and perimeter security
- Authorization
- Audit
- Data protection

This chapter provides an overview of the security features implemented in the Hortonworks Data Platform (HDP). Subsequent chapters in this guide provide more details on each of these security features.

1.1. Understanding Data Lake Security


The general consensus in nearly every industry is that data is an essential new driver of competitive advantage. Hadoop plays a critical role in the modern data architecture by providing low-cost, large-scale data storage and processing. The successful Hadoop journey typically starts with data architecture optimization or new advanced analytic applications, which leads to the formation of a Data Lake. As new and existing types of data from sources such as machine sensors, server logs, clickstream data, and other sources flow into the Data Lake, it serves as a central repository based on shared Hadoop services that power deep organizational insights across a broad and diverse set of data.

The need to protect the Data Lake with comprehensive security is clear. As large and growing volumes of diverse data are channeled into the Data Lake, it will store vital and often highly sensitive business data. However, the external ecosystem of data and operational systems feeding the Data Lake is highly dynamic and can introduce new

security threats on a regular basis. Users across multiple business units can access the Data Lake freely and refine, explore, and enrich its data at will, using methods of their own choosing, further increasing the risk of a breach. Any breach of this enterprise-wide data can be catastrophic: privacy violations, regulatory infractions, or the compromise of vital corporate intelligence. To prevent damage to the company's business, customers, finances, and reputation, IT leaders must ensure that their Data Lake meets the same high standards of security as any legacy data environment.

Only as Secure as the Weakest Link

Piecemeal protections are no more effective for a Data Lake than they would be in a traditional repository. Hortonworks firmly believes that effective Hadoop security depends on a holistic approach. Our framework for comprehensive security revolves around five pillars of security: administration, authentication/ perimeter security, authorization, audit, and data protection.




Requirements for Enterprise-Grade Security

Security administrators must address questions and provide enterprise-grade coverage across each of these areas as they design the infrastructure to secure data in Hadoop. If any of these pillars is vulnerable, it will become a risk vector built into the very fabric of the company's Big Data environment. In this light, your Hadoop security strategy must address all five pillars, with a consistent implementation approach to ensure their effectiveness.

Needless to say, you can't achieve comprehensive protection across the Hadoop stack by using a hodgepodge of point solutions. Security must be an integral part of the platform on which your Data Lake is built. This bottom-up approach makes it possible to enforce and manage security across the stack through a central point of administration, thereby preventing gaps and inconsistencies. This approach is especially important for Hadoop implementations where new applications or data engines are always on the horizon in the form of new Open Source projects – a dynamic scenario that can quickly exacerbate any vulnerability.

Hortonworks helps customers maintain the high levels of protection for enterprise data by building centralized security administration and management into the infrastructure of the Hortonworks Data Platform. HDP provides an enterprise-ready data platform with


rich capabilities spanning security, governance, and operations. HDP includes powerful data security functionality that works across component technologies and integrates with preexisting EDW, RDBMS and MPP systems. By implementing security at the platform level, Hortonworks ensures that security is consistently administered to all of the applications across the stack, and simplifies the process of adding or removing Hadoop applications.



The Hortonworks Data Platform

1.2. HDP Security Features

HDP uses Apache Ranger to provide centralized security administration and management. The Ranger Administration Portal is the central interface for security administration. Users can create and update policies, which are then stored in a policy database. Ranger plugins (light-weight Java programs) are embedded within the processes of each cluster component. For example, the Ranger plugin for Apache Hive is embedded within Hiveserver2.




Apache Ranger Architecture

These plugins pull policies from a central server and store them locally in a file. When a user request comes through the component, these plugins intercept the request and evaluate it against the security policy. Plugins also collect data from the user request and follow a separate thread to send this data back to the audit server.

1.2.1. Administration

In order to deliver consistent security administration and management, Hadoop administrators require a centralized user interface that can be used to define, administer and manage security policies consistently across all of the Hadoop stack components.



Ranger Centralized Security Administration

The Apache Ranger administration console provides a central point of administration for the other four pillars of Hadoop security.



Ranger Admin Console

1.2.2. Authentication and Perimeter Security

Establishing user identity with strong authentication is the basis for secure access in Hadoop. Users need to reliably identify themselves and then have that identity propagated throughout the Hadoop cluster to access cluster resources. Hortonworks uses Kerberos for authentication. Kerberos is an industry standard used to authenticate users and resources within a Hadoop cluster. HDP also includes Ambari, which simplifies Kerberos setup, configuration, and maintenance.

Apache Knox Gateway is used to ensure perimeter security for Hortonworks customers. With Knox, enterprises can confidently extend the Hadoop REST API to new users without

Kerberos complexities, while also maintaining compliance with enterprise security policies. Knox provides a central gateway for Hadoop REST APIs that have varying degrees of authorization, authentication, SSL, and SSO capabilities to enable a single access point for Hadoop.

Single, simple point of access for a cluster	Central controls ensure consistency across one or more clusters	Integrated with existing systems to simplify identity maintenance
<ul style="list-style-type: none">• Kerberos Encapsulation• Single Hadoop access point• REST API hierarchy• Consolidated API calls• Multi-cluster support	<ul style="list-style-type: none">• Eliminates SSH "edge node"• Central API management• Central audit control• Service level Authorization	<ul style="list-style-type: none">• SSO Integration – Siteminder and OAM*• LDAP & AD integration

Apache Knox Features

1.2.3. Authorization

Ranger manages fine-grained access control through a rich user interface that ensures consistent policy administration across Hadoop data access components. Security administrators have the flexibility to define security policies for a database, table and column, or a file, and can administer permissions for specific LDAP-based groups or individual users. Rules based on dynamic conditions such as time or geolocation, can also be added to an existing policy rule. The Ranger authorization model is highly pluggable and can be easily extended to any data source using a service-based definition.

Administrators can use Ranger to define a centralized security policy for the following Hadoop components:

- HDFS
- YARN
- Hive
- HBase
- Storm
- Knox
- Solr
- Kafka

Ranger works with standard authorization APIs in each Hadoop component, and is able to enforce centrally administered policies for any method used to access the data lake.

Policy Details :

Policy Name * enabled

Hive Database * include

table include

Hive Column * include

Description

Audit Logging YES

User and Group Permissions :

Permissions Select Group Select User Delegate Admin

Add Permissions + Delegate Admin

select update Create Drop Alter Index Lock All Select/Deselect All

Ranger Security Policy Definitions

Ranger provides administrators with deep visibility into the security administration process that is required for auditing purposes. The combination of Ranger’s rich user interface with deep audit visibility makes it highly intuitive to use, enhancing productivity for security administrators.

Ranger Access Manager Audit Settings admin

Service Manager sandbox_hive Policies

List of Policies : sandbox_hive

Search for your policy...

Add New Policy

Policy ID	Policy Name	Status	Audit Logging	Groups	Users	Action
3	sandbox_hive-1-20150529142947	Enabled	Enabled	--	xapolicymgr	
4	Hive Global Tables Allow	Disabled	Enabled	public	--	
5	Hive Global UDF Allow	Disabled	Enabled	public	--	
18	Call_Details_Table	Enabled	Enabled	developer	--	
19	Customer_Details_Table	Disabled	Enabled	Marketing	--	
20	Hive Demo Table Loader	Enabled	Enabled	--	hive	
21	Hive Demo UDF Loader	Enabled	Enabled	--	hive	
29	admin policy	Enabled	Enabled	--	admin	

Ranger Security Policy Overview

1.2.4. Audit

As customers deploy Hadoop into corporate data and processing environments, metadata and data governance must be vital parts of any enterprise-ready data lake. For these reasons, Hortonworks [established the Data Governance Initiative \(DGI\) with Aetna, Merck, Target, and SAS](#) to introduce a common approach to Hadoop data governance into the open source community. This initiative has since evolved into a new open source project called Apache Atlas. Apache Atlas is a set of core foundational governance services that enables enterprises to effectively and efficiently meet their compliance requirements within Hadoop, and also allows integration with the complete enterprise data ecosystem. These services include:

- Search and Lineage for datasets
- Metadata-driven data access control
- Indexed and searchable centralized auditing operational events
- Data lifecycle management – ingestion to disposition
- Metadata interchange with other tools

Ranger also provides a centralized framework for collecting access audit history and easily reporting this data, including the ability to filter data based on various parameters. HDP enhances audit information that is captured within various components within Hadoop, and provides insights through this centralized reporting capability.

1.2.5. Data Protection

Data protection adds a robust layer of security by making data unreadable in transit over the network or at rest on a disk. HDP fully satisfies enterprise requirements for security and compliance by using transparent data encryption (TDE) to encrypt data for HDFS files, along with a Ranger-embedded open source Hadoop key management store (KMS). Ranger provides security administrators with the ability to manage keys and authorization policies for KMS. Hortonworks is also working extensively with its encryption partners to integrate HDFS encryption with enterprise-grade key management frameworks. With Hortonworks, our customers have the flexibility to leverage an open source key management store (KMS), or use enterprise-wide KMS solutions provided by the partner ecosystem.

Encryption in HDFS, combined with KMS access policies maintained by Ranger, prevents rogue Linux or Hadoop administrators from accessing data, and supports segregation of duties for both data access and encryption.

2. Authentication

2.1. Enabling Kerberos Authentication Using Ambari

This chapter describes how to configure Kerberos for strong authentication for Hadoop users and hosts in an Ambari-managed cluster.

- [Kerberos Overview \[8\]](#)
- [Hadoop and Kerberos Principals \[9\]](#)
- [Installing and Configuring the KDC \[10\]](#)
- [Enabling Kerberos Security \[15\]](#)

2.1.1. Kerberos Overview

Strongly authenticating and establishing a user's identity is the basis for secure access in Hadoop. Users need to be able to reliably "identify" themselves and then have that identity propagated throughout the Hadoop cluster. Once this is done, those users can access resources (such as files or directories) or interact with the cluster (like running MapReduce jobs). Besides users, Hadoop cluster resources themselves (such as Hosts and Services) need to authenticate with each other to avoid potential malicious systems or daemon's "posing as" trusted components of the cluster to gain access to data.

Hadoop uses Kerberos as the basis for strong authentication and identity propagation for both user and services. Kerberos is a third party authentication mechanism, in which users and services rely on a third party - the Kerberos server - to authenticate each to the other. The Kerberos server itself is known as the **Key Distribution Center**, or **KDC**. At a high level, it has three parts:

- A database of the users and services (known as **principals**) that it knows about and their respective Kerberos passwords
- An **Authentication Server (AS)** which performs the initial authentication and issues a **Ticket Granting Ticket (TGT)**
- A **Ticket Granting Server (TGS)** that issues subsequent service tickets based on the initial TGT

A **user principal** requests authentication from the AS. The AS returns a TGT that is encrypted using the user principal's Kerberos password, which is known only to the user principal and the AS. The user principal decrypts the TGT locally using its Kerberos password, and from that point forward, until the ticket expires, the user principal can use the TGT to get service tickets from the TGS. Service tickets are what allow a principal to access various services.


Because cluster resources (hosts or services) cannot provide a password each time to decrypt the TGT, they use a special file, called a **keytab**, which contains the resource principal's authentication credentials. The set of hosts, users, and services over which the Kerberos server has control is called a **realm**.

Terminology

Term	Description
Key Distribution Center, or KDC	The trusted source for authentication in a Kerberos-enabled environment.
Kerberos KDC Server	The machine, or server, that serves as the Key Distribution Center (KDC).
Kerberos Client	Any machine in the cluster that authenticates against the KDC.
Principal	The unique name of a user or service that authenticates against the KDC.
Keytab	A file that includes one or more principals and their keys.
Realm	The Kerberos network that includes a KDC and a number of Clients.
KDC Admin Account	An administrative account used by Ambari to create principals and generate keytabs in the KDC.

2.1.2. Hadoop and Kerberos Principals

Each service and sub-service in Hadoop must have its own principal. A **principal** name in a given realm consists of a primary name and an instance name, in this case the instance name is the FQDN of the host that runs that service. As services do not log in with a password to acquire their tickets, their principal's authentication credentials are stored in a **keytab** file, which is extracted from the Kerberos database and stored locally in a secured directory with the service principal on the service component host.



Principals and Keytabs

Principal and Keytab Naming Conventions

Asset	Convention	Example
Principals	<code>\$service_component_name/\$FQDN@EXAMPLE.COM</code>	<code>nn/c6401.ambari.apache.org@EXAMPLE.COM</code>
Keytabs	<code>\$service_component_abbreviation.service.keytab</code>	<code>nn/security/keytabs/nn.service.keytab</code>



Note

In addition to the Hadoop **Service Principals**, Ambari itself also requires a set of **Ambari Principals** to perform service "smoke" checks and alert health checks.

Keytab files for the Ambari, or headless, principals reside on each cluster host, just as keytab files for the service principals.

Notice in the preceding example the primary name for each service principal. These primary names, such as nn or hive for example, represent the NameNode or Hive service, respectively. Each primary name has appended to it the instance name, the FQDN of the host on which it runs. This convention provides a unique principal name for services that run on multiple hosts, like DataNodes and NodeManagers. Adding the host name serves to distinguish, for example, a request from DataNode A from a request from DataNode B. This is important for the following reasons:

- Compromised Kerberos credentials for one DataNode do not automatically lead to compromised Kerberos credentials for all DataNodes.
- If multiple DataNodes have exactly the same principal and are simultaneously connecting to the NameNode, and if the Kerberos authenticator being sent happens to have same timestamps, then the authentication is rejected as a replay request.

2.1.3. Installing and Configuring the KDC

Ambari is able to configure Kerberos in the cluster to work with an existing MIT KDC, or existing Active Directory installation. This section describes the steps necessary to prepare for this integration.



Note

If you do not have an existing KDC (MIT or Active Directory), [install a new MIT KDC](#). Please be aware that installing a KDC on a cluster host **after** installing the Kerberos client may overwrite the krb5.conf file generated by Ambari.

You can choose to have Ambari connect to the KDC and automatically create the necessary Service and Ambari principals, generate and distribute the keytabs (“Automated Kerberos Setup”). Ambari also provides an advanced option to manually configure Kerberos. If you choose this option, you must create the principals, generate and distribute the keytabs. Ambari will not do this automatically (“Manual Kerberos Setup”).

Supported Key Distribution Center (KDC) Versions

- Microsoft Active Directory 2008 and above
- MIT Kerberos v5
- [Use an Existing MIT KDC \[10\]](#)
- [Use an Existing Active Directory \[11\]](#)
- [Use Manual Kerberos Setup \[11\]](#)

2.1.3.1. Use an Existing MIT KDC

To use an existing MIT Kerberos v5 KDC for the cluster, you must prepare the following:

- Ambari Server and cluster hosts have network access to both the KDC and KDC admin hosts.
- KDC administrative credentials are on-hand.

Proceed with [Enabling Kerberos Security in Ambari](#).

2.1.3.2. Use an Existing Active Directory

To use an existing Microsoft Active Directory 2008 and later domain for the cluster with Automated Kerberos Setup, you must prepare the following:

- Ambari Server and cluster hosts have network access to, and be able to resolve the DNS names of, the Domain Controllers.
- Active Directory secure LDAP (LDAPS) connectivity has been configured.
- Active Directory User container for principals has been created and is on-hand. For example, "OU=Hadoop,OU=People,dc=apache,dc=org"
- Active Directory administrative credentials with delegated control of "Create, delete, and manage user accounts" on the previously mentioned User container are on-hand.

Proceed with [Enabling Kerberos Security in Ambari](#).

2.1.3.3. Use Manual Kerberos Setup

To perform Manual Kerberos Setup, you must prepare the following:

- Cluster hosts have network access to the KDC.
- Kerberos client utilities (such as kinit) have been installed on every cluster host.
- The Java Cryptography Extensions (JCE) have been setup on the Ambari Server host and all hosts in the cluster.
- The Service and Ambari Principals will be manually created in the KDC before completing this wizard.
- The keytabs for the Service and Ambari Principals will be manually created and distributed to cluster hosts before completing this wizard.

Proceed with [Enabling Kerberos Security in Ambari](#).

2.1.3.4. (Optional) Install a new MIT KDC

The following gives a very high level description of the KDC installation process. To get more information see specific Operating Systems documentation, such as [RHEL documentation](#), [CentOS documentation](#), or [SLES documentation](#).



Note

Because Kerberos is a time-sensitive protocol, all hosts in the realm must be time-synchronized, for example, by using the Network Time Protocol (NTP).

If the local system time of a client differs from that of the KDC by as little as 5 minutes (the default), the client will not be able to authenticate.

Install the KDC Server

1. Install a new version of the KDC server:

RHEL/CentOS/Oracle Linux

```
yum install krb5-server krb5-libs krb5-workstation
```

SLES

```
zypper install krb5 krb5-server krb5-client
```

Ubuntu/Debian

```
apt-get install krb5-kdc krb5-admin-server
```

2. Using a text editor, open the KDC server configuration file, located by default here:

```
vi /etc/krb5.conf
```

3. Change the [realms] section of this file by replacing the default "kerberos.example.com" setting for the kdc and admin_server properties with the Fully Qualified Domain Name of the KDC server host. In the following example, "kerberos.example.com" has been replaced with "my.kdc.server".

```
[realms]
EXAMPLE.COM = {
    kdc = my.kdc.server
    admin_server = my.kdc.server
}
```



Note

For Ubuntu/Debian, the setup of the default realm for the KDC and KDC Admin hostnames is performed during the KDC server install. You can re-run setup using `dpkg-reconfigure krb5-kdc`. Therefore, Steps 2 and 3 above are not needed for Ubuntu/Debian.

Create the Kerberos Database

- Use the utility `kdb5_util` to create the Kerberos database.

RHEL/CentOS/Oracle Linux

```
kdb5_util create -s
```

SLES

```
kdb5_util create -s
```

Ubuntu/Debian

```
krb5_newrealm
```

Start the KDC

- Start the KDC server and the KDC admin server.

RHEL/CentOS/Oracle Linux 6

```
/etc/rc.d/init.d/krb5kdc start
```

```
/etc/rc.d/init.d/kadmin start
```

RHEL/CentOS/Oracle Linux 7

```
systemctl start krb5kdc
```

```
systemctl start kadmin
```

SLES 11

```
rckrb5kdc start
```

```
rckadmind start
```

Ubuntu/Debian

```
service krb5-kdc restart
```

```
service krb5-admin-server restart
```



Important

When installing and managing your own MIT KDC, it is **very important** to **set up the KDC server to auto-start on boot**. For example:

RHEL/CentOS/Oracle Linux 6

```
chkconfig krb5kdc on
```

```
chkconfig kadmin on
```

RHEL/CentOS/Oracle Linux 7

```
systemctl enable krb5kdc
```

```
systemctl enable kadmin
```

SLES 11

```
chkconfig rckrb5kdc on
```

```
chkconfig rckadmind on
```

Create a Kerberos Admin

Kerberos principals can be created either on the KDC machine itself or through the network, using an "admin" principal. The following instructions assume you are using the

KDC machine and using the `kadmin.local` command line administration utility. Using `kadmin.local` on the KDC machine allows you to create principals without needing to create a separate "admin" principal before you start.



Note

You will need to provide these admin account credentials to Ambari when enabling Kerberos. This allows Ambari to connect to the KDC, create the cluster principals and generate the keytabs.

1. Create a KDC admin by creating an admin principal.

```
kadmin.local -q "addprinc admin/admin"
```

2. Confirm that this admin principal has permissions in the KDC ACL. Using a text editor, open the KDC ACL file:

RHEL/CentOS/Oracle Linux

```
vi /var/kerberos/krb5kdc/kadm5.acl
```

SLES

```
vi /var/lib/kerberos/krb5kdc/kadm5.acl
```

Ubuntu/Debian

```
vi /etc/krb5kdc/kadm5.acl
```

3. Ensure that the KDC ACL file includes an entry so to allow the admin principal to administer the KDC for your specific realm. When using a realm that is different than `EXAMPLE.COM`, **be sure there is an entry for the realm you are using**. If not present, principal creation will fail. For example, for an `admin/admin@HADOOP.COM` principal, you should have an entry:

```
*/admin@HADOOP.COM *
```

4. After editing and saving the `kadm5.acl` file, you must restart the `kadmin` process.

RHEL/CentOS/Oracle Linux 6

```
/etc/rc.d/init.d/kadmin restart
```

RHEL/CentOS/Oracle Linux 7

```
systemctl restart kadmin
```

SLES 11

```
rckadmind restart
```

Ubuntu/Debian

```
service krb5-admin-server restart
```

2.1.4. Enabling Kerberos Security

Whether you choose automated or manual Kerberos setup, Ambari provides a wizard to help with enabling Kerberos in the cluster. This section provides information on preparing Ambari before running the wizard, and the steps to run the wizard.

- [Installing the JCE \[15\]](#)
- [Creating Mappings Between Principals and UNIX Usernames \[56\]](#)
- [Running the Kerberos Security Wizard \[16\]](#)



Important

Prerequisites for enabling Kerberos are having the JCE installed on all hosts on the cluster (including the Ambari Server) and having the Ambari Server host as part of the cluster. This means the Ambari Server host should be running an Ambari Agent.

You should also [create mappings between principals and UNIX user names](#). Creating mappings can help resolve access issues related to case mismatches between principal and local user names.



Note

Ambari Metrics will not be secured with Kerberos unless it is configured for distributed metrics storage. By default, it uses embedded metrics storage and will not be secured as part of the Kerberos Wizard. If you wish to have Ambari Metrics secured with Kerberos, please see [this topic](#) to enable distributed metrics storage prior to running the Kerberos Wizard.

2.1.4.1. Installing the JCE

Before enabling Kerberos in the cluster, you must deploy the Java Cryptography Extension (JCE) security policy files on the Ambari Server and on all hosts in the cluster.



Important

If you are using Oracle JDK, **you must distribute and install the JCE on all hosts** in the cluster, including the Ambari Server. **Be sure to restart Ambari Server after installing the JCE.** If you are using OpenJDK, some distributions of the OpenJDK come with unlimited strength JCE automatically and therefore, installation of JCE is not required.

2.1.4.1.1. Install the JCE

1. On the Ambari Server, obtain the JCE policy file appropriate for the JDK version in your cluster.
 - For Oracle JDK 1.8:
<http://www.oracle.com/technetwork/java/javase/downloads/jce8-download-2133166.html>

- For Oracle JDK 1.7:

<http://www.oracle.com/technetwork/java/javase/downloads/jce-7-download-432124.html>

2. Save the policy file archive in a temporary location.
3. On Ambari Server and on each host in the cluster, add the unlimited security policy JCE jars to `$JAVA_HOME/jre/lib/security/`.

For example, run the following to extract the policy jars into the JDK installed on your host:

```
unzip -o -j -q jce_policy-8.zip -d /usr/jdk64/jdk1.8.0_40/jre/lib/security/
```

4. Restart Ambari Server: `sudo ambari-server restart`.
5. Proceed to [Running the Security Wizard](#).

2.1.4.2. Running the Kerberos Security Wizard

Ambari provides three options for enabling Kerberos:

- Existing MIT KDC
- Existing Active Directory
- Manage Kerberos principals and keytabs manually

When choosing **Existing MIT KDC** or **Existing Active Directory**, the Kerberos Wizard prompts for information related to the KDC, the KDC Admin Account and the Service and Ambari principals. Once provided, Ambari will automatically create principals, generate keytabs and distribute keytabs to the hosts in the cluster. The services will be configured for Kerberos and the service components are restarted to authenticate against the KDC. This is the **Automated Setup** option. See [Launching the Kerberos Wizard \(Automated Setup\)](#) for more details.

When choosing **Manage Kerberos principals and keytabs manually**, you must create the principals, generate and distribute the keytabs. Ambari will not do this automatically. This is the **Manual Setup** option. See [Launching the Kerberos Wizard \(Manual Setup\)](#) for more details.

2.1.4.2.1. Launching the Kerberos Wizard (Automated Setup)

1. Be sure you have [Installed and Configured your KDC](#) and have [prepared the JCE](#) on each host in the cluster.
2. Log in to Ambari Web and Browse to Admin > Kerberos.
3. Click "Enable Kerberos" to launch the wizard.
4. Select the type of KDC you are using and confirm you have met the prerequisites.

5. Provide information about the KDC and admin account.
 - a. (Optional) In the **Domains** field, provide a list of patterns to use to map hosts in the cluster to the appropriate realm. For example, if your hosts have a common domain in their FQDN such as host1.hortonworks.local and host2.hortonworks.local, you would set this to:

```
.hortonworks.local , hortonworks.local
```

- b. (Optional) To manage your Kerberos client krb5.conf manually (and not have Ambari manage the krb5.conf), expand the **Advanced krb5-conf** section and uncheck the "Manage" option. **You must have the krb5.conf configured on each host.**
 - c. (Optional) to configure any additional KDC's to be used for this environment, add an entry for each additional KDC to the **realms** section of the **Advanced krb5-conf's** krb5-conf template.

```
kdc = {{kdc_host}}  
kdc = otherkdc.example.com
```

- d. (Optional) To not have Ambari install the Kerberos client libraries on all hosts, expand the **Advanced kerberos-env** section and uncheck the "Install OS-specific Kerberos client package(s)" option. **You must have the Kerberos client utilities installed on each host.**
 - e. (Optional) If your Kerberos client libraries are in non-standard path locations, expand the **Advanced kerberos-env** section and adjust the "Executable Search Paths" option.
 - f. (Optional) If your KDC has a password policy, expand the **Advanced kerberos-env** section and adjust the Password options.
 - g. (Optional) Ambari will test your Kerberos settings by generating a test principal and authenticating with that principal. To customize the test principal name that Ambari will use, expand the **Advanced kerberos-env** section and adjust the **Test Principal Name** value. By default, the test principal name is a combination of cluster name and date (**\${cluster_name}-\${short_date}**). This test principal **will be deleted** after the test is complete.
 - h. (Optional) If you need to customize the attributes for the principals Ambari will create, when using Active Directory, see the [Customizing the Attribute Template](#) for more information. When using MIT KDC, you can pass **Principal Attribute** options in the **Advanced kerberos-env** section. For example, you can set options related to pre-auth or max. renew life by passing:

```
-requires_preauth -maxrenewlife "7 days"
```

6. Proceed with the install.
7. Ambari will install Kerberos clients on the hosts and test access to the KDC by testing that Ambari can create a principal, generate a keytab and distribute that keytab.
8. Customize the Kerberos identities used by Hadoop and proceed to kerberize the cluster.



Important

On the **Configure Identities** step, be sure to review the principal names, particularly the **Ambari Principals** on the **General** tab. These principal names, by default, append the name of the cluster to each of the Ambari principals. You can leave this as default or adjust these by removing the "`-${cluster-name}`" from principal name string. For example, if your cluster is named HDP and your realm is EXAMPLE.COM, the hdfs principal will be created as hdfs-HDP@EXAMPLE.COM.

9. Confirm your configuration. You can optionally download a CSV file of the principals and keytabs that Ambari will automatically create.

10. Click **Next** to start the process.

11. After principals have been created and keytabs have been generated and distributed, Ambari updates the cluster configurations, then starts and tests the Services in the cluster.



Note

If your cluster includes Storm, after enabling Kerberos, you must also [set up Ambari for Kerberos](#) for Storm Service Summary information to be displayed in Ambari Web. Otherwise, you will see n/a for Storm information such as Slots, Tasks, Executors and Topologies.

12. Exit the wizard when complete.

2.1.4.2.2. Launching the Kerberos Wizard (Manual Setup)

1. Be sure you have [Installed and Configured your KDC](#) and have [prepared the JCE](#) on each host in the cluster.
2. Log in to Ambari Web and Browse to Admin > Kerberos.
3. Click "Enable Kerberos" to launch the wizard.
4. Select the **Manage Kerberos principals and keytabs manually** option and confirm you have met the prerequisites.
5. Provide information about the KDC and admin account.
 - a. If your Kerberos client libraries are in non-standard path locations, expand the **Advanced kerberos-env** section and adjust the "Executable Search Paths" option.
6. Customize the Kerberos identities used by Hadoop and proceed to kerberize the cluster.



Important

On the **Configure Identities** step, be sure to review the principal names, particularly the **Ambari Principals** on the **General** tab. These principal names,

by default, append the name of the cluster to each of the Ambari principals. You can leave this as default or adjust these by removing the "-`{cluster-name}`" from principal name string. For example, if your cluster is named HDP and your realm is EXAMPLE.COM, the hdfs principal will be created as hdfs-HDP@EXAMPLE.COM.

7. Confirm your configuration. Since you have chosen the Manual Kerberos Setup option, obtain the CSV file for the list of principals and keytabs required for the cluster to work with Kerberos. **Do not proceed until you have manually created and distributed the principals and keytabs to the cluster hosts.**
8. Click **Next** to continue.
9. Ambari updates the cluster configurations, then starts and tests the Services in the cluster.
10. Exit the wizard when complete.

2.1.5. Kerberos Client Packages

If you chose to enable Kerberos using the Automated Kerberos Setup option, as part of the enabling Kerberos process, Ambari installs the Kerberos clients on the cluster hosts. Depending on your operating system, the following packages are installed:

Packages installed by Ambari for the Kerberos Client

Operating System	Packages
RHEL/CentOS/Oracle Linux 7	krb5-workstation
RHEL/CentOS/Oracle Linux 6	krb5-workstation
SLES 11	krb5-client
Ubuntu/Debian	krb5-user, krb5-config

2.1.6. Disabling Kerberos Security

After [Enabling Kerberos Security](#), you can disable Kerberos.

1. Log in to Ambari Web and Browse to Admin > Kerberos.
2. Click **Disable Kerberos** to launch the wizard.
3. Complete the wizard.



Note

If you have enabled Kerberos with an Automated Setup option, Ambari will attempt to contact the KDC and remove the principals created by Ambari. If the KDC is unavailable, the wizard will fail on the Unkerberize step. You can choose to ignore and continue the failure but removal of principals from the KDC will not be performed.

2.1.7. Customizing the Attribute Template

If you are using the Kerberos Automated setup with Active Directory, depending on your KDC policies, you can customize the attributes that Ambari sets when creating principals. On the Configure Kerberos step of the wizard, in the **Advanced kerberos-env** section, you have access to the Ambari Attribute Template. This template (which is based on the [Apache Velocity](#) templating syntax) can be modified to adjust which attributes are set on the principals and how those attribute values are derived.

The following table lists the set of computed attribute variables available if you choose to modify the template:

Attribute Variables	Example
\$normalized_principal	nn/c6401.ambari.apache.org@EXAMPLE.COM
\$principal_name	nn/c6401.ambari.apache.org
\$principal_primary	nn
\$principal_digest	[[MD5 hash of the \$normalized_principal]]
\$principal_instance	c6401.ambari.apache.org
\$realm	EXAMPLE.COM
\$password	[[password]]

2.1.8. Managing Admin Credentials

When you enable Kerberos, if you choose to use an **Existing MIT KDC** or **Existing Active Directory**, the Kerberos Wizard prompts for information related to the KDC, the KDC Admin Account credentials and the Service and Ambari principals. Once provided, Ambari will automatically create principals, generate keytabs and distribute keytabs to the hosts in the cluster. The services will be configured for Kerberos and the service components are restarted to authenticate against the KDC. This is the **Kerberos Automated Setup** option.

By default, Ambari will not retain the KDC Admin Account credentials you provide unless you have [encrypted the passwords stored in Ambari](#). If you have not configured Ambari for password encryption, you will be prompted to provide KDC Admin Account credentials whenever cluster changes are made that require KDC principal and/or keytab changes (such as adding services, components and hosts).

If you have configured Ambari for password encryption, you will have an option to Save Admin Credentials. Ambari will use the retained KDC Admin Account credentials to make the KDC changes automatically.

Save Admin Credentials 



Important

If you **do not** have password encryption enabled for Ambari, the Save Admin Credentials option **will not be** enabled.

Updating KDC Credentials

If you have chosen to Save Admin Credentials when enabling Kerberos, you can update or remove the credentials from Ambari using the following:

1. In Ambari Web, browse to **Admin > Kerberos** and click the **Manage KDC Credentials** button. The **Manage KDC Credentials** dialog is displayed.
2. If credentials have been previously saved, click **Remove** to remove the credentials currently stored in Ambari. Once removed, if cluster changes that require KDC principal and/or keytab changes (such as adding services, components and hosts), you will be prompted to enter the KDC Admin Account credentials.
3. Alternatively, to update the KDC Admin Account credentials, enter the Admin principal and password values and click **Save**.

2.2. Configuring Ambari Authentication with LDAP or AD

2.2.1. Configuring Ambari for LDAP or Active Directory Authentication

By default Ambari uses an internal database as the user store for authentication and authorization. If you want to configure LDAP or Active Directory (AD) external authentication, you need to [collect the following information](#) and [run a setup command](#).

Also, you must [synchronize your LDAP users and groups](#) into the Ambari DB to be able to manage authorization and permissions against those users and groups.



Note

When synchronizing LDAP users and groups, Ambari uses LDAP results paging controls to synchronize large numbers of LDAP objects. Most modern LDAP servers support these control, but for those that do not, such as Oracle Directory Server Enterprise Edition 11g, Ambari introduces a configuration parameter to disable pagination. The `authentication.ldap.pagination.enabled` property can be set to `false` in the `/etc/ambari-server/conf/ambari-properties` file to disable result paging controls. This will limit the maximum number of entities that can be imported at any given time to the maximum result limit of the LDAP server. To work around this, import sets of users or groups using the `-users` and `-groups` options covered in [section 3.1.4 - Specific Set of Users and Groups](#).

2.2.1.1. Setting Up LDAP User Authentication

The following table details the properties and values you need to know to set up LDAP authentication.



Note

If you are going to set `bindAnonymously` to `false` (the default), you need to make sure you have an LDAP Manager name and password set up. If you are going to use SSL, you need to make sure you have already set up your certificate and keys.

Ambari Server LDAP Properties

Property	Values	Description
<code>authentication.ldap.primaryUrl</code>	server:port	The hostname and port for the LDAP or AD server. Example: <code>my.ldap.server:389</code>
<code>authentication.ldap.secondaryUrl</code>	server:port	The hostname and port for the secondary LDAP or AD server. Example: <code>my.secondary.ldap.server:389</code> This is an optional value.
<code>authentication.ldap.useSSL</code>	true or false	If true, use SSL when connecting to the LDAP or AD server.
<code>authentication.ldap.usernameAttribute</code>	[LDAP Attribute]	The attribute for username. Example: <code>uid</code>
<code>authentication.ldap.baseDn</code>	[Distinguished Name]	The root Distinguished Name to search in the directory for users. Example: <code>ou=people,dc=hadoop,dc=apache,dc=org</code>
<code>authentication.ldap.referral</code>	[Referral method]	Determines if LDAP referrals should be followed, or ignored.
<code>authentication.ldap.bindAnonymously</code>	true or false	If true, bind to the LDAP or AD server anonymously
<code>authentication.ldap.managerDn</code>	[Full Distinguished Name]	If Bind anonymous is set to false, the Distinguished Name ("DN") for the manager. Example: <code>uid=hdfs,ou=people,dc=hadoop,dc=apache,dc=org</code>
<code>authentication.ldap.managerPassword</code>	[password]	If Bind anonymous is set to false, the password for the manager
<code>authentication.ldap.userObjectClass</code>	[LDAP Object Class]	The object class that is used for users. Example: <code>organizationalPerson</code>
<code>authentication.ldap.groupObjectClass</code>	[LDAP Object Class]	The object class that is used for groups. Example: <code>groupOfUniqueNames</code>
<code>authentication.ldap.groupMembershipAttribute</code>	[LDAP Attribute]	The attribute for group membership. Example: <code>uniqueMember</code>
<code>authentication.ldap.groupNameAttribute</code>	[LDAP attribute]	The attribute for group name.

2.2.1.2. Configure Ambari to use LDAP Server



Note

Only if you are using LDAPS, and the LDAPS server certificate is signed by a trusted Certificate Authority, there is no need to import the certificate into Ambari so this section does not apply to you. If the LDAPS server certificate is self-signed, or is signed by an unrecognized certificate authority such as an internal certificate authority, you must import the certificate and create a keystore file. The following example creates a keystore file at `/keys/ldaps-keystore.jks`, but you can create it anywhere in the file system:

Run the LDAP setup command on the Ambari server and answer the prompts, using the information you collected above:

```
1. mkdir /etc/ambari-server/keys
```

where the keys directory does not exist, but should be created.

```
2. $JAVA_HOME/bin/keytool -import -trustcacerts -alias root -file
   $PATH_TO_YOUR_LDAPS_CERT -keystore /etc/ambari-server/keys/
   ldaps-keystore.jks
```

3. Set a password when prompted. You will use this during `ambari-server setup-ldap`.

```
ambari-server setup-ldap
```

1. At the `Primary URL*` prompt, enter the server URL and port you collected above. Prompts marked with an asterisk are required values.
2. At the `Secondary URL*` prompt, enter the secondary server URL and port. This value is optional.
3. At the `Use SSL*` prompt, enter your selection. **If using LDAPS**, enter `true`.
4. At the `User object class*` prompt, enter the object class that is used for users.
5. At the `User name attribute*` prompt, enter your selection. The default value is `uid`.
6. At the `Group object class*` prompt, enter the object class that is used for groups.
7. At the `Group name attribute*` prompt, enter the attribute for group name.
8. At the `Group member attribute*` prompt, enter the attribute for group membership.
9. At the `Distinguished name attribute*` prompt, enter the attribute that is used for the distinguished name.
10. At the `Base DN*` prompt, enter your selection.
11. At the `Referral method*` prompt, enter to follow or ignore LDAP referrals.
12. At the `Bind anonymously*` prompt, enter your selection.
13. At the `Manager DN*` prompt, enter your selection if you have set **bind.Anonymously** to false.
14. At the `Enter the Manager Password*` prompt, enter the password for your LDAP manager DN.
15. If you set `Use SSL* = true` in step 3, the following prompt appears: Do you want to provide custom TrustStore for Ambari?

Consider the following options and respond as appropriate.

- **More secure option:** If using a self-signed certificate that you do not want imported to the existing JDK keystore, enter `y`.

For example, you want this certificate used only by Ambari, not by any other applications run by JDK on the same host.

If you choose this option, additional prompts appear. Respond to the additional prompts as follows:

- At the `TrustStore` type prompt, enter `jks`.
- At the `Path to TrustStore file` prompt, enter `/keys/ldaps-keystore.jks` (or the actual path to your keystore file).
- At the `Password for TrustStore` prompt, enter the password that you defined for the keystore.
- **Less secure option:** If using a self-signed certificate that you want to import and store in the existing, default JDK keystore, enter `n`.
- Convert the SSL certificate to X.509 format, if necessary, by executing the following command:

```
openssl x509 -in slapd.pem -out <slapd.crt>
```

Where `<slapd.crt>` is the path to the X.509 certificate.

- Import the SSL certificate to the existing keystore, for example the default `jre` certificates storage, using the following instruction:

```
/usr/jdk64/jdk1.7.0_45/bin/keytool -import -trustcacerts -file slapd.crt -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

Where Ambari is set up to use JDK 1.7. Therefore, the certificate must be imported in the JDK 7 keystore.

16. Review your settings and if they are correct, select `y`.

17. Start or restart the Server

```
ambari-server restart
```

The users you have just imported are initially granted the Ambari User privilege. Ambari Users can read metrics, view service status and configuration, and browse job information. For these new users to be able to start or stop services, modify configurations, and run smoke tests, they need to be Admins. To make this change, as an Ambari Admin, use `Manage Ambari > Users > Edit`. For instructions, see [Managing Users and Groups](#).

2.2.1.2.1. Example Active Directory Configuration

Directory Server implementations use specific object classes and attributes for storing identities. In this example, configurations specific to Active Directory are displayed as an example. Only those properties that are specific to Active Directory are displayed.

Run `ambari-server setup-ldap` and provide the following information about your Domain.

Prompt	Example AD Values
User object class* (<code>posixAccount</code>)	<code>user</code>
User name attribute* (<code>uid</code>)	<code>sAMAccountName</code>

Prompt	Example AD Values
Group object class* (posixGroup)	group
Group member attribute* (memberUid)	member
Distinguished name attribute* (dn)	distinguishedName

2.2.1.3. Synchronizing LDAP Users and Groups

Run the LDAP synchronize command and answer the prompts to initiate the sync:

```
ambari-server sync-ldap [option]
```



Note

To perform this operation, your Ambari Server must be running.

- When prompted, you must provide credentials for an Ambari Admin.
- When syncing ldap, Local user accounts with matching username will switch to LDAP type, which means their authentication will be against the external LDAP and not against the Local Ambari user store.
- LDAP sync only syncs up-to-1000 users. If your LDAP contains over 1000 users and you plan to import over 1000 users, you must use the `--users` option when syncing and specify a filtered list of users to perform import in batches.

The utility provides three options for synchronization:

- Specific set of users and groups, or
- Synchronize the existing users and groups in Ambari with LDAP, or
- All users and groups

Review log files for failed synchronization attempts, at `/var/log/ambari-server/ambari-server.log` on the Ambari Server host.



Note

When synchronizing LDAP users and groups, Ambari uses LDAP results paging controls to synchronize large numbers of LDAP objects. Most modern LDAP servers support these control, but for those that do not, such as Oracle Directory Server Enterprise Edition 11g, Ambari introduces a configuration parameter to disable pagination. The `authentication.ldap.pagination.enabled` property can be set to `false` in the `/etc/ambari-server/conf/ambari-properties` file to disable result paging controls. This will limit the maximum number of entities that can be imported at any given time to the maximum result limit of the LDAP server. To work around this, import sets of users or groups using the `--users` and `--groups` options covered in [section 3.1.4 - Specific Set of Users and Groups](#).

2.2.1.4. Specific Set of Users and Groups

```
ambari-server sync-ldap --users users.txt --groups groups.txt
```

Use this option to synchronize a specific set of users and groups from LDAP into Ambari. Provide the command a text file of comma-separated users and groups. The comma separated entries in each of these files should be based off of the values in LDAP of the attributes chosen during setup. The "User name attribute" should be used for the users.txt file, and the "Group name attribute" should be used for the groups.txt file. This command will find, import, and synchronize the matching LDAP entities with Ambari.



Note

Group membership is determined using the Group Membership Attribute (groupMembershipAttr) specified during setup-ldap. User name is determined by using the Username Attribute (usernameAttribute) specified during setup-ldap.

2.2.1.5. Existing Users and Groups

```
ambari-server sync-ldap --existing
```

After you have performed a synchronization of a [specific set of users and groups](#), you use this option to synchronize only those entities that are in Ambari with LDAP. Users will be removed from Ambari if they no longer exist in LDAP, and group membership in Ambari will be updated to match LDAP.



Note

Group membership is determined using the Group Membership Attribute specified during setup-ldap.

2.2.1.6. All Users and Groups



Important

Only use this option if you are sure you want to synchronize all users and groups from LDAP into Ambari. If you only want to synchronize a subset of users and groups, use a [specific set of users and groups](#) option.

```
ambari-server sync-ldap --all
```

This will import all entities with matching LDAP user and group object classes into Ambari.

2.2.2. Configuring Ranger Authentication with UNIX, LDAP, or AD

2.2.2.1. UNIX Authentication Settings

The following figure shows the UNIX authentication settings, and the table below describes each of these properties.

Add Service Wizard

Ranger Settings

External URL:

Authentication method:

- LDAP
- ACTIVE_DIRECTORY
- UNIX
- NONE

HTTP enabled:

Unix Authentication Settings

Allow remote Login:

ranger.unixauth.service.hostname:

ranger.unixauth.service.port:

Knox SSO Settings

Advanced ranger-admin-site

Table 2.1. UNIX Authentication Settings

Configuration Property
Allow remote Login
ranger.unixauth.service.hostname
ranger.unixauth.service.port

2.2.2.2. Active Directory Authentication Settings

This section describes how to configure settings for Active Directory authentication.



Note

In addition to these settings, you may also need to configure the Active Directory properties described in Configuring Usersync Settings.

2.2.2.2.1. AD Settings

The following figure shows the Active Directory (AD) authentication settings, and the table below describes each of these properties.




Table 2.2. Active Directory Authentication Settings

Configuration Property Name	Description	Default Value	Example Value	Required?
ranger.ldap.ad.domain	Server domain name (or IP address) where ranger-usersync module is running (along with the AD Authentication Service). The default value of "localhost" must be changed to the domain name.	localhost	example.com	Yes, if Active Directory authentication is selected.
ranger.ldap.ad.url	The URL and port number where ranger-usersync module is running the AD Authentication Service. The default value is a placeholder and must be changed to point to the AD server.	ldap://ad.xasecure.net:389	ldap://127.0.0.1:389	Yes, if Active Directory authentication is selected.

2.2.2.2.2. Custom ranger-admin-site Settings for Active Directory (Optional)

The following Custom ranger-admin-site settings for Active Directory authentication are optional.

To add a Custom ranger-admin-site property:

1. Select **Custom ranger-admin-site**, then click **Add Property**.

The screenshot displays a configuration interface for Ranger. At the top, the 'AD Settings' section is expanded, showing two properties: 'ranger.idap.ad.domain' with the value 'localhost' and 'ranger.idap.ad.url' with the value 'ldap://ad.xasecure.net:389'. Below this, several other settings are collapsed, including 'LDAP Settings', 'Advanced ranger-admin-site', 'Advanced ranger-env', 'Advanced ranger-ugsync-site', 'Custom admin-properties', 'Custom ranger-admin-site', 'Custom ranger-site', 'Custom ranger-ugsync-site', and 'Custom usersync-properties'. The 'Custom ranger-admin-site' section is expanded, and the 'Add Property ...' button is highlighted with a red rectangle.

2. On the Add Property pop-up, type the property name in the **Key** box, type the property value in the **Value** box, then click **Add**.

Add Property

Type: ranger-site.xml

Key: ranger.ldap.ad.base.dn

Value: dc=example,dc=com

Cancel Add

The following figure shows the Custom ranger-admin-site settings required for Active Directory (AD) authentication, and the table below describes each of these properties.

Custom ranger-site

ranger.ldap.ad.base.dn: dc=example,dc=com

ranger.ldap.ad.bind.dn: cn=adadmin,cn=Users,dc=example,dc=com

ranger.ldap.ad.bind.password: secret123!

ranger.ldap.ad.referral: follow

Add Property ...

Table 2.3. Active Directory Custom ranger-admin-site Settings

Custom Property Name	Sample Values for AD Authentication
ranger.ldap.ad.base.dn	dc=example,dc=com
ranger.ldap.ad.bind.dn	cn=adadmin,cn=Users,dc=example,dc=com
ranger.ldap.ad.bind.password	secret123!
ranger.ldap.ad.referral	follow ignore throw

There are three possible values for `ranger.ldap.ad.referral`: `follow`, `throw`, and `ignore`. The recommended setting is `follow`.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

- When this property is set to `follow`, the AD service provider processes all of the normal entries first, and then follows the continuation references.

- When this property is set to `throw`, all of the normal entries are returned in the enumeration first, before the `ReferralException` is thrown. By contrast, a "referral" error response is processed immediately when this property is set to `follow` or `throw`.
- When this property is set to `ignore`, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search. In the case of AD, a `PartialResultException` is returned when referrals are encountered while search results are processed.

2.2.2.3. LDAP Authentications Settings

This section describes how to configure LDAP and Advanced ranger-ugsync-site settings for Active Directory authentication.



Note

In addition to these settings, you must also configure the LDAP properties described in [Configuring Usersync Settings](#).

2.2.2.3.1. LDAP Settings

The following figure shows the LDAP authentication settings, and the table below describes each of these properties.




Table 2.4. LDAP Authentication Settings

Configuration Property Name	Description	Default Value	Example Value	Required?
ranger.ldap.url	The URL and port number where ranger-usersync module is running the LDAP Authentication Service.	ldap://71.127.43.33:389	ldap://127.0.0.1:389	Yes, if LDAP authentication is selected.
ranger.ldap.user.dnpattern	The domain name pattern.	uid={0},ou=users,dc=xasecure,dc=net	cn=ldapadmin,ou=Users,dc=example,dc=com	Yes, if LDAP authentication is selected.
ranger.ldap.group.roleattribute	The LDAP group role attribute.	cn	cn	Yes, if LDAP authentication is selected.

2.2.2.3.2. Custom ranger-admin-site Settings for LDAP (Optional)

The following Custom ranger-admin-site settings for LDAP are optional.

To add a Custom ranger-admin-site property:

1. Select **Custom ranger-admin-site**, then click **Add Property**.

The screenshot shows the Ranger Admin console interface. At the top, there is a section for 'AD Settings' with two input fields: 'ranger ldap.ad.domain' containing 'localhost' and 'ranger ldap.ad.url' containing 'ldap://ad.xasecure.net:389'. Below this are several expandable sections: 'LDAP Settings', 'Advanced ranger-admin-site', 'Advanced ranger-env', 'Advanced ranger-ugsync-site', 'Custom admin-properties', 'Custom ranger-admin-site', 'Custom ranger-site', 'Custom ranger-ugsync-site', and 'Custom usersync-properties'. The 'Custom ranger-admin-site' section is expanded, and the 'Add Property ...' button is highlighted with a red rectangular box.

2. On the Add Property pop-up, type the property name in the **Key** box, type the property value in the **Value** box, then click **Add**.

Add Property

Type: ranger-admin-site.xml

Key: ranger.ldap.base.dn

Value: dc=example,dc=com

Buttons: Cancel, Add

The following figure shows the Custom ranger-admin-site settings required for LDAP authentication, and the table below describes each of these properties.

Custom ranger-site

ranger.ldap.ad.base.dn: dc=example,dc=com

ranger.ldap.ad.bind.dn: cn=adadmin,cn=Users,dc=example,dc=com

ranger.ldap.ad.bind.password: secret123!

ranger.ldap.ad.referral: follow

Add Property ...

Table 2.5. LDAP Custom ranger-admin-site Settings

Custom Property Name	Sample Values for AD or LDAP Authentication
ranger.ldap.base.dn	dc=example,dc=com
ranger.ldap.bind.dn	cn=adadmin,cn=Users,dc=example,dc=com
ranger.ldap.bind.password	secret123!
ranger.ldap.referral	follow ignore throw

There are three possible values for `ranger.ldap.referral`: `follow`, `throw`, and `ignore`. The recommended setting is `follow`.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

- When this property is set to `follow`, the LDAP service provider processes all of the normal entries first, and then follows the continuation references.
- When this property is set to `throw`, all of the normal entries are returned in the enumeration first, before the `ReferralException` is thrown. By contrast, a "referral" error response is processed immediately when this property is set to `follow` or `throw`.
- When this property is set to `ignore`, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search.

2.2.2.3.3. Advanced ranger-admin-site Settings

The following Advanced ranger-admin-site properties apply only to LDAP authentication.

Table 2.6. Active Directory Authentication Settings

Property Name	Sample values for LDAP Authentication
<code>ranger.ldap.group.searchbase</code>	<code>dc=example,dc=com</code>
<code>ranger.ldap.group.searchfilter</code>	<code>(member=cn={0},ou=Users,dc=example,dc=com)</code>

2.2.3. Encrypting Database and LDAP Passwords in Ambari

By default the passwords to access the Ambari database and the LDAP server are stored in a plain text configuration file. To have those passwords encrypted, you need to run a special setup command.

Ambari Server should not be running when you do this: either make the edits before you start Ambari Server the first time or bring the server down to make the edits.

1. On the Ambari Server, run the special setup command and answer the prompts:

```
ambari-server setup-security
```

- a. Select Option 2: Choose one of the following options:

- [1] Enable HTTPS for Ambari server.
- [2] Encrypt passwords stored in `ambari.properties` file.
- [3] Setup Ambari kerberos JAAS configuration.

- b. Provide a master key for encrypting the passwords. You are prompted to enter the key twice for accuracy.

If your passwords are encrypted, you need access to the master key to start Ambari Server.

- c. You have three options for maintaining the master key:

- Persist it to a file on the server by pressing `y` at the prompt.
- Create an environment variable `AMBARI_SECURITY_MASTER_KEY` and set it to the key.

- Provide the key manually at the prompt on server start up.

d. Start or restart the Server

```
ambari-server restart
```

2.2.3.1. Reset Encryption

There may be situations in which you want to:

- [Remove Encryption Entirely \[36\]](#)
- [Change the current master key](#), either because the key has been forgotten or because you want to change the current key as a part of a security routine.

Ambari Server should not be running when you do this.

2.2.3.2. Remove Encryption Entirely

To reset Ambari database and LDAP passwords to a completely unencrypted state:

1. On the Ambari host, open `/etc/ambari-server/conf/ambari.properties` with a text editor and set this property

```
security.passwords.encryption.enabled=false
```

2. Delete `/var/lib/ambari-server/keys/credentials.jceks`
3. Delete `/var/lib/ambari-server/keys/master`
4. You must now reset the database password and, if necessary, the LDAP password. Run [ambari-server setup](#) and [ambari-server setup-ldap](#) again.

2.2.3.3. Change the Current Master Key

To change the master key:

- **If you know the current master key or if the current master key has been persisted:**

1. Re-run the encryption setup command and follow the prompts.

```
ambari-server setup-security
```

a. Select Option 2: Choose one of the following options:

- [1] Enable HTTPS for Ambari server.
- [2] Encrypt passwords stored in `ambari.properties` file.
- [3] Setup Ambari kerberos JAAS configuration.

b. Enter the current master key when prompted if necessary (if it is not persisted or set as an environment variable).

c. At the `Do you want to reset Master Key` prompt, enter `yes`.

d. At the prompt, enter the new master key and confirm.

- If you do **not** know the current master key:
 - Remove encryption entirely, as described [here](#).
 - Re-run `ambari-server setup-security` as described [here](#).
 - Start or restart the Ambari Server.

```
ambari-server restart
```

2.3. Configuring LDAP Authentication in Hue

You can configure Hue to authenticate users by using LDAP, including importing users and groups from the LDAP directory service, OpenLDAP, or through Active Directory (AD).

Integrating Hue with LDAP enables users to leverage existing authentication credentials' group permissions directly from their LDAP profiles.

For you to configure LDAP authentication in Hue, Hue must be running and the Hue UI must be accessible.

Each of the following subsections describes a property that needs to be setup for Hue to work with LDAP.

2.3.1. Enabling the LDAP Backend

To use LDAP, you must specify the following Hue values in the Hue configuration file, `/etc/hue/conf/hue.ini`. Specifying this configuration enables Hue to validate login credentials against the LDAP directory service:

```
[desktop]
  [[auth]]
    .....
    .....
    backend=desktop.auth.backend.LdapBackend
    .....
```

2.3.2. Enabling User Authentication with Search Bind

Settings related to LDAP are in the LDAP section of the Hue configuration file, `/etc/hue/conf/hue.ini`:

```
[desktop]
  [[ldap]]
```

There are two ways to authenticate users by using the LDAP directory service in Hue:

- Search Bind (default)

Setting the `search_bind_authentication` property to `true` in `/etc/hue/conf/hue.ini` enables LDAP search using the bind credentials specified for the `bind_dn` and `bind_password` properties.

Search bind performs an LDAP search against the directory service and then binds the results by using the found Distinguished Name (DN) and provided password. The search process starts from the base DN specified for the `base_dn` property and continues to search the base DN for an entry with an attribute that matches the specified in `user_name_attr` of the username provided at login.

You can restrict the results of this search process by using the `user_filter` (default value `objectclass=*`) and `user_name_attr` (default value `sAMAccountName`) properties in the `[desktop] > [[ldap]] > [[[users]]]` section of `/etc/hue/conf/hue.ini`.

If you use the default values of `user_filter` and `user_name_attr`, the LDAP search filter appears as follows, where `<username>` is the the user name provided on the Hue login page:

```
(&(objectClass=*)(sAMAccountName=<username>))
```

- Direct Bind

Setting the `search_bind_authentication` property to `false` in `/etc/hue/conf/hue.ini` enables the LDAP direct bind mechanism to authenticate users. Hue binds to the LDAP server using the user name and password provided on the login page.

Depending on the value of the `nt_domain` property, there are two ways that direct bind works:

- If `nt_domain` is specified, the `nt_domain` property is intended to be used only with Active Directory (AD) service.

This property allows Hue to authenticate with AD without having to follow LDAP references to other partitions.

Hue forms the User Principal Name (UPN) as a concatenation of the user name provided on the Hue login page and the `nt_domain` property value: for example, `<username>@<nt_domain>`. The `ldap_username_pattern` property is ignored.

- If `nt_domain` is not specified, the `nt_domain` property is intended to be used for all other directory services.

Without the `nt_domain` property specified, the `ldap_username_pattern` appears as follows, where `<username>` is the user name provided on the Hue login page:

```
uid=<username>,ou=People,dc=mycompany,dc=com
```

2.3.3. Setting the Search Base to Find Users and Groups

You must set the correct `base_dn` value in the `/etc/hue/conf/hue.ini` file to enable Hue to find users and groups:

```
# The search base for finding users and groups
base_dn="DC=mycompany,DC=com"
```

2.3.4. Specifying the URL of the LDAP Server

Specify the following URL in the `/etc/hue/conf/hue.ini` file to specify the endpoint of the corporate LDAP server:

```
# URL of the LDAP server
ldap_url=ldap://auth.mycompany.com
```

2.3.5. Specifying LDAPS and StartTLS Support

LDAPS (secure communication with LDAP) is provided using the SSL/TLS and StartTLS protocols. Using these protocols allows Hue to validate the directory service with which it is going to interact. Optionally, specify the path to the certificate for authentication over TLS in the `/etc/hue/conf/hue.ini` file:

```
# A PEM-format file containing certificates for the CA's that
# Hue will trust for authentication over TLS.
# The certificate for the CA that signed the
# LDAP server certificate must be included among these certificates.
# See more here http://www.openldap.org/doc/admin24/tls.html.
ldap_cert=<path/to/cert/file
use_start_tls=true
```

2.3.6. Specifying Bind Credentials for LDAP Searches

If the LDAP server does not support anonymous searches, you must specify the distinguished name of the user to bind and the bind password in the `/etc/hue/conf/hue.ini` file:

```
# Distinguished name of the user to bind as -- not necessary if the LDAP
server
# supports anonymous searches
bind_dn="CN=ServiceAccount,DC=mycompany,DC=com"

# Password of the bind user -- not necessary if the LDAP server supports
# anonymous searches
bind_password=your_password
```

2.3.7. Synchronizing Users and Groups

You can use the LDAP username pattern to restrict users when performing searches. Using this pattern provides a template for the DN that is sent to the directory service when authenticating. Replace the `<username>` parameter with the user name provided on the Hue login page. Specify this pattern in the `/etc/hue/conf/hue.ini` file:

```
# Pattern for searching for usernames -- Use <username> for the parameter
# For use when using LdapBackend for Hue authentication
ldap_username_pattern="uid=<username>,ou=People,dc=mycompany,dc=com"
```


When performing the authentication, Hue must import users to its database to work properly. In this case, passwords are never imported.

By default, the LDAP authentication backend automatically creates users that do not exist in Hue database. The purpose of disabling the automatic import process is to allow only a predefined list of manually imported users to log in.

```
# Create users in Hue when they try to login with their LDAP credentials
# For use when using LdapBackend for Hue authentication
create_users_on_login = true
```

You can specify that user groups be synchronized when a user logs in (to keep the user permission up to date):

```
# Synchronize a users groups when they login
sync_groups_on_login=false
```

You can configure Hue to ignore username lettercasing or to force lowercasing:

```
# Ignore the case of usernames when searching for existing users in Hue.
ignore_username_case=false

# Force usernames to lowercase when creating new users from LDAP.
force_username_lowercase=false
```

2.3.8. Setting Search Bind Authentication and Importing Users and Groups

Hue uses search bind authentication by default. To enable direct bind authentication, set the `search_bind_authentication` property to `false` in the `/etc/hue/conf/hue.ini` file:

```
# Do not use search bind authentication.
search_bind_authentication=false
```

When you set search bind authentication and you also need to set the kind of subgrouping and referrals for users and groups in the `/etc/hue/conf/hue.ini` file:

```
# Choose which kind of subgrouping to use: nested or subordinate(deprecated).
subgroups=subordinate

# Define the number of levels to search for nested members.
nested_members_search_depth=10

# Whether or not to follow referrals
follow_referrals=false
```

2.3.9. Setting LDAP Users' Filter

You can restrict user access by setting the LDAP filter (`user_filter` attribute) and the username attribute in the LDAP schema (`user_name_attr` attribute) in the `/etc/hue/conf/hue.ini` file. The typical attributes for search in the LDAP schema are `uid` and `SAMAccountName`:

```
[[[users]]]

# Base filter for searching for users
user_filter="objectclass=*"

# The username attribute in the LDAP schema
user_name_attr=sAMAccountName
```

2.3.10. Setting an LDAP Groups Filter

You can restrict the synchronization of LDAP directory groups when using the Hue useradmin application by setting a base filter (`group_filter` attribute) and the username attribute in the LDAP schema (`group_name_attr` attribute) of the `/etc/hue/conf/hue.ini` file:

```
[[[groups]]]

# Base filter for searching for groups
group_filter="objectclass=*"

# The username attribute in the LDAP schema
group_name_attr=cn
```

2.3.11. Setting Multiple LDAP Servers

Hue enables you to configure multiple LDAP servers by providing the multiple server declaration in `/etc/hue/conf/hue.ini`:

```
[[[ldap_servers]]]

[[[[mycompany]]]]

# The search base for finding users and groups
base_dn="DC=mycompany,DC=com"

# URL of the LDAP server
ldap_url=ldap://auth.mycompany.com

# A PEM-format file containing certificates for the CA's that
# Hue will trust for authentication over TLS.
# The certificate for the CA that signed the
# LDAP server certificate must be included among these certificates.
# See more here http://www.openldap.org/doc/admin24/tls.html.
## ldap_cert=
## use_start_tls=true

# Distinguished name of the user to bind as -- not necessary if the LDAP
server
# supports anonymous searches
bind_dn="CN=ServiceAccount,DC=mycompany,DC=com"

# Password of the bind user -- not necessary if the LDAP server supports
# anonymous searches
bind_password=your_password

# Pattern for searching for usernames -- Use <username> for the parameter
```

```
# For use when using LdapBackend for Hue authentication
ldap_username_pattern="uid=<username>,ou=People,dc=mycompany,dc=com"

# Whether or not to follow referrals
## follow_referrals=false

[[[[[users]]]]]

# Base filter for searching for users
user_filter="objectclass=Person"

# The username attribute in the LDAP schema
user_name_attr=sAMAccountName

[[[[[groups]]]]]

# Base filter for searching for groups
group_filter="objectclass=groupOfNames"

# The username attribute in the LDAP schema
group_name_attr=cn
```

2.4. Advanced Security Options for Ambari

This section describes several security options for an Ambari-monitored-and-managed Hadoop cluster.

- [Configuring Ambari for Non-Root \[42\]](#)
- [Optional: Ambari Web Inactivity Timeout \[45\]](#)
- [Set Up Kerberos for Ambari Server \[46\]](#)
- [Optional: Set Up Two-Way SSL Between Ambari Server and Ambari Agents \[47\]](#)
- [Optional: Configure Ciphers and Protocols for Ambari Server \[47\]](#)
- [Optional: HTTP Cookie Persistence \[47\]](#)

2.4.1. Configuring Ambari for Non-Root

In most secure environments, restricting access to and limiting services that run as root is a hard requirement. For these environments, Ambari can be configured to operate without direct root access. Both Ambari Server and Ambari Agent components allow for non-root operation, and the following sections will walk you through the process.

- [How to Configure Ambari Server for Non-Root \[42\]](#)
- [How to Configure an Ambari Agent for Non-Root \[43\]](#)

2.4.1.1. How to Configure Ambari Server for Non-Root

You can configure the Ambari Server to run as a non-root user.

During the [ambari-server setup](#) process, when prompted to Customize user account for ambari-server daemon?, choose y.

The setup process prompts you for the appropriate, non-root user to run the Ambari Server as; for example: `ambari`.



Note

The non-root user you choose to run the Ambari Server should be part of the Hadoop group. This group must match the service Hadoop group accounts referenced in the Customize Services > Misc tab during the Install Wizard configuration step. The default group name is `hadoop` but if you customized this value during cluster install, be sure to make the non-root user a part of that group. See [Customizing HDP Services](#) for more information on service account users and groups.



Note

If Ambari Server is running as a non-root user, such as 'ambari', and you are planning on using Ambari Views, the following properties in **Services > HDFS > Configs > Advanced core-site** must be added:

```
hadoop.proxyuser.ambari.groups=*
hadoop.proxyuser.ambari.hosts=*
```

2.4.1.2. How to Configure an Ambari Agent for Non-Root

You can configure the Ambari Agent to run as a non-privileged user as well. That user requires specific sudo access in order to su to Hadoop service accounts and perform specific privileged commands. Configuring Ambari Agents to run as non-root requires that you manually install agents on all nodes in the cluster. For these details, see [Installing Ambari Agents Manually](#). After installing each agent, you must configure the agent to run as the desired, non-root user. In this example we will use the `ambari` user.

Change the `run_as_user` property in the `/etc/ambari-agent/conf/ambari-agent.ini` file, as illustrated below:

```
run_as_user=ambari
```

Once this change has been made, the `ambari-agent` must be restarted to begin running as the non-root user.

The non-root functionality relies on sudo to run specific commands that require elevated privileges as defined in the [Sudoer Configuration](#). The sudo configuration is split into three sections: [Customizable Users](#), [Non-Customizable Users, Commands](#), and [Sudo Defaults](#).

2.4.1.2.1. Sudoer Configuration

The [Customizable Users](#), [Non-Customizable Users, Commands](#), and [Sudo Defaults](#) sections will cover how sudo should be configured to enable Ambari to run as a non-root user. Each of the sections includes the specific sudo entries that should be placed in `/etc/sudoers` by running the `visudo` command.

2.4.1.2.2. Customizable Users

This section contains the `su` commands and corresponding Hadoop service accounts that are configurable on install:

```
# Ambari Customizable Users
ambari ALL=(ALL) NOPASSWD:SETENV: /bin/su hdfs *,/bin/su ambari-qa *,/bin/su
ranger *,/bin/su zookeeper *,/bin/su Knox *,/bin/su falcon *,/bin/su ams *,
/bin/su flume *,/bin/su hbase *,/bin/su spark *,/bin/su accumulo *,/bin/su
hive *,/bin/su hcat *,/bin/su kafka *,/bin/su mapred *,/bin/su oozie *,/bin/
su sqoop *,/bin/su storm *,/bin/su tez *,/bin/su atlas *,/bin/su yarn *,/bin/
su kms *
```



Note

These user accounts must match the service user accounts referenced in the **Customize Services > Misc** tab during the Install Wizard configuration step. For example, if you customize YARN to run as `xyz_yarn`, modify the `su` command above to be `/bin/su xyz_yarn`.

These user accounts must match the service user accounts referenced in the **Customize Services > Misc** tab during the Install Wizard configuration step. For example, if you customize YARN to run as `xyz_yarn`, modify the `su` command above to be `/bin/su xyz_yarn`.

2.4.1.2.3. Non-Customizable Users

This section contains the `su` commands for the system accounts that cannot be modified, and is **only required** if you are using the Ambari-installed-and-managed MySQL instance for the Hive Metastore. If you choose to use an existing MySQL, PostgreSQL or Oracle database for the Hive Metastore, you do not need to include this sudoer command.

```
# Ambari Non-Customizable Users
ambari ALL=(ALL) NOPASSWD:SETENV: /bin/su mysql *
```

2.4.1.2.4. Commands

This section contains the specific commands that must be issued for standard agent operations:

```
# Ambari Commands
ambari ALL=(ALL) NOPASSWD:SETENV: /usr/bin/yum,/usr/bin/zypper,/usr/bin/apt-
get, /bin/mkdir, /usr/bin/test, /bin/ln, /bin/chown, /bin/chmod, /bin/chgrp,
/usr/sbin/groupadd, /usr/sbin/groupmod, /usr/sbin/useradd, /usr/sbin/usermod,
/bin/cp, /usr/sbin/setenforce, /usr/bin/test, /usr/bin/stat, /bin/mv, /bin/
sed, /bin/rm, /bin/kill, /bin/readlink, /usr/bin/pgrep, /bin/cat, /usr/bin/
unzip, /bin/tar, /usr/bin/tee, /bin/touch, /usr/bin/hdp-select, /usr/bin/
conf-select, /usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh, /usr/lib/
hadoop/bin/hadoop-daemon.sh, /usr/lib/hadoop/sbin/hadoop-daemon.sh, /sbin/
chkconfig gmond off, /sbin/chkconfig gmetad off, /etc/init.d/httpd *, /sbin/
service hdp-gmetad start, /sbin/service hdp-gmond start, /usr/sbin/gmond, /
usr/sbin/update-rc.d ganglia-monitor *, /usr/sbin/update-rc.d gmetad *, /etc/
init.d/apache2 *, /usr/sbin/service hdp-gmond *, /usr/sbin/service hdp-gmetad
*, /sbin/service mysqld *, /usr/bin/python2.6 /var/lib/ambari-agent/data/tmp/
validateKnoxStatus.py *, /usr/hdp/current/knox-server/bin/knoxcli.sh *, /usr/
bin/dpkg *, /bin/rpm *, /usr/sbin/hst *
```

```
# Ambari Ranger Commands
ambari ALL=(ALL) NOPASSWD:SETENV: /usr/hdp/*/ranger-usersync/setup.sh, /usr/
bin/ranger-usersync-stop, /usr/bin/ranger-usersync-start, /usr/hdp/*/ranger-
admin/setup.sh *, /usr/hdp/*/ranger-knox-plugin/disable-knox-plugin.sh *, /
usr/hdp/*/ranger-storm-plugin/disable-storm-plugin.sh *, /usr/hdp/*/ranger-
```

```
hbase-plugin/disable-hbase-plugin.sh *, /usr/hdp/*/ranger-hdfs-plugin/disable-  
hdfs-plugin.sh *, /usr/hdp/current/ranger-admin/ranger_credential_helper.py,  
/usr/hdp/current/ranger-kms/ranger_credential_helper.py, /usr/hdp/*/ranger-*/  
ranger_credential_helper.py
```



Important

Do not modify the command lists, only the usernames in the [Customizable Users](#) section may be modified.

To re-iterate, you must do this sudo configuration on every node in the cluster. To ensure that the configuration has been done properly, you can su to the ambari user and run sudo -l. There, you can double check that there are no warnings, and that the configuration output matches what was just applied.

2.4.1.2.5. Sudo Defaults

Some versions of sudo have a default configuration that prevents sudo from being invoked from a non-interactive shell. In order for the agent to run its commands non-interactively, some defaults need to be overridden.

```
Defaults exempt_group = ambari  
Defaults !env_reset,env_delete==PATH  
Defaults: ambari !requiretty
```

To re-iterate, this sudo configuration must be done on every node in the cluster. To ensure that the configuration has been done properly, you can su to the ambari user and run sudo -l. There, you can double-check that there are no warnings, and that the configuration output matches what was just applied.

2.4.2. Optional: Ambari Web Inactivity Timeout

Ambari is capable of automatically logging a user out of Ambari Web after a period of inactivity. After a configurable amount of time, the user's session will be terminated and they will be redirected to the login page.

This capability can be separately configured for Operators and Read-Only users. This allows you to distinguish a read-only user (useful when Ambari Web is used as a monitoring dashboard) from other operators. Alternatively, you can set both inactivity timeout values to be the same so that regardless of the user type, automatic logout will occur after a set period of time.

By default, the Ambari Web inactivity timeout is not enabled (i.e. is set to 0). The following instructions should be used to enable inactivity timeout and set as the amount of time in seconds before users are automatically logged out.

Ensure the Ambari Server is completely stopped before making changes to the inactivity timeout. Either make these changes before you start Ambari Server the first time, or bring the server down before making these changes.

1. On the Ambari Server host, open

```
/etc/ambari-server/conf/ambari.properties with a text editor.
```

2. There are two properties for the inactivity timeout setting. Both are initially set to 0 (which means this capability is disabled).

Property	Description
user.inactivity.timeout.default	Sets the inactivity timeout (in seconds) for all users except Read-Only users.
user.inactivity.timeout.role.readonly.default	Sets the inactivity timeout (in seconds) for all Read-Only users.

3. Modify the values to enable the capability. The values are in seconds.
4. Save changes and restart Ambari Server.
5. After a user logs into Ambari Web, once a period of inactivity occurs, the user will be presented with an Automatic Logout dialog 60 seconds from logout. The user can click to remain logged in or if no activity occurs, Ambari Web will automatically log the user out and redirect the application to the login page.

2.4.3. Set Up Kerberos for Ambari Server

When a cluster is enabled for Kerberos, the component REST endpoints (such as the YARN ATS component) require [SPNEGO](#) authentication.

Depending on the Services in your cluster, Ambari Web needs access to these APIs. As well, views such as the [Tez View](#) need access to ATS. Therefore, the Ambari Server requires a Kerberos principal in order to authenticate via SPNEGO against these APIs. This section describes how to configure Ambari Server with a Kerberos principal and keytab to allow views to authenticate via SPNEGO against cluster components.

1. Create a principal in your KDC for the Ambari Server. For example, using `kadmin`:

```
addprinc -randkey ambari-server@EXAMPLE.COM
```

2. Generate a keytab for that principal.

```
xst -k ambari.server.keytab ambari-server@EXAMPLE.COM
```

3. Place that keytab on the Ambari Server host. Be sure to set the file permissions so the user running the Ambari Server daemon can access the keytab file.

```
/etc/security/keytabs/ambari.server.keytab
```

4. Stop the ambari server.

```
ambari-server stop
```

5. Run the `setup-security` command.

```
ambari-server setup-security
```

6. Select 3 for Setup Ambari kerberos JAAS configuration.

7. Enter the Kerberos principal name for the Ambari Server you set up earlier.

8. Enter the path to the keytab for the Ambari principal.

9. Restart Ambari Server.

```
ambari-server restart
```

2.4.4. Optional: Set Up Two-Way SSL Between Ambari Server and Ambari Agents

Two-way SSL provides a way to encrypt communication between Ambari Server and Ambari Agents. By default Ambari ships with Two-way SSL disabled. To enable Two-way SSL:

Ambari Server should not be running when you do this: either make the edits before you start Ambari Server the first time or bring the server down to make the edits.

1. On the Ambari Server host, open `/etc/ambari-server/conf/ambari.properties` with a text editor.

2. Add the following property:

```
security.server.two_way_ssl = true
```

3. Start or restart the Ambari Server.

```
ambari-server restart
```

The Agent certificates are downloaded automatically during Agent Registration.

2.4.5. Optional: Configure Ciphers and Protocols for Ambari Server

Ambari provides control of ciphers and protocols that are exposed via Ambari Server.

1. To disable specific ciphers, you can optionally add a list of the following format to `ambari.properties`. If you specify multiple ciphers, separate each cipher using a vertical bar `|`.

```
security.server.disabled.ciphers=TLS_ECDHE_RSA_WITH_3DES_EDE_CBC_SHA
```

2. To disable specific protocols, you can optionally add a list of the following format to `ambari.properties`. If you specify multiple protocols, separate each protocol using a vertical bar `|`.

```
security.server.disabled.protocols=SSL|SSLv2|SSLv3
```

2.4.6. Optional: HTTP Cookie Persistence

During HTTP authentication, a cookie is dropped. This is a persistent cookie that is valid across browser sessions. For clusters that require enhanced security, it is desirable to have a session cookie that gets deleted when the user closes the browser session.

In HDP-2.3.4 and higher versions, you can use the following property in the `etc/hadoop/conf/core-site.xml` file to specify cookie persistence across browser sessions.

```
<property>
  <name>hadoop.http.authentication.cookie.persistent</name>
  <value>true</value>
</property>
```


The default value for this property is `false`.

2.5. Enabling SPNEGO Authentication for Hadoop

By default, access to the HTTP-based services and UIs for the cluster are not configured to require authentication. Kerberos authentication can be configured for the Web UIs for HDFS, YARN, MapReduce2, HBase, Oozie, Falcon, and Storm. SPNEGO authentication for HBase Web UIs is only available in HDP 2.5 and later.

- [Configure Ambari Server for Authenticated HTTP \[48\]](#)
- [Configuring HTTP Authentication for HDFS, YARN, MapReduce2, HBase, Oozie, Falcon and Storm \[48\]](#)

2.5.1. Configure Ambari Server for Authenticated HTTP

In order for Ambari to work with a cluster in which authenticated HTTP access to the Web UI's is required, you must configure the Ambari Server for Kerberos. Refer to [Set Up Kerberos for Ambari Server](#) for more information.

2.5.2. Configuring HTTP Authentication for HDFS, YARN, MapReduce2, HBase, Oozie, Falcon and Storm

1. Create a secret key used for signing authentication tokens. This file should contain random data and be placed on every host in the cluster. It should also be owned by the `hdfs` user and group owned by the `hadoop` group. Permissions should be set to 440. For example:

```
dd if=/dev/urandom of=/etc/security/http_secret bs=1024 count=1
chown hdfs:hadoop /etc/security/http_secret
chmod 440 /etc/security/http_secret
```

2. In Ambari Web, browse to **Services > HDFS > Configs** .
3. Add or modify the following configuration properties to Advanced core-site .

Property	New Value
<code>hadoop.http.authentication.simple.anonymous.allowed</code>	<code>false</code>
<code>hadoop.http.authentication.signature.secret.file</code>	<code>/etc/security/http_secret</code>
<code>hadoop.http.authentication.type</code>	<code>kerberos</code>
<code>hadoop.http.authentication.kerberos.keytab</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>
<code>hadoop.http.authentication.kerberos.principal</code>	<code>HTTP/_HOST@EXAMPLE.COM</code>
<code>hadoop.http.filter.initializers</code>	<code>org.apache.hadoop.security.AuthenticationFilterInitializer</code>
<code>hadoop.http.authentication.cookie.domain</code>	<code>hortonworks.local</code>



Important

The entries listed in the above table in **bold** and italicized are site-specific. The `hadoop.http.authentication.cookie.domain` property is based off

of the fully qualified domain names of the servers in the cluster. For example if the FQDN of your NameNode is `host1.hortonworks.local`, the `hadoop.http.authentication.cookie.domain` should be set to `hortonworks.local`.

4. For sites using **HBase**: Add or modify the following configuration properties in the `hbase-site.xml` file.

Property	New Value
<code>hbase.security.authentication.ui</code>	<code>kerberos</code>
<code>hbase.security.authentication.signature.secret.file</code>	<code>/etc/security/http_secret</code>
<code>hbase.security.authentication.spnego.kerberos.keytab</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>
<code>hbase.security.authentication.spnego.kerberos.principal</code>	<code>HTTP/_HOST@EXAMPLE.COM</code>

5. Save the configuration, then restart the affected services.

2.6. Setting Up Kerberos Authentication for Non-Ambari Clusters

This section provides information for enabling security for a manually installed version of HDP.

- [Preparing Kerberos \[49\]](#)
- [Configuring HDP for Kerberos \[55\]](#)
- [Configuring HBase and ZooKeeper \[72\]](#)
- [Configuring Hue \[79\]](#)
- [Setting up One-Way Trust with Active Directory \[81\]](#)
- [Configuring Proxy Users \[83\]](#)

2.6.1. Preparing Kerberos

This subsection provides information on setting up Kerberos for an HDP installation.

2.6.1.1. Kerberos Overview

To create secure communication among its various components, HDP uses Kerberos. Kerberos is a third-party authentication mechanism, in which users and services that users wish to access rely on the Kerberos server to authenticate each to the other. This mechanism also supports encrypting all traffic between the user and the service.

The Kerberos server itself is known as the *Key Distribution Center*, or KDC. At a high level, it has three parts:

- A database of users and services (known as *principals*) and their respective Kerberos passwords
- An *authentication server (AS)* which performs the initial authentication and issues a *Ticket Granting Ticket (TGT)*

- A *Ticket Granting Server* (TGS) that issues subsequent service tickets based on the initial TGT.

A user principal requests authentication from the AS. The AS returns a TGT that is encrypted using the user principal's Kerberos password, which is known only to the user principal and the AS. The user principal decrypts the TGT locally using its Kerberos password, and from that point forward, until the ticket expires, the user principal can use the TGT to get service tickets from the TGS.

Because a service principal cannot provide a password each time to decrypt the TGT, it uses a special file, called a *keytab*, which contains its authentication credentials.

The service tickets allow the principal to access various services. The set of hosts, users, and services over which the Kerberos server has control is called a *realm*.



Note

Because Kerberos is a time-sensitive protocol, all hosts in the realm must be time-synchronized, for example, by using the Network Time Protocol (NTP). If the local system time of a client differs from that of the KDC by as little as 5 minutes (the default), the client will not be able to authenticate.

2.6.1.2. Installing and Configuring the KDC

To use Kerberos with HDP, either use an existing KDC or install a new one for HDP only. The following gives a very high level description of the installation process. For more information, see [RHEL documentation](#), [CentOS documentation](#), [SLES documentation](#), or [Ubuntu and Debian documentation](#).

1. Install the KDC server:

- On RHEL, CentOS, or Oracle Linux, run:

```
yum install krb5-server krb5-libs krb5-auth-dialog krb5-workstation
```

- On SLES, run:

```
zypper install krb5 krb5-server krb5-client
```

- On Ubuntu or Debian, run:

```
apt-get install krb5 krb5-server krb5-client
```



Note

The host on which you install the KDC must itself be secure.

2. When the server is installed you must edit the two main configuration files.

Update the KDC configuration by replacing EXAMPLE.COM with your domain and `kerberos.example.com` with the FQDN of the KDC host. Configuration files are in the following locations:

- On RHEL, CentOS, or Oracle Linux:

```
/etc/krb5.conf
```

```
/var/kerberos/krb5kdc/kdc.conf
```

- On SLES:

```
/etc/krb5.conf  
/var/lib/kerberos/krb5kdc/kdc.conf
```

- On Ubuntu or Debian:

```
/etc/krb5.conf  
/var/kerberos/krb5kdc/kdc.conf
```

3. Copy the updated `krb5.conf` to every cluster node.

2.6.1.3. Creating the Database and Setting Up the First Administrator

1. Use the utility `kdb5_util` to create the Kerberos database:

- On RHEL, CentOS, or Oracle Linux:

```
/usr/sbin/kdb5_util create -s
```

- On SLES:

```
kdb5_util create -s
```

- On Ubuntu or Debian:

```
kdb5_util -s create
```



Note

The `-s` option stores the master server key for the database in a stash file. If the stash file is not present, you must log into the KDC with the master password (specified during installation) each time it starts. This will automatically regenerate the master server key.

2. Set up the KDC Access Control List (ACL):

- On RHEL, CentOS, or Oracle Linux add administrators to `/var/kerberos/krb5kdc/kadm5.acl`.
- On SLES, add administrators to `/var/lib/kerberos/krb5kdc/kadm5.acl`.



Note

For example, the following line grants full access to the database for users with the admin extension: `*/admin@EXAMPLE.COM *`

3. Start **kadmin** for the change to take effect.
4. Create the first user principal. This must be done at a terminal window on the KDC machine itself, while you are logged in as root. Notice the `.local`. Normal `kadmin` usage requires that a principal with appropriate access already exist. The `kadmin.local` command can be used even if no principals exist:

```
/usr/sbin/kadmin.local -q "addprinc $username/admin
```

Now this user can create additional principals either on the KDC machine or through the network. The following instruction assumes that you are using the KDC machine.

5. On the KDC, start Kerberos:

- On RHEL, CentOS, or Oracle Linux:

```
/sbin/service krb5kdc start
/sbin/service kadmin start
```

- On SLES:

```
rckrb5kdc start
rckadmind start
```

- On Ubuntu or Debian:

```
/etc/init.d/krb5-kdc start
/etc/init.d/kadmin start
```

2.6.1.4. Creating Service Principals and Keytab Files for HDP

Each service in HDP must have its own principal. Because services do not login with a password to acquire their tickets, their principal's authentication credentials are stored in a keytab file, which is extracted from the Kerberos database and stored locally with the service principal.

First create the principal, using mandatory naming conventions. Then create the keytab file with that principal's information, and copy the file to the keytab directory on the appropriate service host.

1. To create a service principal you will use the kadmin utility. This is a command-line driven utility into which you enter Kerberos commands to manipulate the central database. To start kadmin, enter:

```
'kadmin $USER/admin@REALM'
```

To create a service principal, enter the following:

```
kadmin: addprinc -randkey $principal_name/$service-host-FQDN@$hadoop.realm
```

You must have a principal with administrative permissions to use this command. The randkey is used to generate the password.

The \$principal_name part of the name must match the values in the following table.

In the example each service principal's name has appended to it the fully qualified domain name of the host on which it is running. This is to provide a unique principal name for services that run on multiple hosts, like DataNodes and TaskTrackers. The addition of the hostname serves to distinguish, for example, a request from DataNode A from a request from DataNode B.

This is important for two reasons:

- a. If the Kerberos credentials for one DataNode are compromised, it does not automatically lead to all DataNodes being compromised

- b. If multiple DataNodes have exactly the same principal and are simultaneously connecting to the NameNode, and if the Kerberos authenticator being sent happens to have same timestamp, then the authentication would be rejected as a replay request.

Note: The NameNode, Secondary NameNode, and Oozie require two principals each.

If you are configuring High Availability (HA) for a Quorum-based NameNode, you must also generate a principle (jn/\$FQDN) and keytab (jn.service.keytab) for each JournalNode. JournalNode also requires the keytab for its HTTP service. If the JournalNode is deployed on the same host as a NameNode, the same keytab file (spnego.service.keytab) can be used for both. In addition, HA requires two NameNodes. Both the active and standby NameNodes require their own principle and keytab files. The service principles of the two NameNodes can share the same name, specified with the `dfs.namenode.kerberos.principal` property in `hdfs-site.xml`, but the NameNodes still have different fully qualified domain names.

Table 2.7. Service Principals

Service	Component	Mandatory Principal Name
HDFS	NameNode	nn/\$FQDN
HDFS	NameNode HTTP	HTTP/\$FQDN
HDFS	SecondaryNameNode	nn/\$FQDN
HDFS	SecondaryNameNode HTTP	HTTP/\$FQDN
HDFS	DataNode	dn/\$FQDN
MR2	History Server	jhs/\$FQDN
MR2	History Server HTTP	HTTP/\$FQDN
YARN	ResourceManager	rm/\$FQDN
YARN	NodeManager	nm/\$FQDN
Oozie	Oozie Server	oozie/\$FQDN
Oozie	Oozie HTTP	HTTP/\$FQDN
Hive	Hive Metastore HiveServer2	hive/\$FQDN
Hive	WebHCat	HTTP/\$FQDN
HBase	MasterServer	hbase/\$FQDN
HBase	RegionServer	hbase/\$FQDN
Storm	Nimbus server DRPC daemon	nimbus/\$FQDN **
Storm	Storm UI daemon Storm Logviewer daemon Nodes running process controller (such as Supervisor)	storm/\$FQDN **
Kafka	KafkaServer	kafka/\$FQDN
Hue	Hue Interface	hue/\$FQDN
ZooKeeper	ZooKeeper	zookeeper/\$FQDN
JournalNode Server*	JournalNode	jn/\$FQDN
Gateway	Knox	knox/\$FQDN

* Only required if you are setting up NameNode HA.

** For more information, see [Configure Kerberos Authentication for Storm](#).

For example: To create the principal for a DataNode service, issue this command:

```
kadmin: addprinc -randkey dn/$datanode-host@$hadoop.realm
```

2. Extract the related keytab file and place it in the keytab directory of the appropriate respective components. The default directory is `/etc/krb5.keytab`.

```
kadmin: xst -k $keytab_file_name $principal_name/fully.qualified.domain.name
```

You must use the mandatory names for the `$keytab_file_name` variable shown in the following table.

Table 2.8. Service Keytab File Names

Component	Principal Name	Mandatory Keytab File Name
NameNode	nn/\$FQDN	nn.service.keytab
NameNode HTTP	HTTP/\$FQDN	spnego.service.keytab
SecondaryNameNode	nn/\$FQDN	nn.service.keytab
SecondaryNameNode HTTP	HTTP/\$FQDN	spnego.service.keytab
DataNode	dn/\$FQDN	dn.service.keytab
MR2 History Server	jhs/\$FQDN	nm.service.keytab
MR2 History Server HTTP	HTTP/\$FQDN	spnego.service.keytab
YARN	rm/\$FQDN	rm.service.keytab
YARN	nm/\$FQDN	nm.service.keytab
Oozie Server	oozie/\$FQDN	oozie.service.keytab
Oozie HTTP	HTTP/\$FQDN	spnego.service.keytab
Hive Metastore	hive/\$FQDN	hive.service.keytab
HiveServer2		
WebHCat	HTTP/\$FQDN	spnego.service.keytab
HBase Master Server	hbase/\$FQDN	hbase.service.keytab
HBase RegionServer	hbase/\$FQDN	hbase.service.keytab
Storm	storm/\$FQDN	storm.service.keytab
Kafka	kafka/\$FQDN	kafka.service.keytab
Hue	hue/\$FQDN	hue.service.keytab
ZooKeeper	zookeeper/\$FQDN	zk.service.keytab
Journal Server*	jn/\$FQDN	jn.service.keytab
Knox Gateway**	knox/\$FQDN	knox.service.keytab

* Only required if you are setting up NameNode HA.

** Only required if you are using a Knox Gateway.

For example: To create the keytab files for the NameNode, issue these commands:

```
kadmin: xst -k nn.service.keytab nn/$namenode-host kadmin: xst -k spnego.  
service.keytab HTTP/$namenode-host
```

When you have created the keytab files, copy them to the keytab directory of the respective service hosts.

3. Verify that the correct keytab files and principals are associated with the correct service using the klist command. For example, on the NameNode:

```
klist -k -t /etc/security/nn.service.keytab
```

Do this on each respective service in your cluster.

2.6.2. Configuring HDP for Kerberos

Configuring HDP for Kerberos has two parts:

- Creating a mapping between service principals and UNIX usernames.

Hadoop uses group memberships of users at various places, such as to determine group ownership for files or for access control.

A user is mapped to the groups it belongs to using an implementation of the GroupMappingServiceProvider interface. The implementation is pluggable and is configured in `core-site.xml`.

By default Hadoop uses ShellBasedUnixGroupsMapping, which is an implementation of GroupMappingServiceProvider. It fetches the group membership for a username by executing a UNIX shell command. In secure clusters, since the usernames are actually Kerberos principals, ShellBasedUnixGroupsMapping will work only if the Kerberos principals map to valid UNIX usernames. Hadoop provides a feature that lets administrators specify mapping rules to map a Kerberos principal to a local UNIX username.

- Adding information to three main service configuration files.

There are several optional entries in the three main service configuration files that must be added to enable security on HDP.

This section provides information on configuring HDP for Kerberos.

- [Creating Mappings Between Principals and UNIX Usernames \[56\]](#)
- [Adding Security Information to Configuration Files \[57\]](#)
- [Configuring HBase and ZooKeeper \[72\]](#)
- [Configuring Hue \[79\]](#)



Note

You must adhere to the existing upper and lower case naming conventions in the configuration file templates.

2.6.2.1. Creating Mappings Between Principals and UNIX Usernames

HDP uses a rule-based system to create mappings between service principals and their related UNIX usernames. The rules are specified in the `core-site.xml` configuration file as the value to the optional key `hadoop.security.auth_to_local`.

The default rule is simply named `DEFAULT`. It translates all principals in your default domain to their first component. For example, `myusername@APACHE.ORG` and `myusername/admin@APACHE.ORG` both become `myusername`, assuming your default domain is `APACHE.ORG`.

Creating Rules

To accommodate more complex translations, you can create a hierarchical set of rules to add to the default. Each rule is divided into three parts: base, filter, and substitution.

- **The Base**

The base begins with the number of components in the principal name (excluding the realm), followed by a colon, and the pattern for building the username from the sections of the principal name. In the pattern section `$0` translates to the realm, `$1` translates to the first component, and `$2` to the second component.

For example:

```
[1:$1@$0] translates myusername@APACHE.ORG to myusername@APACHE.ORG
[2:$1] translates myusername/admin@APACHE.ORG to myusername
[2:$1%$2] translates myusername/admin@APACHE.ORG to "myusername%admin"
```

- **The Filter**

The filter consists of a regular expression (regex) in a parentheses. It must match the generated string for the rule to apply.

For example:

```
(.*%admin) matches any string that ends in %admin
(.*@SOME.DOMAIN) matches any string that ends in @SOME.DOMAIN
```

- **The Substitution**

The substitution is a sed rule that translates a regex into a fixed string. For example:

```
s/@ACME\.COM// removes the first instance of @ACME.DOMAIN
s/@[A-Z]*\.COM// remove the first instance of @ followed by a name followed
by COM.
s/X/Y/g replace all of X's in the name with Y
```

2.6.2.2. Examples

- If your default realm was `APACHE.ORG`, but you also wanted to take all principals from `ACME.COM` that had a single component `joe@ACME.COM`, the following rule would do this:

```
RULE:[1:$1@$0](.@ACME.COM)s/@.//
```

```
DEFAULT
```

- To translate names with a second component, you could use these rules:

```
RULE:[1:$1@$0](. @ACME.COM)s/@. //
RULE:[2:$1@$0](. @ACME.COM)s/@. // DEFAULT
```

- To treat all principals from APACHE.ORG with the extension /admin as admin, your rules would look like this:

```
RULE[2:$1%$2@$0](. %admin@APACHE.ORG)s/. /admin/
DEFAULT
```

2.6.2.3. Adding Security Information to Configuration Files

To enable security on HDP, you must add optional information to various configuration files.

Before you begin, set JSVC_Home in hadoop-env.sh.

- For RHEL/CentOS/Oracle Linux:

```
export JSVC_HOME=/usr/libexec/bigtop-utils
```

- For SLES and Ubuntu:

```
export JSVC_HOME=/usr/hdp/current/bigtop-utils
```

2.6.2.3.1. core-site.xml

Add the following information to the `core-site.xml` file on every host in your cluster:

Table 2.9. General core-site.xml, Knox, and Hue

Property Name	Property Value	Description
hadoop.security.authentication	kerberos	Set the authentication type for the cluster. Valid values are: simple or kerberos.
hadoop.rpc.protection	authentication; integrity; privacy	This is an [OPTIONAL] setting. If not set, defaults to authentication. authentication = authentication only; the client and server mutually authenticate during connection setup. integrity = authentication and integrity; guarantees the integrity of data exchanged between client and server as well as authentication. privacy = authentication, integrity, and confidentiality; guarantees that data exchanged between client and server is encrypted and is not readable by a "man in the middle".
hadoop.security.authorization	true	Enable authorization for different protocols.
hadoop.security.auth_to_local	The mapping rules. For example: RULE:[2:\$1@\$0] ([jt]t@.*EXAMPLE.COM)s/. */	The mapping from Kerberos principal names to local OS user names. See Creating Mappings Between Principals

Property Name	Property Value	Description
	mapred/ RULE:[2:\$1@\$0] ([nd]n@.*EXAMPLE.COM)s/.*/ hdfs/ RULE:[2:\$1@\$0] (hm@.*EXAMPLE.COM)s/.*/ hbase/ RULE:[2:\$1@\$0] (rs@.*EXAMPLE.COM)s/.*/ hbase/ DEFAULT	and UNIX Usernames for more information.

Following is the XML for these entries:

```
<property>
  <name>hadoop.security.authentication</name>
  <value>kerberos</value>
  <description> Set the authentication for the cluster.
  Valid values are: simple or kerberos.</description>
</property>

<property>
  <name>hadoop.security.authorization</name>
  <value>>true</value>
  <description>Enable authorization for different protocols.</description>
</property>

<property>
  <name>hadoop.security.auth_to_local</name>
  <value>
  RULE:[2:$1@$0]([jt]t@.*EXAMPLE.COM)s/.*/mapred/
  RULE:[2:$1@$0]([nd]n@.*EXAMPLE.COM)s/.*/hdfs/
  RULE:[2:$1@$0](hm@.*EXAMPLE.COM)s/.*/hbase/
  RULE:[2:$1@$0](rs@.*EXAMPLE.COM)s/.*/hbase/
  DEFAULT
  </value>
  <description>The mapping from kerberos principal names
  to local OS user names.</description>
</property>
```

When using the Knox Gateway, add the following to the `core-site.xml` file on the master nodes host in your cluster:

Table 2.10. core-site.xml Master Node Settings – Knox Gateway

Property Name	Property Value	Description
hadoop.proxyuser.knox.groups	users	Grants proxy privileges for Knox user.
hadoop.proxyuser.knox.hosts	\$knox_host_FQDN	Identifies the Knox Gateway host.

When using Hue, add the following to the `core-site.xml` file on the master nodes host in your cluster:

Table 2.11. core-site.xml Master Node Settings – Hue

Property Name	Property Value	Description
hue.kerberos.principal.shortname	hue	Group to which all the Hue users belong. Use the wild card character to select multiple groups, for example cli*.
hadoop.proxyuser.hue.groups	*	Group to which all the Hue users belong. Use the wild card character to select multiple groups, for example cli*.

Property Name	Property Value	Description
hadoop.proxyuser.hue.hosts	*	
hadoop.proxyuser.knox.hosts	\$hue_host_FQDN	Identifies the Knox Gateway host.

Following is the XML for both Knox and Hue settings:

```
<property>
  <name>hadoop.security.authentication</name>
  <value>kerberos</value>
  <description>Set the authentication for the cluster.
  Valid values are: simple or kerberos.</description>
</property>

<property>
  <name>hadoop.security.authorization</name>
  <value>>true</value>
  <description>Enable authorization for different protocols.
  </description>
</property>

<property>
  <name>hadoop.security.auth_to_local</name>
  <value>
    RULE:[2:$1@$0]([jt]t@.*EXAMPLE.COM)s/./mapred/
    RULE:[2:$1@$0]([nd]n@.*EXAMPLE.COM)s/./hdfs/
    RULE:[2:$1@$0](hm@.*EXAMPLE.COM)s/./hbase/
    RULE:[2:$1@$0](rs@.*EXAMPLE.COM)s/./hbase/
    DEFAULT
  </value>
  <description>The mapping from kerberos principal names
  to local OS user names.</description>
</property>

<property>
  <name>hadoop.proxyuser.knox.groups</name>
  <value>users</value>
</property>

<property>
  <name>hadoop.proxyuser.knox.hosts</name>
  <value>Knox.EXAMPLE.COM</value>
</property>
```

2.6.2.3.1.1. HTTP Cookie Persistence

During HTTP authentication, a cookie is dropped. This is a persistent cookie that is valid across browser sessions. For clusters that require enhanced security, it is desirable to have a session cookie that gets deleted when the user closes the browser session.

You can use the following `core-site.xml` property to specify cookie persistence across browser sessions.

```
<property>
  <name>hadoop.http.authentication.cookie.persistent</name>
  <value>>true</value>
</property>
```

The default value for this property is `false`.

2.6.2.3.2. hdfs-site.xml

To the `hdfs-site.xml` file on every host in your cluster, you must add the following information:

Table 2.12. hdfs-site.xml File Property Settings

Property Name	Property Value	Description
<code>dfs.permissions.enabled</code>	<code>true</code>	If true, permission checking in HDFS is enabled. If false, permission checking is turned off, but all other behavior is unchanged. Switching from one parameter value to the other does not change the mode, owner or group of files or directories.
<code>dfs.permissions.supergroup</code>	<code>hdfs</code>	The name of the group of super-users.
<code>dfs.block.access.token.enable</code>	<code>true</code>	If true, access tokens are used as capabilities for accessing DataNodes. If false, no access tokens are checked on accessing DataNodes.
<code>dfs.namenode.kerberos.principal</code>	<code>nn/_HOST@EXAMPLE.COM</code>	Kerberos principal name for the NameNode.
<code>dfs.secondary.namenode.kerberos.principal</code>	<code>nn/_HOST@EXAMPLE.COM</code>	Kerberos principal name for the secondary NameNode.
<code>dfs.web.authentication.kerberos.principal</code>	<code>HTTP/_HOST@EXAMPLE.COM</code>	The HTTP Kerberos principal used by Hadoop-Auth in the HTTP endpoint. The HTTP Kerberos principal MUST start with 'HTTP/' per Kerberos HTTP SPNEGO specification.
<code>dfs.web.authentication.kerberos.keytab</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>	The Kerberos keytab file with the credentials for the HTTP Kerberos principal used by Hadoop-Auth in the HTTP endpoint.
<code>dfs.datanode.kerberos.principal</code>	<code>dn/_HOST@EXAMPLE.COM</code>	The Kerberos principal that the DataNode runs as. "_HOST" is replaced by the real host name.
<code>dfs.namenode.keytab.file</code>	<code>/etc/security/keytabs/nn.service.keytab</code>	Combined keytab file containing the NameNode service and host principals.
<code>dfs.secondary.namenode.keytab.file</code>	<code>/etc/security/keytabs/nn.service.keytab</code>	Combined keytab file containing the NameNode service and host principals. <question?>
<code>dfs.datanode.keytab.file</code>	<code>/etc/security/keytabs/dn.service.keytab</code>	The filename of the keytab file for the DataNode.
<code>dfs.https.port</code>	<code>50470</code>	The HTTPS port to which the NameNode binds.
<code>dfs.namenode.https-address</code>	Example: <code>ip-10-111-59-170.ec2.internal:50470</code>	The HTTPS address to which the NameNode binds.
<code>dfs.datanode.data.dir.perm</code>	<code>750</code>	The permissions that must be set on the <code>dfs.data.dir</code> directories. The DataNode will not come up if all existing <code>dfs.data.dir</code> directories do not have this setting. If the directories do not exist, they will be created with this permission.
<code>dfs.cluster administrators</code>	<code>hdfs</code>	ACL for who all can view the default servlets in the HDFS.

Property Name	Property Value	Description
dfs.namenode.kerberos.internal.spnego.principal	\${dfs.web.authentication.kerberos.principal}	
dfs.secondary.namenode.kerberos.internal.spnego.principal	\${dfs.web.authentication.kerberos.principal}	

Following is the XML for these entries:

```
<property>
  <name>dfs.permissions</name>
  <value>>true</value>
  <description> If "true", enable permission checking in
HDFS. If "false", permission checking is turned
off, but all other behavior is
unchanged. Switching from one parameter value to the other does
not change the mode, owner or group of files or
directories. </description>
</property>

<property>
  <name>dfs.permissions.supergroup</name>
  <value>hdfs</value>
  <description>The name of the group of
super-users.</description>
</property>

<property>
  <name>dfs.namenode.handler.count</name>
  <value>100</value>
  <description>Added to grow Queue size so that more
client connections are allowed</description>
</property>

<property>
  <name>ipc.server.max.response.size</name>
  <value>5242880</value>
</property>

<property>
  <name>dfs.block.access.token.enable</name>
  <value>true</value>
  <description> If "true", access tokens are used as capabilities
for accessing datanodes. If "false", no access tokens are checked on
accessing datanodes. </description>
</property>

<property>
  <name>dfs.namenode.kerberos.principal</name>
  <value>nn/_HOST@EXAMPLE.COM</value>
  <description> Kerberos principal name for the
NameNode </description>
</property>

<property>
  <name>dfs.secondary.namenode.kerberos.principal</name>
  <value>nn/_HOST@EXAMPLE.COM</value>
  <description>Kerberos principal name for the secondary NameNode.
</description>
</property>
```

```
<property>
  <!--cluster variant -->
  <name>dfs.secondary.http.address</name>
  <value>ip-10-72-235-178.ec2.internal:50090</value>
  <description>Address of secondary namenode web server</description>
</property>

<property>
  <name>dfs.secondary.https.port</name>
  <value>50490</value>
  <description>The https port where secondary-namenode
  binds</description>
</property>

<property>
  <name>dfs.web.authentication.kerberos.principal</name>
  <value>HTTP/_HOST@EXAMPLE.COM</value>
  <description> The HTTP Kerberos principal used by Hadoop-Auth in the HTTP
  endpoint.
  The HTTP Kerberos principal MUST start with 'HTTP/' per Kerberos HTTP
  SPNEGO specification.
  </description>
</property>

<property>
  <name>dfs.web.authentication.kerberos.keytab</name>
  <value>/etc/security/keytabs/spnego.service.keytab</value>
  <description>The Kerberos keytab file with the credentials for the HTTP
  Kerberos principal used by Hadoop-Auth in the HTTP endpoint.
  </description>
</property>

<property>
  <name>dfs.datanode.kerberos.principal</name>
  <value>dn/_HOST@EXAMPLE.COM</value>
  <description>
  The Kerberos principal that the DataNode runs as. "_HOST" is replaced by
  the real
  host name.
  </description>
</property>

<property>
  <name>dfs.namenode.keytab.file</name>
  <value>/etc/security/keytabs/nn.service.keytab</value>
  <description>
  Combined keytab file containing the namenode service and host
  principals.
  </description>
</property>

<property>
  <name>dfs.secondary.namenode.keytab.file</name>
  <value>/etc/security/keytabs/nn.service.keytab</value>
  <description>
  Combined keytab file containing the namenode service and host
  principals.
  </description>
</property>
```

```
<property>
  <name>dfs.datanode.keytab.file</name>
  <value>/etc/security/keytabs/dn.service.keytab</value>
  <description>
    The filename of the keytab file for the DataNode.
  </description>
</property>

<property>
  <name>dfs.https.port</name>
  <value>50470</value>
  <description>The https port where namenode
    binds</description>
</property>

<property>
  <name>dfs.https.address</name>
  <value>ip-10-111-59-170.ec2.internal:50470</value>
  <description>The https address where namenode binds</description>
</property>

<property>
  <name>dfs.datanode.data.dir.perm</name>
  <value>750</value>
  <description>The permissions that should be there on
    dfs.data.dir directories. The datanode will not come up if the
    permissions are different on existing dfs.data.dir directories. If
    the directories don't exist, they will be created with this
    permission.</description>
</property>

<property>
  <name>dfs.access.time.precision</name>
  <value>0</value>
  <description>The access time for HDFS file is precise upto this
    value.The default value is 1 hour. Setting a value of 0
    disables access times for HDFS.
  </description>
</property>

<property>
  <name>dfs.cluster.administrators</name>
  <value> hdfs</value>
  <description>ACL for who all can view the default
    servlets in the HDFS</description>
</property>

<property>
  <name>ipc.server.read.threadpool.size</name>
  <value>5</value>
  <description></description>
</property>

<property>
  <name>dfs.namenode.kerberos.internal.spnego.principal</name>
  <value>${dfs.web.authentication.kerberos.principal}</value>
</property>

<property>
  <name>dfs.secondary.namenode.kerberos.internal.spnego.principal</name>
```



```
<value>${dfs.web.authentication.kerberos.principal}</value>
</property>
```

In addition, you must set the user on all secure DataNodes:

```
export HADOOP_SECURE_DN_USER=hdfs
export HADOOP_SECURE_DN_PID_DIR=/grid/0/var/run/hadoop/$HADOOP_SECURE_DN_USER
```

2.6.2.3.3. yarn-site.xml

You must add the following information to the `yarn-site.xml` file on every host in your cluster:

Table 2.13. yarn-site.xml Property Settings

Property	Value	Description
<code>yarn.resourcemanager.principal</code>	<code>yarn/localhost@EXAMPLE.COM</code>	The Kerberos principal for the ResourceManager.
<code>yarn.resourcemanager.keytab</code>	<code>/etc/krb5.keytab</code>	The keytab for the ResourceManager.
<code>yarn.nodemanager.principal</code>	<code>yarn/localhost@EXAMPLE.COM</code>	The Kerberos principal for the NodeManager.
<code>yarn.nodemanager.keytab</code>	<code>/etc/krb5.keytab</code>	The keytab for the NodeManager.
<code>yarn.nodemanager.container-executor.class</code>	<code>org.apache.hadoop.yarn.server.nodemanager.LinuxContainerExecutor</code>	The class that will execute (launch) the containers.
<code>yarn.nodemanager.linux-container-executor.path</code>	<code>hadoop-3.0.0-SNAPSHOT/bin/container-executor</code>	The path to the Linux container executor.
<code>yarn.nodemanager.linux-container-executor.group</code>	<code>hadoop</code>	A special group (e.g., <code>hadoop</code>) with executable permissions for the container executor, of which the NodeManager UNIX user is the group member and no ordinary application user is. If any application user belongs to this special group, security will be compromised. This special group name should be specified for the configuration property.
<code>yarn.timeline-service.principal</code>	<code>yarn/localhost@EXAMPLE.COM</code>	The Kerberos principal for the Timeline Server.
<code>yarn.timeline-service.keytab</code>	<code>/etc/krb5.keytab</code>	The Kerberos keytab for the Timeline Server.
<code>yarn.resourcemanager.webapp.delegation-token-auth-filter.enabled</code>	<code>true</code>	Flag to enable override of the default Kerberos authentication filter with the RM authentication filter to allow authentication using delegation tokens (fallback to Kerberos if the tokens are missing). Only applicable when the http authentication type is Kerberos.
<code>yarn.timeline-service.http-authentication.type</code>	<code>kerberos</code>	Defines authentication used for the Timeline Server HTTP endpoint. Supported values are: <code>simple</code> <code>kerberos</code> <code>\$_AUTHENTICATION_HANDLER_CLASSNAME</code>
<code>yarn.timeline-service.http-authentication.kerberos.principal</code>	<code>HTTP/localhost@EXAMPLE.COM</code>	The Kerberos principal to be used for the Timeline Server HTTP endpoint.
<code>yarn.timeline-service.http-authentication.kerberos.keytab</code>	<code>authentication.kerberos.keytab /etc/krb5.keytab</code>	The Kerberos keytab to be used for the Timeline Server HTTP endpoint.

Following is the XML for these entries:

```
<property>
  <name>yarn.resourcemanager.principal</name>
  <value>yarn/localhost@EXAMPLE.COM</value>
</property>

<property>
  <name>yarn.resourcemanager.keytab</name>
  <value>/etc/krb5.keytab</value>
</property>

<property>
  <name>yarn.nodemanager.principal</name>
  <value>yarn/localhost@EXAMPLE.COM</value>
</property>

<property>
  <name>yarn.nodemanager.keytab</name>
  <value>/etc/krb5.keytab</value>
</property>

<property>
  <name>yarn.nodemanager.container-executor.class</name>
  <value>org.apache.hadoop.yarn.server.nodemanager.LinuxContainerExecutor</
value>
</property>

<property>
  <name>yarn.nodemanager.linux-container-executor.path</name>
  <value>hadoop-3.0.0-SNAPSHOT/bin/container-executor</value>
</property>

<property>
  <name>yarn.nodemanager.linux-container-executor.group</name>
  <value>hadoop</value>
</property>

<property>
  <name>yarn.timeline-service.principal</name>
  <value>yarn/localhost@EXAMPLE.COM</value>
</property>

<property>
  <name>yarn.timeline-service.keytab</name>
  <value>/etc/krb5.keytab</value>
</property>

<property>
  <name>yarn.resourcemanager.webapp.delegation-token-auth-filter.enabled</
name>
  <value>>true</value>
</property>

<property>
  <name>yarn.timeline-service.http-authentication.type</name>
  <value>kerberos</value>
</property>

<property>
```

```

    <name>yarn.timeline-service.http-authentication.kerberos.principal</name>
    <value>HTTP/localhost@EXAMPLE.COM</value>
  </property>

  <property>
    <name>yarn.timeline-service.http-authentication.kerberos.keytab</name>
    <value>/etc/krb5.keytab</value>
  </property>

```

2.6.2.3.4. mapred-site.xml

You must add the following information to the `mapred-site.xml` file on every host in your cluster:

Table 2.14. mapred-site.xml Property Settings

Property Name	Property Value	Description
<code>mapreduce.jobhistory.keytab</code>	<code>/etc/security/keytabs/jhs.service.keytab</code>	Kerberos keytab file for the MapReduce JobHistory Server.
<code>mapreduce.jobhistory.principal</code>	<code>jhs/_HOST@TODO-KERBEROS-DOMAIN</code>	Kerberos principal name for the MapReduce JobHistory Server.
<code>mapreduce.jobhistory.webapp.address</code>	<code>TODO-JOBHISTORYNODE-HOSTNAME:19888</code>	MapReduce JobHistory Server Web UI host:port
<code>mapreduce.jobhistory.webapp.https.address</code>	<code>TODO-JOBHISTORYNODE-HOSTNAME:19889</code>	MapReduce JobHistory Server HTTPS Web UI host:port
<code>mapreduce.jobhistory.webapp.spnego-keytab-file</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>	Kerberos keytab file for the spnego service.
<code>mapreduce.jobhistory.webapp.spnego-principal</code>	<code>HTTP/_HOST@TODO-KERBEROS-DOMAIN</code>	Kerberos principal name for the spnego service.

Following is the XML for these entries:

```

<property>
  <name>mapreduce.jobhistory.keytab</name>
  <value>/etc/security/keytabs/jhs.service.keytab</value>
</property>

<property>
  <name>mapreduce.jobhistory.principal</name>
  <value>jhs/_HOST@TODO-KERBEROS-DOMAIN</value>
</property>

<property>
  <name>mapreduce.jobhistory.webapp.address</name>
  <value>TODO-JOBHISTORYNODE-HOSTNAME:19888</value>
</property>

<property>
  <name>mapreduce.jobhistory.webapp.https.address</name>
  <value>TODO-JOBHISTORYNODE-HOSTNAME:19889</value>
</property>

<property>
  <name>mapreduce.jobhistory.webapp.spnego-keytab-file</name>
  <value>/etc/security/keytabs/spnego.service.keytab</value>
</property>

<property>
  <name>mapreduce.jobhistory.webapp.spnego-principal</name>

```

```
<value>HTTP/_HOST@TODO-KERBEROS-DOMAIN</value>
</property>
```

2.6.2.3.5. hbase-site.xml

For HBase to run on a secured cluster, HBase must be able to authenticate itself to HDFS. Add the following information to the `hbase-site.xml` file on your HBase server. There are no default values; the following are only examples:

Table 2.15. hbase-site.xml Property Settings – HBase Server

Property Name	Property Value Example	Description
<code>hbase.master.keytab.file</code>	<code>/etc/security/keytabs/hbase.service.keytab</code>	The keytab for the HMaster service principal.
<code>hbase.master.kerberos.principal</code>	<code>hbase/_HOST@EXAMPLE.COM</code>	The Kerberos principal name that should be used to run the HMaster process. If <code>_HOST</code> is used as the hostname portion, it will be replaced with the actual hostname of the running instance.
<code>hbase.regionserver.keytab.file</code>	<code>/etc/security/keytabs/hbase.service.keytab</code>	The keytab for the HRegionServer service principal.
<code>hbase.regionserver.kerberos.principal</code>	<code>hbase/_HOST@EXAMPLE.COM</code>	The Kerberos principal name that should be used to run the HRegionServer process. If <code>_HOST</code> is used as the hostname portion, it will be replaced with the actual hostname of the running instance.
<code>hbase.superuser</code>	<code>hbase</code>	A comma-separated list of users or groups that are allowed full privileges, regardless of stored ACLs, across the cluster. Only used when HBase security is enabled.
<code>hbase.coprocessor.region.classes</code>	<i>Setting 1:</i> <code>org.apache.hadoop.hbase.security.token.TokenProvider,</code> <i>Setting 2:</i> <code>org.apache.hadoop.hbase.security.access.SecureBulkLoadEndpoint,</code> <i>Setting 3:</i> <code>org.apache.hadoop.hbase.security.access.AccessController</code>	A comma-separated list of coprocessors that are loaded by default on all tables. For any implemented coprocessor methods, the listed classes will be called in order. After implementing your own coprocessor, add the class to HBase's classpath and add the fully qualified class name here. Coprocessors can also be programmatically loaded using <code>HTableDescriptor</code> .
<code>hbase.coprocessor.master.classes</code>	<code>org.apache.hadoop.hbase.security.access.AccessController</code>	A comma-separated list of MasterObserver coprocessors that are loaded by the active HMaster process. For any implemented coprocessor methods, the listed classes will be called in order. After implementing your own MasterObserver, add the class to HBase's classpath and add the fully qualified class name here.
<code>hbase.coprocessor.regionserver.classes</code>	<code>org.apache.hadoop.hbase.security.access.AccessController</code>	A comma-separated list of RegionServerObserver coprocessors that are loaded by the HRegionServer processes. For any implemented coprocessor methods, the listed classes will be called in order. After implementing your own RegionServerObserver, add the class to

Property Name	Property Value Example	Description
		the HBase classpath and fully qualified class name here.
phoenix.queryserver.kerberos.principal	hbase/_HOST@EXAMPLE.COM	The Kerberos principal for the Phoenix Query Server process. The Phoenix Query Server is an optional component; this property only needs to be set when the query server is installed.
phoenix.queryserver.keytab.file	/etc/security/keytabs/hbase.service.keytab	The path to the Kerberos keytab file for the Phoenix Query Server process. The Phoenix Query Server is an optional component; this property only needs to be set when the query server is installed.

Following is the XML for these entries:

```
<property>
  <name>hbase.master.keytab.file</name>
  <value>/etc/security/keytabs/hbase.service.keytab</value>
  <description>Full path to the Kerberos keytab file to use for logging
  in the configured HMaster server principal.
  </description>
</property>

<property>
  <name>hbase.master.kerberos.principal</name>
  <value>hbase/_HOST@EXAMPLE.COM</value>
  <description>Ex. "hbase/_HOST@EXAMPLE.COM".
  The Kerberos principal name that should be used to run the HMaster
  process. The principal name should be in the form: user/hostname@DOMAIN.
  If "_HOST" is used as the hostname portion, it will be replaced with
  the actual hostname of the running instance.
  </description>
</property>

<property>
  <name>hbase.regionserver.keytab.file</name>
  <value>/etc/security/keytabs/hbase.service.keytab</value>
  <description>Full path to the Kerberos keytab file to use for logging
  in the configured HRegionServer server principal.
  </description>
</property>

<property>
  <name>hbase.regionserver.kerberos.principal</name>
  <value>hbase/_HOST@EXAMPLE.COM</value>
  <description>Ex. "hbase/_HOST@EXAMPLE.COM".
  The Kerberos principal name that
  should be used to run the HRegionServer process. The
  principal name should be in the form:
  user/hostname@DOMAIN. If _HOST
  is used as the hostname portion, it will be replaced
  with the actual hostname of the running
  instance. An entry for this principal must exist
  in the file specified in hbase.regionserver.keytab.file
  </description>
</property>
```

```
<!--Additional configuration specific to HBase security -->

<property>
  <name>hbase.superuser</name>
  <value>hbase</value>
  <description>List of users or groups (comma-separated), who are
  allowed full privileges, regardless of stored ACLs, across the cluster.
  Only used when HBase security is enabled.
  </description>
</property>

<property>
  <name>hbase.coprocessor.region.classes</name>
  <value>org.apache.hadoop.hbase.security.token.TokenProvider,
  org.apache.hadoop.hbase.security.access.SecureBulkLoadEndpoint,
  org.apache.hadoop.hbase.security.access.AccessController</value>
  <description>A comma-separated list of coprocessors that are loaded
  by default on all tables. For any override coprocessor method,
  these classes will be called in order. After implementing your
  own coprocessor, just put it in HBase's classpath and add the
  fully qualified class name here. A coprocessor can also be loaded on
  demand by setting HTableDescriptor.
  </description>
</property>

<property>
  <name>hbase.coprocessor.master.classes</name>
  <value>org.apache.hadoop.hbase.security.access.AccessController</value>
  <description>A comma-separated list of coprocessors that are
  loaded by default on all tables. For any implemented coprocessor methods,

  the listed classes will be called in order. After implementing your
  own coprocessor, add the class to HBase's classpath and add the
  fully qualified class name here. Coprocessors can also be
  programmatically loaded using HTableDescriptor.
  </description>
</property>

<property>
  <name>hbase.coprocessor.regionserver.classes</name>
  <value>org.apache.hadoop.hbase.security.access.AccessController</value>
  <description>A comma-separated list of RegionServerObserver coprocessors
  that are loaded by the HRegionServer processes. For any implemented
  coprocessor methods, the listed classes will be called in order. After
  implementing your own RegionServerObserver, add the class to the HBase
  classpath and fully qualified class name here.
  </description>
</property>

<property>
  <name>phoenix.queryserver.kerberos.principal</name>
  <value>hbase/_HOST@EXAMPLE.COM</value>
  <description>The Kerberos principal for the Phoenix Query Server
  process. The Phoenix Query Server is an optional component; this
  property only needs to be set when the query server is installed.
  </description>
</property>

<property>
  <name>phoenix.queryserver.keytab.file</name>
```

```
<value>/etc/security/keytabs/hbase.service.keytab</value>
<description>The path to the Kerberos keytab file for the
Phoenix Query Server process. The Phoenix Query Server is an optional
component; this property only needs to be set when the query server
is installed.</description>
</property>
```

2.6.2.3.6. hive-site.xml

HiveServer2 supports Kerberos authentication for all clients.

Add the following information to the `hive-site.xml` file on every host in your cluster:

Table 2.16. hive-site.xml Property Settings

Property Name	Description
hive.metastore.sasl.enabled	If true, the Metastore Thrift interface will be secured with SASL and clients must authenticate with Kerberos.
hive.metastore.kerberos.keytab.file	The keytab for the Metastore Thrift service principal.
hive.metastore.kerberos.principal	The service principal for the Metastore Thrift server. If <code>_HOST</code> is used as the hostname portion, it will be replaced with the actual hostname of the running instance.

Following is the XML for these entries:

```
<property>
  <name>hive.metastore.sasl.enabled</name>
  <value>true</value>
  <description>If true, the metastore thrift interface will be secured with
SASL.
  Clients must authenticate with Kerberos.</description>
</property>

<property>
  <name>hive.metastore.kerberos.keytab.file</name>
  <value>/etc/security/keytabs/hive.service.keytab</value>
  <description>The path to the Kerberos Keytab file containing the
metastore thrift server's service principal.
  </description>
</property>

<property>
  <name>hive.metastore.kerberos.principal</name>
  <value>hive/_HOST@EXAMPLE.COM</value>
  <description>The service principal for the metastore thrift server. The
special string _HOST will be replaced automatically with the correct
hostname.</description>
</property>
```

2.6.2.3.7. oozie-site.xml

To the `oozie-site.xml` file, add the following information:

Table 2.17. oozie-site.xml Property Settings

Property Name	Property Value	Description
oozie.service.AuthorizationService.security.enabled	true	Specifies whether security (user name/admin role) is enabled or not. If it is disabled any user can manage the Oozie system and manage any job.

Property Name	Property Value	Description
oozie.service.HadoopAccessorService.kerberos.enabled	true	Indicates if Oozie is configured to use Kerberos.
local.realm	EXAMPLE.COM	Kerberos Realm used by Oozie and Hadoop. Using local.realm to be aligned with Hadoop configuration.
oozie.service.HadoopAccessorService.keytab.file	/etc/security/keytabs/oozie.service.keytab	The keytab for the Oozie service principal.
oozie.service.HadoopAccessorService.kerberos.principaloozie/_HOSTI@EXAMPLE.COM	oozie/_HOSTI@EXAMPLE.COM	Kerberos principal for Oozie service.
oozie.authentication.type	kerberos	
oozie.authentication.kerberos.principal	HTTP/_HOST@EXAMPLE.COM	Whitelisted job tracker for Oozie service.
oozie.authentication.kerberos.keytab	/etc/security/keytabs/spnego.service.keytab	Location of the Oozie user keytab file.
oozie.service.HadoopAccessorService.nameNode.whitelist		
oozie.authentication.kerberos.name.rules	RULE:[2:\$1@\$0] ([jt]t@.*EXAMPLE.COM)s/.*/mapred/ RULE:[2:\$1@\$0] ([nd]n@.*EXAMPLE.COM)s/.*/hdfs/ RULE:[2:\$1@\$0] (hm@.*EXAMPLE.COM)s/.*/hbase/ RULE:[2:\$1@\$0] (rs@.*EXAMPLE.COM)s/.*/hbase/ DEFAULT	The mapping from Kerberos principal names to local OS user names. See Creating Mappings Between Principals and UNIX Usernames for more information.
oozie.service.ProxyUserService.proxyuser.knox.groups	users	Grant proxy privileges to the Knox user. Note only required when using a Knox Gateway.
oozie.service.ProxyUserService.proxyuser.knox.hosts	\$knox_host_FQDN	Identifies the Knox Gateway. Note only required when using a Knox Gateway.

2.6.2.3.8. webhcat-site.xml

To the `webhcat-site.xml` file, add the following information:

Table 2.18. webhcat-site.xml Property Settings

Property Name	Property Value	Description
templeton.kerberos.principal	HTTP/_HOST@EXAMPLE.COM	
templeton.kerberos.keytab	/etc/security/keytabs/spnego.service.keytab	
templeton.kerberos.secret	secret	
hadoop.proxyuser.knox.groups	users	Grant proxy privileges to the Knox user. Note only required when using a Knox Gateway.
hadoop.proxyuser.knox.hosts	\$knox_host_FQDN	Identifies the Knox Gateway. Note only required when using a Knox Gateway.

2.6.2.3.9. limits.conf

Adjust the Maximum Number of Open Files and Processes

In a secure cluster, if the DataNodes are started as the root user, JSVC downgrades the processing using `setuid` to `hdfs`. However, the `ulimit` is based on the `ulimit` of the root user,

and the default ulimit values assigned to the root user for the maximum number of open files and processes may be too low for a secure cluster. This can result in a “Too Many Open Files” exception when the DataNodes are started.

Therefore, when configuring a secure cluster you should increase the following root ulimit values:

- `nofile`: The maximum number of open files. Recommended value: 32768
- `nproc`: The maximum number of processes. Recommended value: 65536

To set system-wide ulimits to these values, log in as root and add the following lines to the `/etc/security/limits.conf` file on every host in your cluster:

```
* - nofile 32768
* - nproc 65536
```

To set only the root user ulimits to these values, log in as root and add the following lines to the `/etc/security/limits.conf` file.

```
root - nofile 32768
root - nproc 65536
```

You can use the `ulimit -a` command to view the current settings:

```
[root@node-1 /]# ulimit -a
core file size (blocks, -c) 0
data seg size (kbytes, -d) unlimited
scheduling priority (-e) 0
file size (blocks, -f) unlimited
pending signals (-i) 14874
max locked memory (kbytes, -l) 64
max memory size (kbytes, -m) unlimited
open files (-n) 1024
pipe size (512 bytes, -p) 8
POSIX message queues (bytes, -q) 819200
real-time priority (-r) 0
stack size (kbytes, -s) 10240
cpu time (seconds, -t) unlimited
max user processes (-u) 14874
virtual memory (kbytes, -v) unlimited
file locks (-x) unlimited
```

You can also use the `ulimit` command to dynamically set these limits until the next reboot. This method sets a temporary value that will revert to the settings in the `/etc/security/limits.conf` file after the next reboot, but it is useful for experimenting with limit settings. For example:

```
[root@node-1 /]# ulimit -n 32768
```

The updated value can then be displayed:

```
[root@node-1 /]# ulimit -n
32768
```

2.6.2.4. Configuring HBase and ZooKeeper

Use the following instructions to set up secure HBase and ZooKeeper:

1. [Configure HBase Master \[73\]](#)

2. [Create JAAS configuration files \[75\]](#)
3. [Start HBase and ZooKeeper services \[76\]](#)
4. [Configure secure client side access for HBase \[77\]](#)
5. [Optional: Configure client-side operation for secure operation - Thrift Gateway \[78\]](#)
6. [Optional: Configure client-side operation for secure operation - REST Gateway \[78\]](#)
7. [Configure HBase for Access Control Lists \(ACL\) \[79\]](#)

2.6.2.4.1. Configure HBase Master

Edit `$HBASE_CONF_DIR/hbase-site.xml` file on your HBase Master server to add the following information (`$HBASE_CONF_DIR` is the directory to store the HBase configuration files. For example, `/etc/hbase/conf`):



Note

There are no default values. The following are all examples.

```
<property>
  <name>hbase.master.keytab.file</name>
  <value>/etc/security/keytabs/hbase.service.keytab</value>
  <description>Full path to the kerberos keytab file to use
    for logging in the configured HMaster server principal.
  </description>
</property>
```

```
<property>
  <name>hbase.master.kerberos.principal</name>
  <value>hbase/_HOST@EXAMPLE.COM</value>
  <description>Ex. "hbase/_HOST@EXAMPLE.COM".
    The kerberos principal name that should be used to run the HMaster
    process.
    The principal name should be in the form: user/hostname@DOMAIN.
    If "_HOST" is used as the hostname portion,
    it will be replaced with the actual hostname of the running instance.
  </description>
</property>
```

```
<property>
  <name>hbase.regionserver.keytab.file</name>
  <value>/etc/security/keytabs/hbase.service.keytab</value>
  <description>Full path to the kerberos keytab file to use for logging
    in the configured HRegionServer server principal.
  </description>
</property>
```

```
<property>
  <name>hbase.regionserver.kerberos.principal</name>
  <value>hbase/_HOST@EXAMPLE.COM</value>
  <description>Ex. "hbase/_HOST@EXAMPLE.COM".
    The kerberos principal name that
    should be used to run the HRegionServer process.
    The
```

```
principal name should be in the form:
user/hostname@DOMAIN.
If _HOST
is used as the hostname portion, it will be replaced
with the actual hostname of the running
instance.
An entry for this principal must exist
in the file specified in hbase.regionserver.keytab.file
    </description>
</property>
```

```
<!--Additional configuration specific to HBase security -->

<property>
    <name>hbase.superuser</name>
    <value>hbase</value>
    <description>List of users or groups (comma-separated), who are
    allowed full privileges, regardless of stored ACLs, across the cluster.
    Only used when HBase security is enabled.
    </description>
</property>
```

```
<property>
    <name>hbase.coprocessor.region.classes</name>
    <value>org.apache.hadoop.hbase.security.token.TokenProvider,
org.apache.hadoop.hbase.security.access.SecureBulkLoadEndpoint,
org.apache.hadoop.hbase.security.access.AccessController </value>
    <description>A comma-separated list of Coprocessors that are loaded by
    default on all tables.
    </description>
</property>
```

```
<property>
    <name>hbase.security.authentication</name>
    <value>kerberos</value>
</property>
```

```
<property>
    <name>hbase.rpc.engine</name>
    <value>org.apache.hadoop.hbase.ipc.SecureRpcEngine</value>
</property>
```

```
<property>
    <name>hbase.security.authorization</name>
    <value>true</value>
    <description>Enables HBase authorization.
    Set the value of this property to false to disable HBase authorization.
    </description>
</property>
```

```
<property>
    <name>hbase.coprocessor.master.classes</name>
    <value>org.apache.hadoop.hbase.security.access.AccessController</
value>
</property>
```

```
<property>
  <name>hbase.bulkload.staging.dir</name>
  <value>/apps/hbase/staging</value>
  <description>Directory in the default filesystem,
owned by the hbase user, and has permissions(-rwx--x--x, 711) </description>
</property>
```

For more information on bulk loading in secure mode, see [HBase Secure BulkLoad](#). Note that the `hbase.bulkload.staging.dir` is created by HBase.

2.6.2.4.2. Create JAAS configuration files

1. Create the following JAAS configuration files on the HBase Master, RegionServer, and HBase client host machines.

These files must be created under the `$HBASE_CONF_DIR` directory:

where `$HBASE_CONF_DIR` is the directory to store the HBase configuration files. For example, `/etc/hbase/conf`.

- On each machine running an HBase server, create the `hbase-server.jaas` file under the `/etc/hbase/conf` directory and add the following content:

```
Client {
  com.sun.security.auth.module.Krb5LoginModule required
  useKeyTab=true
  storeKey=true
  useTicketCache=false
  keyTab="/etc/security/keytabs/hbase.service.keytab"
  principal="hbase/$fully.qualified.domain.name";
};
```

- On HBase client machines, create the `hbase-client.jaas` file under the `/etc/hbase/conf` directory. HBase servers include the HMaster and RegionServer. In this file, add the following content:

```
Client {
  com.sun.security.auth.module.Krb5LoginModule required
  useKeyTab=false
  useTicketCache=true;
};
```

2. Create the following JAAS configuration files on the ZooKeeper Server and client host machines.

These files must be created under the `$ZOOKEEPER_CONF_DIR` directory, where `$ZOOKEEPER_CONF_DIR` is the directory to store the HBase configuration files. For example, `/etc/zookeeper/conf`:

- On ZooKeeper server host machines, create the `zookeeper-server.jaas` file under the `/etc/zookeeper/conf` directory and add the following content:

```
Server {
  com.sun.security.auth.module.Krb5LoginModule required
  useKeyTab=true
  storeKey=true
  useTicketCache=false
  keyTab="/etc/security/keytabs/zookeeper.service.keytab"
  principal="zookeeper/$ZooKeeper.Server.hostname" ;
};
```

- On ZooKeeper client host machines, create the `zookeeper-client.jaas` file under the `/etc/zookeeper/conf` directory and add the following content:

```
Client {
  com.sun.security.auth.module.Krb5LoginModule required
  useKeyTab=false
  useTicketCache=true;
};
```

3. Edit the `hbase-env.sh` file on your HBase server to add the following information:

```
export HBASE_OPTS="-Djava.security.auth.login.config=
$HBASE_CONF_DIR/hbase-client.jaas"
export HBASE_MASTER_OPTS="-Djava.security.auth.login.config=
$HBASE_CONF_DIR/hbase-server.jaas"
export HBASE_REGIONSERVER_OPTS="-Djava.security.auth.login.config=
$HBASE_CONF_DIR/hbase-server.jaas"
```

where `HBASE_CONF_DIR` is the HBase configuration directory. For example, `/etc/hbase/conf`.

4. Edit `zoo.cfg` file on your ZooKeeper server to add the following information:

```
authProvider.1=org.apache.zookeeper.server.auth.SASLAuthenticationProvider
jaasLoginRenew=3600000
kerberos.removeHostFromPrincipal=true
kerberos.removeRealmFromPrincipal=true
```

5. Edit `zookeeper-env.sh` file on your ZooKeeper server to add the following information:

```
export SERVER_JVMFLAGS="-Djava.security.auth.login.
config=$ZOOKEEPER_CONF_DIR/zookeeper-server.jaas"
export CLIENT_JVMFLAGS="-Djava.security.auth.login.
config=$ZOOKEEPER_CONF_DIR/zookeeper-client.jaas"
```

where `ZOOKEEPER_CONF_DIR` is the ZooKeeper configuration directory. For example, `/etc/zookeeper/conf`.

2.6.2.4.3. Start HBase and ZooKeeper services

Start the HBase and ZooKeeper services using the instructions provided in the HDP Reference Manual, [Starting HDP Services](#).

If the configuration is successful, you should see the following in your ZooKeeper server logs:

```

11/12/05 22:43:39 INFO zookeeper.Login: successfully logged in.
11/12/05 22:43:39 INFO server.NIOServerCnxnFactory: binding to port 0.0.0.0/0.0.0.0:2181
11/12/05 22:43:39 INFO zookeeper.Login: TGT refresh thread started.
11/12/05 22:43:39 INFO zookeeper.Login: TGT valid starting at:          Mon Dec
05 22:43:39 UTC 2011
11/12/05 22:43:39 INFO zookeeper.Login: TGT expires:                  Tue Dec
06 22:43:39 UTC 2011
11/12/05 22:43:39 INFO zookeeper.Login: TGT refresh sleeping until: Tue Dec 06
18:36:42 UTC 2011
..
11/12/05 22:43:59 INFO auth.SaslServerCallbackHandler:
  Successfully authenticated client: authenticationID=hbase/ip-10-166-175-249.
us-west-1.compute.internal@HADOOP.LOCALDOMAIN;
  authorizationID=hbase/ip-10-166-175-249.us-west-1.compute.internal@HADOOP.
LOCALDOMAIN.
11/12/05 22:43:59 INFO auth.SaslServerCallbackHandler: Setting authorizedID:
  hbase
11/12/05 22:43:59 INFO server.ZooKeeperServer: adding SASL authorization for
  authorizationID: hbase

```

2.6.2.4.4. Configure secure client side access for HBase

HBase configured for secure client access is expected to be running on top of a secure HDFS cluster. HBase must be able to authenticate to HDFS services.

1. Provide a Kerberos principal to the HBase client user using the instructions provided [here](#).

- **Option I:** Provide Kerberos principal to normal HBase clients.

For normal HBase clients, Hortonworks recommends setting up a password to the principal.

- Set `maxrenewlife`.

The client principal's `maxrenewlife` should be set high enough so that it allows enough time for the HBase client process to complete. Client principals are not renewed automatically.

For example, if a user runs a long-running HBase client process that takes at most three days, we might create this user's principal within `kadmin` with the following command:

```
addprinc -maxrenewlife 3days
```

- **Option II:** Provide Kerberos principal to long running HBase clients.

- a. Set-up a keytab file for the principal and copy the resulting keytab files to where the client daemon will execute.

Ensure that you make this file readable only to the user account under which the daemon will run.

2. On every HBase client, add the following properties to the `$HBASE_CONF_DIR/hbase-site.xml` file:

```
<property>
  <name>hbase.security.authentication</name>
  <value>kerberos</value>
</property>
```



Note

The client environment must be logged in to Kerberos from KDC or keytab via the `kinit` command before communication with the HBase cluster is possible. Note that the client will not be able to communicate with the cluster if the `hbase.security.authentication` property in the client- and server-side site files fails to match.

```
<property>
  <name>hbase.rpc.engine</name>
  <value>org.apache.hadoop.hbase.ipc.SecureRpcEngine</value>
</property>
```

2.6.2.4.5. Optional: Configure client-side operation for secure operation - Thrift Gateway

Add the following to the `$HBASE_CONF_DIR/hbase-site.xml` file for every Thrift gateway:

```
<property>
  <name>hbase.thrift.keytab.file</name>
  <value>/etc/hbase/conf/hbase.keytab</value>
</property>
<property>
  <name>hbase.thrift.kerberos.principal</name>
  <value>${USER}/_HOST@HADOOP.LOCALDOMAIN</value>
</property>
```

Substitute the appropriate credential and keytab for `$USER` and `$KEYTAB` respectively.

The Thrift gateway will authenticate with HBase using the supplied credential. No authentication will be performed by the Thrift gateway itself. All client access via the Thrift gateway will use the Thrift gateway's credential and have its privilege.

2.6.2.4.6. Optional: Configure client-side operation for secure operation - REST Gateway

Add the following to the `$HBASE_CONF_DIR/hbase-site.xml` file for every REST gateway:

```
<property>
  <name>hbase.rest.keytab.file</name>
  <value>${KEYTAB}</value>
</property>
<property>
  <name>hbase.rest.kerberos.principal</name>
  <value>${USER}/_HOST@HADOOP.LOCALDOMAIN</value>
</property>
```

Substitute the appropriate credential and keytab for *\$USER* and *\$KEYTAB* respectively.

The REST gateway will authenticate with HBase using the supplied credential. No authentication will be performed by the REST gateway itself. All client access via the REST gateway will use the REST gateway's credential and have its privilege.

2.6.2.4.7. Configure HBase for Access Control Lists (ACL)

Use the following instructions to configure HBase for ACL:

1. Open `kinit` as HBase user.
 - a. Create a keytab for principal `hbase@REALM` and store it in the `hbase.headless.keytab` file. See instructions provided [here](#) for creating principal and keytab file.
 - b. Open `kinit` as HBase user. Execute the following command on your HBase Master:

```
kinit -kt hbase.headless.keytab hbase
```

2. Start the HBase shell. On the HBase Master host machine, execute the following command:

```
hbase shell
```

3. Set ACLs using HBase shell:

```
grant '$USER', '$permissions'
```

where

- *\$USER* is any user responsible for create/update/delete operations in HBase.



Note

You must set the ACLs for all those users who will be responsible for create/update/delete operations in HBase.

- *\$permissions* is zero or more letters from the set "RWCA": READ('R'), WRITE('W'), CREATE('C'), ADMIN('A').

2.6.2.5. Configuring Hue

Before you can configure Hue to work with an HDP cluster that is configured for Kerberos, you must refer to and complete the instructions for [Configuring Ambari and Hadoop for Kerberos](#) or [Setting Up Kerberos Security for Manual Installs](#).

To enable Hue to work with an HDP cluster configured for Kerberos, make the following changes to Hue and Kerberos.:

1. Where *\$FQDN* is the host name of the Hue server and *EXAMPLE.COM* is the Hadoop realm, create a principal for the Hue server:

```
# kadmin.local
kadmin.local: addprinc -randkey hue/$FQDN@EXAMPLE.COM
```


- Where `$FQDN` is the host name of the Hue server and `EXAMPLE.COM` is the Hadoop realm, generate a keytab for the Hue principal:

```
kadmin.local: xst -k hue.service.keytab hue/$FQDN@EXAMPLE.COM
```

- Put the `hue.service.keytab` file on the host where the Hue server is installed, in the directory `/etc/security/keytabs`.
- Set the permissions and ownership of the `/etc/security/keytabs/hue.service.keytab` file as follows:

```
chown hue:hadoop /etc/security/keytabs/hue.service.keytab
chmod 600 /etc/security/keytabs/hue.service.keytab
```

- Where `$FQDN` is the host name of the Hue server and `EXAMPLE.COM` is the Hadoop realm, use `kinit` to confirm that the `/etc/security/keytabs/hue.service.keytab` file is accessible to Hue:

```
su - hue kinit -k -t /etc/security/keytabs/hue.service.keytab hue/$FQDN@EXAMPLE.COM
```

- Where `$FQDN` is the host name of the Hue server and `EXAMPLE.COM` is the Hadoop realm, add the following to the `[kerberos]` section in the `/etc/hue/conf/hue.ini` configuration file:

```
[[kerberos]]
# Path to Hue's Kerberos keytab file
hue_keytab=/etc/security/keytabs/hue.service.keytab
# Kerberos principal name for Hue
hue_principal=hue/$FQDN@EXAMPLE.COM
```

- Set the path to `kinit`, based on the OS.

If you do not know the full path to `kinit`, you can find it by issuing the command `whereis kinit`.

The following is an example of setting the path to `kinit` for RHEL/CentOS 6.x:

```
# Path to kinit
# For RHEL/CentOS 6.x, kinit_path is /usr/bin/kinit
kinit_path=/usr/kerberos/bin/kinit
```

- Optionally, for faster performance, you can keep Kerberos credentials cached:

```
ccache_path=/tmp/hue_krb5_ccache
```

- Edit the `/etc/hue/conf/hue.ini` configuration file and set `security_enabled=true` for every component in the configuration file.

10 Save the `/etc/hue/conf/hue.ini` configuration file.

11 Restart Hue:

```
# /etc/init.d/hue start
```

12 Validate the Hue installation.

- To view the current configuration of your Hue server, select **About > Configuration** or http://hue.server:8000/dump_config.

- b. To ensure that Hue server was configured properly, select **About > Check** for misconfiguration or http://hue.server:8000/debug/check_config.

If you detect any potential misconfiguration, fix it and restart Hue.

2.6.2.6. Configuring Phoenix Query Server

The HBase configuration provides most of the settings that enable secure Kerberos environments for Phoenix. However, there are additional configuration properties that complete the setup of Kerberos security for the Phoenix Query Server.

Prerequisite: The value of the `hbase.security.authentication` property in the `$HBASE_CONF_DIR/hbase-site.xml` file must be set to `kerberos`.

Provide the Kerberos principal and keytab for the Phoenix Query Server in the `$HBASE_CONF_DIR/hbase-site.xml` file, as follows:

```
<property>
  <name>phoenix.queryserver.kerberos.principal</name>
  <value>hbase/_HOST@EXAMPLE.COM</value>
  <description>The Kerberos principal name that should be used to run the
Phoenix Query Server process.
  The principal name should be in the form: user/hostname@DOMAIN. If
  "_HOST" is used as the hostname
  portion, it will be replaced with the actual hostname of the running
  instance.
  </description>
</property>

<property>
  <name>phoenix.queryserver.keytab.file</name>
  <value>/etc/security/keytabs/hbase.service.keytab</value>
  <description>Full path to the Kerberos keytab file to use for logging
in the configured Phoenix Query Server service principal.
  </description>
</property>
```

2.6.3. Setting up One-Way Trust with Active Directory

In environments where users from Active Directory (AD) need to access Hadoop Services, set up one-way trust between Hadoop Kerberos realm and the AD (Active Directory) domain.



Important

Hortonworks recommends setting up one-way trust after fully configuring and testing your Kerberized Hadoop Cluster.

2.6.3.1. Configure Kerberos Hadoop Realm on the AD DC

Configure the Hadoop realm on the AD DC server and set up the one-way trust.

1. Add the Hadoop Kerberos realm and KDC host to the DC:

```
ksetup /addkdc $hadoop.realm $KDC-host
```

2. Establish one-way trust between the AD domain and the Hadoop realm:

```
netdom trust $hadoop.realm /Domain:$AD.domain /add /realm /passwordt:
$trust_password
```

3. **(Optional)** If Windows clients within the AD domain need to access Hadoop Services, and the domain does not have a search route to find the services in Hadoop realm, run the following command to create a hostmap for Hadoop service host:

```
ksetup /addhosttorealmmap $hadoop-service-host $hadoop.realm
```



Note

Run the above for each \$hadoop-host that provides services that need to be accessed by Windows clients. For example, Oozie host, WebHCat host, etc.

4. **(Optional)** Define the encryption type:

```
ksetup /SetEncTypeAttr $hadoop.realm $encryption_type
```

Set encryption types based on your security requirements. Mismatched encryption types cause problems.



Note

Run `ksetup /GetEncTypeAttr $krb_realm` to list the available encryption types. Verify that the encryption type is configured for the Hadoop realm in the `krb5.conf`.

2.6.3.2. Configure the AD Domain on the KDC and Hadoop Cluster Hosts

Add the AD domain as a realm to the `krb5.conf` on the Hadoop cluster hosts. Optionally configure encryption types and UDP preferences.

1. Open the `krb5.conf` file with a text editor and make the following changes:

- To `libdefaults`, add the following properties.

- Set the Hadoop realm as default:

```
[libdefaults]
default_domain = $hadoop.realm
```

- Set the encryption type:

```
[libdefaults]
default_tkt_enctypes = $encryption_types
default_tgs_enctypes = $encryption_types
permitted_enctypes = $encryption_types
```

where the `$encryption_types` match the type supported by your environment.

For example:

```
default_tkt_enctypes = aes256-cts aes128-cts rc4-hmac arcfour-hmac-md5
des-cbc-md5 des-cbc-crc
```

```
default_tgs_etypes = aes256-cts aes128-cts rc4-hmac arcfour-hmac-md5
des-cbc-md5 des-cbc-crc
permitted_etypes = aes256-cts aes128-cts rc4-hmac arcfour-hmac-md5
des-cbc-md5 des-cbc-crc
```

- If TCP is open on the KDC and AD Server:

```
[libdefaults]
udp_preference_limit = 1
```

- Add a realm for the AD domain:

```
[realms]
$AD.DOMAIN = {
kdc = $AD-host-FQDN
admin_server = $AD-host-FQDN
default_domain = $AD-host-FQDN
}
```

- Save the krb5.conf changes to all Hadoop Cluster hosts.

2. Add the trust principal for the AD domain to the Hadoop MIT KDC:

```
kadmin
kadmin:addprinc krbtgt/$hadoop.realm@$AD.domain
```

This command will prompt you for the trust password. Use the same password as the earlier step.



Note

If the encryption type was defined, then use the following command to configure the AD principal:

```
kadmin:addprinc -e "$encryption_type"krbtgt/$hadoop.realm@$AD.
domain
```

When defining encryption, be sure to also enter the encryption type (e.g., 'normal')

2.6.4. Configuring Proxy Users

For information about configuring a superuser account that can submit jobs or access HDFS on behalf of another user, see the following information on the Apache site:

[Proxy user - Superusers Acting on Behalf of Other Users.](#)

2.7. Perimeter Security with Apache Knox


2.7.1. Apache Knox Gateway Overview

The Apache Knox Gateway (“Knox”) is a system to extend the reach of Apache™Hadoop® services to users outside of a Hadoop cluster without reducing Hadoop Security. Knox also simplifies Hadoop security for users who access the cluster data and execute jobs.

Knox integrates with Identity Management and SSO systems used in enterprises and allows identity from these systems be used for access to Hadoop clusters.

Knox Gateways provides security for multiple Hadoop clusters, with these advantages:

- **Simplifies access:** Extends Hadoop's REST/HTTP services by encapsulating Kerberos to within the Cluster.
- **Enhances security:** Exposes Hadoop's REST/HTTP services without revealing network details, providing SSL out of the box.
- **Centralized control:** Enforces REST API security centrally, routing requests to multiple Hadoop clusters.
- **Enterprise integration:** Supports LDAP, Active Directory, SSO, SAML and other authentication systems.



Typical Security Flow: Firewall, Routed Through Knox Gateway


Knox can be used with both unsecured Hadoop clusters, and Kerberos secured clusters. In an enterprise solution that employs Kerberos secured clusters, the Apache Knox Gateway provides an enterprise security solution that:

- Integrates well with enterprise identity management solutions
- Protects the details of the Hadoop cluster deployment (hosts and ports are hidden from end users)
- Simplifies the number of services with which a client needs to interact

2.7.1.1. Knox Gateway Deployment Architecture

Users who access Hadoop externally do so either through Knox, via the Apache REST API, or through the Hadoop CLI tools.

The following diagram shows how Apache Knox fits into a Hadoop deployment.



NN=NameNode, RM=Resource Manager, DN=DataNode, NM=NodeManager

2.7.1.2. Supported Hadoop Services

Apache Knox Gateway supports the following Hadoop services versions in both Kerberized and Non-Kerberized clusters:

Table 2.19. Supported Hadoop Services

Service	Version
YARN	2.7.0
WebHDFS	2.7.0
WebHCat/Templeton	0.13.0
Oozie	4.2.0
HBase/Stargate	1.1
Hive (via WebHCat)	1.2.0
Hive (via JDBC)	1.2.0



Note

UIs in the Apache Knox project that are not listed above are considered Community Features.

Community Features are developed and tested by the Apache Knox community but are not officially supported by Hortonworks. These features are excluded for a variety of reasons, including insufficient reliability or incomplete test case coverage, declaration of non-production readiness by the community at large, and feature deviation from Hortonworks best practices. Do not use these features in your production environments.

2.7.1.3. Knox Gateway Samples

There are a number of different methods you can use to deploy the Knox Gateway in your cluster. Each of these methods consists of different ways you can use to install and configure the Knox Gateway. For more information on these methods, refer to the following Apache documentation:

- <http://knox.apache.org/books/knox-0-5-0/knox-0-5-0.html#Gateway+Samples>

2.7.2. Configuring the Knox Gateway

This section describes how to configure the Knox Gateway. This section describes how you can:

- [Create and Secure the Gateway Directories \[86\]](#)
- [Customize the Gateway Port and Path \[87\]](#)
- [Manage the Master Secret \[87\]](#)
- [Manually Redeploy Cluster Topologies \[88\]](#)
- [Manually Start and Stop Apache Knox \[89\]](#)

2.7.2.1. Create and Secure the Gateway Directories

Installing Knox Gateway with the platform-specific installers creates the following directories:

- HADOOP_NODE_INSTALL_ROOT
- `knox-X.X.X.X.X.X-XXXX` – the \$gateway directory.

For example, `D:/hdp/knox-0.4.0.2.1.1.0-1557` The directory contains the following files:

Table 2.20. Apache Service Gateway Directores

Directory/Filename	Description
conf/topologies	Contains global gateway configuration files.
bin	Contains the executable shell scripts, batch files, and JARs for clients and servers.
deployments	Contains cluster topology descriptor files that define Hadoop clusers.
lib	Contains the JARs for all the components that make up the gateway.
dep	Contains the JARs for all of the component upon which the gateway depends.
ext	A directory where user-supplied extensions JARs can be placed to extends the gateway functionality.
samples	Contains a number of samples that can be used to explore the functionality of the gateway.
templates	Contains default configuration files that can be copied and customized.
README	Provides basic informaiton about the Apache Knox Gateway.
ISSUES	Describes significant known issues.
CHANGES	Enumerates the changes between releases.
LICENSE	Documents the license under which this software is provided.
NOTICE	Documents required attribution notices for included dependencies.
DISCLAIMER	Documents that this release is from a project undergoing incubaiton at Apache.

- `SystemDrive/hadoop/logs Knox`

This contains the output files from the Knox Gateway.

2.7.2.2. Customize the Gateway Port and Path

The Knox Gateway properties effect the URL used by the external clients to access the internal cluster. By default the port is set to 8443 and the context path is gateway.

To change the context path or port:

1. Edit `gateway-site.xml` and modify the following properties:

- `propertyname`
- `gateway.port namevalue`
- `gateway.portvalue`

where:

- `$gateway_port` is the HTTP port for the gateway (default port=8443)
- `$gateway` is the context path in the external URL (preconfigured value=gateway). For example, `https://knox.hortonworks.com:8443/hadoop/`, where `hadoop` is the context path.

2. Restart the gateway:

```
cd $gateway.bin/gateway.sh stop bin/gateway.sh start
```

The gateway loads the new configuration on startup.

2.7.2.3. Manage the Master Secret

The master secret is required to start the gateway. The secret protects artifacts used by the gateway instance, such as the keystore, trust stores and credential stores.

You configure the gateway to persist the master secret, which is saved in the `$gateway / data/security/master` file. Ensure that this directory has the appropriate permissions set for your environment. To set the master secret, enter:

```
cd $gateway bin/knoxcli.cmd create-master
```

A warning displays indicating that persisting the secret is less secure than providing it at startup. Knox protects the password by encrypting it with AES 128 bit encryption; where possible, the file permissions are set to be accessible only by the Knox user.



Warning

Ensure that the security directory, `$gateway/data/security`, and its contents are readable and writable only by the Knox user. This is the most important layer of defense for master secret. **Do not assume that the encryption is sufficient protection.**

Changing the Master Secret

The Master Secret can be changed under dire situations where the Administrator has to redo all the configurations for every gateway instance in a deployment, and no longer knows the Master Secret. Recreating the Master Secret requires not only recreating the master, but also removing all existing keystores and reprovisioning the certificates and credentials.

1. To change the Master Secret:

```
cd $gateway bin/knoxcli.cmd create-master--force
```

2. If there is an existing keystore, update the keystore.

2.7.2.4. Manually Redeploy Cluster Topologies

You are not required to manually redeploy clusters after updating cluster properties. The gateway monitors the topology descriptor files in the `$gateway/conf/topologies` directory and automatically redeploys the cluster if any descriptor changes or a new one is added. (The corresponding deployment is in `$gateway/data/deployments`.)

However, you must redeploy the clusters after changing any of the following gateway properties or gateway-wide settings:

- Time settings on the gateway host
- Implementing or updating Kerberos
- Implementing or updating SSL certificates
- Changing a cluster alias

Redeploying all clusters at the same time

When making gateway-wide changes (such as implementing Kerberos or SSL), or if you change the system clock, you must redeploy all the Cluster Topologies. Do the following:

1. To verify the timestamp on the currently deployed clusters enter: `cd $gatewaydir data/deployments`. The system displays something similar to:

```
Directory of C:/hdp/knox-0.4.0.2.1.1.0-1557/data/deployments

04/17/2014 05:30 PM <DIR> .
04/17/2014 05:30 PM <DIR> ..
04/17/2014 05:30 PM <DIR> cluster.war.145514f4dc8
04/17/2014 05:30 PM <DIR> myCluster.war.145514f4dc8
04/11/2014 08:35 AM <DIR> sandbox.war.145514f4dc8
0 File(s) 0 bytes
5 Dir(s) 9,730,977,792 bytes free
```

2. To redeploy all clusters, enter `/bin/knoxcli.cmd redeploy`.
3. To verify that a new cluster WAR was created, enter `cd $gatewaydir data/deployments`. The system displays something similar to:

```
Directory of C:/hdp/knox-0.4.0.2.1.1.0-1557/data/deployments

04/17/2014 05:34 PM <DIR> .
04/17/2014 05:34 PM <DIR> ..
04/17/2014 05:30 PM <DIR> cluster.war.145514f4dc8
```

```
04/17/2014 05:34 PM <DIR> cluster.war.1457241b5dc
04/17/2014 05:30 PM <DIR> myCluster.war.145514f4dc8
04/17/2014 05:34 PM <DIR> myCluster.war.1457241b5dc
04/11/2014 08:35 AM <DIR> sandbox.war.145514f4dc8
04/17/2014 05:34 PM <DIR> sandbox.war.1457241b5dc
0 File(s) 0 bytes
8 Dir(s) 9,730,850,816 bytes free
```

A new file is created for each cluster, with the current timestamp.

Redeploy only specific clusters

When making changes that impact a single cluster, such as changing an alias or restoring from an earlier cluster topology descriptor file, you only redeploy the effected cluster. Do the following:

1. To verify the timestamp on the currently deployed Cluster Topology WAR files, enter: `cd $gatewaydir data/deployments`. The system displays something similar to:

```
Directory of C:/hdp/knox-0.4.0.2.1.1.0-1557/data/deployments

04/17/2014 05:30 PM <DIR> .
04/17/2014 05:30 PM <DIR> ..
04/17/2014 05:30 PM <DIR> cluster.war.145514f4dc8
04/17/2014 05:30 PM <DIR> myCluster.war.145514f4dc8
04/11/2014 08:35 AM <DIR> sandbox.war.145514f4dc8
0 File(s) 0 bytes
5 Dir(s) 9,730,977,792 bytes free
```

2. To redeploy a specific cluster, enter:

```
cd $gateway bin/knoxcli.cmd redeploy --cluster $cluster_name
```

where `$cluster_name` is the name of the cluster topology descriptor (without the `.xml` extension). For example, `myCluster`.

3. To verify that the cluster was deployed, enter: `cd $gatewaydir data/deployments`. The system displays something similar to:

```
Directory of C:/hdp/knox-0.4.0.2.1.1.0-1557/data/deployments

04/17/2014 05:30 PM <DIR> .
04/17/2014 05:30 PM <DIR> ..
04/17/2014 05:30 PM <DIR> cluster.war.145514f4dc8
04/17/2014 05:30 PM <DIR> myCluster.war.145514f4dc8
04/17/2014 05:34 PM <DIR> myCluster.war.1457241b5dc
04/11/2014 08:35 AM <DIR> sandbox.war.145514f4dc8
0 File(s) 0 bytes
5 Dir(s) 9,730,977,792 bytes free
```

You should see that existing cluster war files are unchanged, but the war file for `myCluster` was updated (has a current timestamp).

2.7.2.5. Manually Start and Stop Apache Knox

Except for changes to `../conf/topology/*.xml`, changes to the Knox Gateway global settings in `$gateway /conf/gateway-site.xml` cannot be loaded before the Gateway is restarted.

To manually stop Knox:

```
cd $gateway/bin/gateway.sh stop
```

This is known as a clean shutdown, as the gateway script cleans out all `.out` and `.err` files in the logs directory.

To manually start Knox for the first time, or re-start Knox after a clean shutdown:

```
cd $gateway /bin/gateway.sh start
```

To manually re-start Knox after an unclean shutdown:

```
cd $gateway/bin/gateway.sh clean /bin/gateway.sh start
```

This command eliminates old `.out` and `.err` files in the logs directory.

2.7.3. Defining Cluster Topologies

The Knox Gateway supports one or more Hadoop clusters. Each Hadoop cluster configuration is defined in a topology deployment descriptor file in the `$gateway/conf/topologies` directory and is deployed to a corresponding WAR file in the `$gateway/data/deployments` directory. These files define how the gateway communicates with each Hadoop cluster.

The descriptor is an XML file contains the following sections:

- `gateway/provider` – configuration settings enforced by the Knox Gateway while providing access to the Hadoop cluster.
- `service` – defines the Hadoop service URLs used by the gateway to proxy communications from external clients.

The gateway automatically redeploys the cluster whenever it detects a new topology descriptor file, or detects a change in an existing topology descriptor file.

The following table provides an overview of the providers and services:

Table 2.21. Cluster Topology Provider and Service Roles

Type	Role	Description
gateway/provider	hostmap	Maps external to internal node hostnames, replacing the internal hostname with the mapped external name when the hostname is embedded in a response from the cluster.
	authentication	Integrates an LDAP store to authenticate external requests accessing the cluster via the Knox Gateway. Refer to Set Up LDAP Authentication for more information.
	federation	Defines HTTP header authentication fields for an SSO or federation solution provider. Refer to Set up HTTP Header Authentication for Federation/SSO
	identity-assertion	Responsible for the way that the authenticated user's identity is asserted

Type	Role	Description
		to the service that the request is intended for. Also maps external authenticated users to an internal cluster that the gateway asserts as the current session user or group. Refer to Configure Identity Assertion for more information.
	authorization	Service level authorization that restricts cluster access to specified users, groups, and/or IP addresses. Refer to Configure Service Level Authorization for more information.
	webappspec	Configures a web application security plugin that provides protection filtering against Cross Site Request Forgery Attacks. Refer to Configure Web Application Security for more information.
HA provider	high availability	Syncs all Knox instances to use the same topologies credentials keystores.
service	\$service_name	Binds a Hadoop service with an internal URL that the gateway uses to proxy requests from external clients to the internal cluster services. Refer to Configure Hadoop Service URLs for more information.

Cluster topology descriptors have the following XML format:

```
<topology>
  <gateway>
    <provider>
      <role></role>
      <name></name>
      <enabled></enabled>
      <param>
        <name></name>
        <value></value>
      </param>
    </provider>
  </gateway>
  <service></service>
</topology>
```

2.7.4. Configuring a Hadoop Server for Knox

The Apache Knox Gateway redirects external requests to an internal Hadoop service using service name and URL of the service definition.

This chapter describes:

- [Setting up Hadoop Service URLs \[92\]](#)
- [Example Service Definitions \[92\]](#)
- [Validating Service Connectivity \[93\]](#)
- [Adding a New Service to the Knox Gateway \[95\]](#)

2.7.4.1. Setting up Hadoop Service URLs

To configure access to an internal Hadoop service through the Knox Gateway:

1. Edit `$gateway/conf/topologies$cluster-name.xml` to add an entry similar to the following, for each Hadoop service:

```
<topology>
  <gateway>
    ...
  </gateway>
  <service>
    <role> $service_name </role>
    <url> $schema://$hostname:$port</url>
  </service>
</topology>
```

where:

- `$service_name` is either WEBHDFS, WEBHCAT, WEBHBASE, OOZIE, HIVE, NAMENODE, or JOBTRACKER.
- `<url>` is the complete internal cluster URL required to access the service, including:
 - `$schema` – the service protocol
 - `$hostname` – the resolvable internal host name
 - `$port` – the service listening port

2. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.



Note

It is not necessary to restart the Knox server after making changes to the topology/Hadoop Cluster services.

2.7.4.2. Example Service Definitions

Configure each service that you want to expose externally, being careful to define the internal hostname and service ports of your cluster.

The following example uses the defaults ports and supported service names.

```
<service>
  <role>NAMENODE</role>
  <url>hdfs://namenode-host:8020</url>
</service>

<service>
  <role>JOBTRACKER</role>
  <url>rpc://jobtracker-host:8050</url>
</service>
```

```

<service>
  <role>RESOURCEMANAGER</role>
  <url>http://red3:8088/ws</url>
</service>

<service>
  <role>WEBHDFS</role>
  <url>http://localhost:50070/webhdfs</url>
</service>

<service>
  <role>WEBHCAT</role>
  <url>http://webcat-host:50111/templeton</url>
</service>

<service>
  <role>OOZIE</role>
  <url>http://oozie-host:11000/oozie</url>
</service>

<service>
  <role>WEBHBASE</role>
  <url>http://webhbase-host:60080</url>
</service>

<service>
  <role>HIVE</role>
  <url>http://hive-host:10001/cliservice</url>
</service>

```

2.7.4.3. Validating Service Connectivity

Use the commands in this section to test connectivity between the gateway host and the Hadoop service, and then test connectivity between an external client to the Hadoop service through the gateway.



Tip

If the communication between the gateway host and an internal Hadoop service fails, telnet to the service port to verify that the gateway is able to access the cluster node. Use the hostname and ports you specified in the service definition.

Testing WebHDFS by getting the home directory

- At the gateway host, enter the following command:

```
curl http://$webhdfs-host:50070/webhdfs/v1?op=GETHOMEDIRECTORY
```

The host displays:

```
{ "Path" : "/user/gopher" }
```

- At an external client, enter the following command:

```
curl https://$gateway-host:$gateway_port/$gateway/$cluster_name/
$webhdfs_service_name/v1?op=GETHOMEDIRECTORY
```

The external client displays:

```
{ "Path": "/user/gopher" }
```

Testing WebHCat/Templeton by getting the version

- At the gateway host, enter the following command:

```
curl http://$webhdfs-host:50111/templeton/v1/version
```

The host displays:

```
{ "supportedVersions": [ "v1" ], "version": "v1" }
```

- At an external client, enter the following command:

```
curl https://$gateway-host:$gateway_port/$gateway/$cluster_name/  
$webhcat_service_name/v1/version
```

The external client displays:

```
{ "supportedVersions": [ "v1" ], "version": "v1" }
```

Testing Oozie by getting the version

- At the gateway host, enter the following command:

```
curl http://$oozie-host:11000/oozie/v1/admin/build-version
```

The host displays:

```
{ "buildVersion": "4.0.0.2.1.1.0-302" }
```

- At an external client, enter the following command:

```
curl https://$gateway-host:$gateway_port/$gateway/$cluster_name/  
$oozie_service_name/v1/admin/build-version
```

The external client displays:

```
{ "buildVersion": "4.0.0.2.1.1.0-302" }
```

Testing HBase/Stargate by getting the version

- At the gateway host, enter the following command:

```
curl http://$hbase-host:17000/version
```

The host displays:

```
rest 0.0.2 JVM: Oracle Corporation 1.7.0_51-24.45-b08 OS: Linux 3.8.0-29-  
generic amd64 Server:jetty/6.1.26 Jersey:1.8:
```

- At an external client, enter the following command:

```
curl http://$hbase-host:17000/version
```

The external client displays:

```
rest 0.0.2 JVM: Oracle Corporation 1.7.0_51-24.45-b08 OS: Linux 3.8.0-29-  
generic amd64 Server:jetty/6.1.26 Jersey:1.8
```

Testing HiveServer2

Both of the following URLs return an authentication error, which users can safely ignore.

1. At the gateway host, enter:

```
curl http://$hive-host:10001/cliservice
```

2. At an external client, enter:

```
curl https://$gateway-host:$gateway_port/$gateway/$cluster_name/$hive_service_name/cliservice
```

2.7.4.4. Adding a New Service to the Knox Gateway

Services and service additions in the Knox Gateway are defined as extensions to existing Knox Gateway functionality that enable you to extend the gateway's capabilities. You use these services to convert information contained in the topology file to runtime descriptors.

The Knox Gateway supports a declarative way for you to "plug in" a new service into the gateway simply and easily by using the following two files:

- `service.xml`- file that contains the routes (paths) that the service will provide and the rewrite rules to bind these paths.
- `rewrite.xml` – file that contains the rewrite rules for the service.



Note

The `service.xml` file is required, whereas the `rewrite.xml` file is optional.

2.7.4.4.1. Service Directory Structure

The Knox Gateway consists of a directory structure that you should become familiar with before attempting to add a new service to the gateway.

If you navigate to the data directory in your Knox home directory (`{GATEWAY_HOME}/data`), you will see the following directory structure:

```
Services
  Service name
    Version
      service.xml
      rewrite.xml
```

For example, if you were to navigate to the WebHDFS Service directory, you would see the following directory structure:

```
Services
  WebHDFS
    2.4.0
      service.xml
      rewrite.xml
```

2.7.4.4.2. Adding a New Service to the Knox Gateway

Adding a new service to the Knox gateway is a very easy and straightforward process, only requiring you to perform a few simple steps, which are listed below.

1. Navigate to the services directory in your Knox gateway HOME directory (`{GATEWAY_HOME}/data/services`)
2. Add the `service.xml` and `rewrite.xml` files to the directory.



Note

If you want to add the service to the Knox build, then add the `service.xml` and `rewrite` files to the `gateway-services-definitions` module.

2.7.5. Mapping the Internal Nodes to External URLs

Hostmapping is an advanced configuration topic. Generally, it is only required in deployments in virtualized environments, such as Cloud deployments and some development and testing environments.

The isolation of the Hadoop cluster is accomplished through virtualization that will hide the internal networking details (such as IP addresses and/or hostnames) from the outside world, while exposing other IP addresses and/or hostnames for use by clients accessing the cluster from outside of the virtualized environment. The exposed IP addresses and hostnames are available for use in the topology descriptor service definitions. This configuration works great for requests that are initiated from the external clients themselves which only ever use the Knox Gateway exposed endpoints.

Difficulties from these virtualized environments arise when the Hadoop cluster redirects client requests to other nodes within the cluster and indicates the internal hostname locations, rather than those designated to be exposed externally. Since the Hadoop services don't know or care whether a request is coming from an external or internal client, it uses its only view of the cluster, which is the internal details of the virtualized environment.

The Knox Gateway needs to know how to route a request that has been redirected by the Hadoop service to an address that is not actually accessible by the gateway. Hostmapping acts as an adapter that intercepts the redirects from the Hadoop service and converts the indicated internal address to a known external address that Knox will be able to route to once the client resends the request through the client facing gateway endpoint. The gateway uses the `hostmap` to replace the internal hostname within the routing policy for the particular request with the externally exposed hostname. This enables the dispatching from the Knox Gateway to successfully connect to the Hadoop service within the virtualized environment. Otherwise, attempting to route to an internal-only address will result in connection failures.

A number of the REST API operations require multi-step interactions that facilitate the client's interaction with multiple nodes within a distributed system such as Hadoop. External clients performing multi-step operations use the URL provided by the gateway in the responses to form the next request. Since the routing policy is hidden by the gateway from the external clients, the fact that the subsequent requests in the multi-stepped interaction are mapped to the appropriate externally exposed endpoints is not exposed to the client.

For example, when uploading a file with WebHDFS service:

1. The external client sends a request to the gateway WebHDFS service.

2. The gateway proxies the request to WebHDFS using the service URL.
3. WebHDFS determines which DataNodes to create the file on and returns the path for the upload as a Location header in a HTTP redirect, which contains the datanode host information.
4. The gateway augments the routing policy based on the datanode hostname in the redirect by mapping it to the externally resolvable hostname.
5. The external client continues to upload the file through the gateway.
6. The gateway proxies the request to the datanode by using the augmented routing policy.
7. The datanode returns the status of the upload and the gateway again translates the information without exposing any internal cluster details.

2.7.5.1. Setting Up a Hostmap Provider

Add the `hostmap` provider to the cluster topology descriptor and a parameter for each DataNode in the cluster, as follows:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add the Hostmap provider to `topology/gateway` using the following format:

```
<provider>
  <role>hostmap</role>
  <name>static</name>
  <enabled>true</enabled>
  <param>
    <name>$external-name</name>
    <value>$internal-dn-host</value>
  </param>
</provider>
```

where:

- `$cluster-name.xml` is the name of the topology descriptor file, located in `$gateway/conf/topologies`.
 - `$external-name` is the value that the gateway uses to replace `$internal_host` host names in responses.
 - `$internal-dn-host` is a comma-separated list of host names that the gateway will replace when rewriting responses.
3. To the `hostmap` provider, add a `param` for each additional DataNode in your cluster:

```
<param> <name> $external-name2 </name> <value> $internal-dn2-host </value> </param>
```
 4. Save the file.

Saving the results automatically deploys the topology with the change. The result is the creation of a new WAR file with modified timestamp in `$gateway/data/deployments`.

2.7.5.2. Example of an EC2 Hostmap Provider

In this EC2 example two VMs have been allocated. Each VM has an external hostname by which it can be accessed via the internet. However the EC2 VM is unaware of this external host name, and instead is configured with the internal hostname.

- **External hostnames** - ec2-23-22-31-165.compute-1.amazonaws.com, ec2-23-23-25-10.compute-1.amazonaws.com
- **Internal hostnames** - ip-10-118-99-172.ec2.internal, ip-10-39-107-209.ec2.internal

The following shows the Hostmap definition required to allow access external to the Hadoop cluster via the Apache Knox Gateway.

```
<topology>
  <gateway>
    ...
    <provider>
      <role>hostmap</role>
      <name>static</name>
      <enabled>true</enabled>
      <!-- For each host enter a set of parameters -->
      <param>
        <name>ec2-23-22-31-165.compute-1.amazonaws.com</name>
        <value>ip-10-118-99-172.ec2.internal</value>
      </param>
      <param>
        <name>ec2-23-23-25-10.compute-1.amazonaws.com</name>
        <value>ip-10-39-107-209.ec2.internal</value>
      </param>
    </provider>
    ...
  </gateway>
  <service>
    ...
  </service>
  ...
</topology>
```

2.7.5.3. Example of Sandbox Hostmap Provider

Hortonwork's Sandbox 2.x poses a different challenge for hostname mapping. This Sandbox version uses port mapping to make Sandbox appear as though it is accessible via localhost. However, Sandbox is internally configured to consider sandbox.hortonworks.com as the hostname. So from the perspective of a client accessing Sandbox the external host name is localhost.

The following shows the `hostmap` definition required to allow access to Sandbox from the local machine:

```
<topology>
  <gateway>
    ...
    <provider>
      <role>hostmap</role>
      <name>static</name>
      <enabled>true</enabled>
```

```
<param>
  <name>localhost</name>
  <value>sandbox,sandbox.hortonworks.com</value>
</param>
</provider>
...
<gateway>
...
</topology>
```

2.7.5.4. Enabling Hostmap Debugging



Warning

Changing the rootLogger value from ERROR to DEBUG generates a large amount of debug logging.

Enable additional logging by editing the `gateway-log4j.properties` file in the directory.

1. Edit the `$gateway /conf/gateway-log4j.properties` file to enable additional logging.
2. Change ERROR to DEBUG on the following line:

```
log4j.rootLogger=ERROR, drfa
```



Warning

Changing the rootLogger value from ERROR to DEBUG generates a large amount of debug logging.

3. Stop and then restart the gateway:

```
cd $gateway bin/gateway.sh stop bin/gateway.sh start
```

2.7.6. Configuring Authentication

Apache Knox Gateway supports authentication using either an LDAP or federation provider for each configured cluster. This section explains how to configure authentication:

- [Setting Up LDAP Authentication \[100\]](#)
- [LDAP Authentication Caching \[101\]](#)
- [Example Active Directory Configuration \[103\]](#)
- [Example OpenLDAP Configuration \[106\]](#)
- [Testing an LDAP Provider \[107\]](#)
- [Setting Up HTTP Header Authentication for Federation_SSO \[107\]](#)
- [Example SiteMinder Configuration \[108\]](#)

- [Testing HTTP Header Tokens \[109\]](#)
- [Setting Up 2-Way SSL Authentication \[109\]](#)



Note

For information on how to configure an identity assertion provider, see [Configuring Identity Assertion](#).

2.7.6.1. Setting Up LDAP Authentication

LDAP authentication is configured by adding a "ShiroProvider" authentication provider to the cluster's topology file. When enabled, the Knox Gateway uses Apache Shiro (org.apache.shiro.realm.ldap.JndiLdapRealm) to authenticate users against the configured LDAP store.



Note

Knox Gateway provides HTTP BASIC authentication against an LDAP user directory. It currently supports only a single Organizational Unit (OU) and does not support nested OUs.

To enable LDAP authentication:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add the `ShiroProvider` authentication provider to `/topology/gateway` as follows:

```
<provider>
  <role>authentication</role>
  <name>ShiroProvider</name>
  <enabled>>true</enabled>
  <param>
    <name>main.ldapRealm</name>
    <value>org.apache.shiro.realm.ldap.JndiLdapRealm</value>
  </param>
  <param>
    <name>main.ldapRealm.userDnTemplate</name>
    <value>${USER_DN}</value>
  </param>
  <param>
    <name>main.ldapRealm.contextFactory.url</name>
    <value>${protocol}://${ldaphost}:${port}</value>
  </param>
  <param>
    <name>main.ldapRealm.contextFactory.authenticationMechanism</name>
    <value>simple</value>
  </param>
  <param>
    <name>urls./*</name>
    <value>${auth_type}</value>
  </param>
  <param>
    <name>sessionTimeout</name>
    <value>${minutes}</value>
  </param>
</provider>
```

```
</param>
</provider>
```

where:

- `$USER_DN`

is a comma-separated list of attribute and value pairs that define the User Distinguished Name (DN). The first pair must be set to "`$attribute_name={0}`" indicating that the `$attribute_name` is equal to the user token parsed from the request. For example, the first attribute in an OpenLdap definition is `UID={0}`. The `main.ldapRealm.userDnTemplate` parameter is only required when authenticating against an LDAP store that requires a full User DN.

- `$protocol :// $ldaphost : $port`

is the URL of the LDAP service, Knox Gateway supports LDAP or LDAPS protocols.

- `$auth_type`

is either `authcBasic`, which provides basic authentication for both secured and non-secured requests, or `ssl authcBasic`, which rejects non-secured requests and provides basic authentication of secured requests.

- `$minutes`

is the session idle time in minutes, the default timeout is 30 minutes.

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.



Note

If the Active Directory and Kerberos names differ in case (e.g. the Active Directory name is in upper case and the Kerberos name is lower case), the Knox Gateway enables you to resolve this conflict using the `auth_to_local` flag.

You can also configure LDAP authentication over SSL by following the steps below.

1. Change the LDAP protocol from `ldap://` to `ldaps://`.
2. If LDAP is using a self-signed certificate, then import the LDAP's certificate into the CACerts file of the Java Virtual Machine (JVM) being used to run the Apache Knox Gateway. To import the LDAP certificate, enter the following commands:

```
%JAVA_HOME%\bin\keytool
-import -trustcerts -alias ldap_ssl -file C:\temp\FileFromLDAP.cert -
keystore %JAVA_HOME%\jre/lib/security/cacerts -storepass "changeit"
```

2.7.6.2. LDAP Authentication Caching

You can also configure the Apache Knox Gateway to cache LDAP authentication information by leveraging built-in caching mechanisms that the Shiro EhCache Manager

provides. The ability to cache LDAP authentication information is useful in eliminating the need to authenticate against the LDAP server each time you use.



Note

When the authentication information is cached, the Knox gateway will not authenticate the user again until the cache expires.

To enable LDAP authentication caching using the Shiro Provider, follow the steps listed below.

1. Use the `org.apache.hadoop.gateway.shirorealm.KnoxLdapRealm` in the Shiro configuration.
2. Set the `main.ldaprealm.authenticationCachingEnabled` property similar to the example shown below.

```
<provider>
  <role>authentication</role>
  <enabled>>true</enabled>
  <param>
    <name>main.ldapRealm</name>
    <value>org.apache.hadoop.gateway.shirorealm.KnoxLdapRealm</value>
  </param>
  <param>
    <name>main.ldapGroupContextFactory</name>
    <value>org.apache.hadoop.gateway.shirorealm.KnoxLdapContextFactory</
value>
  </param>
  <param>
    <name>main.ldapRealm.ContextFactory</name>
    <value>$ldapGroupContextFactory</value>
  </param>
  <param>
    <name>main.ldapRealm.ContextFactory.url</name>
    <value>$ldap://localhost:33389</value>
  </param>
  <param>
    <name>main.ldapRealm.authorizationEnabled</name>
    <value>>true</value>
  </param>
  <param>
    <name>main.ldapRealm.searchBase</name>
    <value>ou-groups,dc=hadoop,dc=apache,dc=org</value>
  </param>
  <param>
    <name>main.cacheManager</name>
    <value>org.apache.shiro.cache.ehcache.EhCacheManager</value>
  </param>
  <param>
    <name>main.securityManager.cacheManager</name>
    <value>$cacheManager</value>
  </param>
  <param>
    <name>main.ldapRealm.authenticationCachingEnabled</name>
    <value>true</value>
  </param>
  <param>
    <name>main.ldapRealm.memberAttributeValueTemplate</name>
```

```

        <value>uid={0}ou=people,dc=hadoop,dc=apache,dc=org</value>
    </param>
    <param>
        <name>main.ldapRealm.contextFactory.systemUsername</name>
        <value>uid=guest,ou=people,dc=hadoop,dc=apache,dc=org</value>
    </param>
    <param>
        <name>main.ldapRealm.contextFactory.systemPassword</name>
        <value>guest=password</value>
    </param>
    <param>
        <name>urls./*</name>
        <value>authBasic</value>
    </param>
</provider>

```

In this example, you need to configure these properties to set the Knox Gateway for LDAP authentication caching. The Knox Gateway also includes several template topology files that you can use to test the caching function. You can locate these template files in the templates directory. To test the caching function, perform the steps listed below.

- a. Navigate to the Knox gateway HOME directory.

```
cd {GATEWAY_HOME}
```

- b. Copy the templates files to your sandbox.

```
cp templates/sandbox.knoxrealm.ehcache.xml
conf.topologies/sandbox.xml
```

- c. Start the LDAP authentication provider.

```
bin/ldap.sh start
```

- d. Start the Knox gateway.

```
bin/gateway.sh start
```

- e. Once the gateway is started, make the following WebHDFS API call:

```
curl -ivk -u tom:tom-password -X GET
https://localhost:8443/gateway/sandbox/webhdfs/v1?op=GETHOMEDIRECTORY
```

- f. To see LDAP authentication caching working, shut down the LDAP authentication provider.

```
bin/ldap.sh stop
```

- g. Run the WebHDFS API call again.

```
curl -ivk -u tom:tom=password -X GET
https://localhost:8443/gateway/sandbox/webhdfs/v1?op=GETHOMEDIRECTORY
```

2.7.6.3. Example Active Directory Configuration

Typically the AD `main.ldapRealm.userDnTemplate` value looks slightly different than OpenLDAP. The value for `main.ldapRealm.userDnTemplate` is only required if AD authentication requires the full User DN.



Note

If Active Directory allows authentication based on the Common Name (CN) and password only, then no value will be required for `main.ldapRealm.userDnTemplate`.

```
<topology>
    <gateway>
        <provider>
            <role>authentication</role>
            <name>ShiroProvider</name>
            <enabled>>true</enabled>
            <param>
                <name>sessionTimeout</name>
                <value>30</value>
            </param>
            <param>
                <name>main.ldapRealm</name>
                <value>org.apache.hadoop.gateway.shirorealm.
KnoxLdapRealm</value>
            </param>
        </provider>
    </gateway>
<!-- changes for AD/user sync -->
<param>
    <name>main.ldapContextFactory</name>
    <value>org.apache.hadoop.gateway.shirorealm.KnoxLdapContextFactory</value>
</param>
<!-- main.ldapRealm.contextFactory needs to be placed before other main.
ldapRealm.contextFactory* entries -->
<param>
    <name>main.ldapRealm.contextFactory</name>
    <value>$ldapContextFactory</value>
</param>
<!-- AD url -->
<param>
    <name>main.ldapRealm.contextFactory.url</name>
    <value>ldap://ad01.lab.hortonworks.net:389</value>
</param>
<!-- system user -->
<param>
    <name>main.ldapRealm.contextFactory.systemUsername</name>
    <value>cn=ldap-reader,ou=ServiceUsers,dc=lab,dc=hortonworks,dc=net</value>
</param>
<!-- pass in the password using the alias created earlier -->
<param>
    <name>main.ldapRealm.contextFactory.systemPassword</name>
    <value>${ALIAS=knoxLdapSystemPassword}</value>
</param>
    <param>
        <name>main.ldapRealm.contextFactory.
authenticationMechanism</name>
```

```

        <value>simple</value>
      </param>
    <param>
      <name>urls./**</name>
      <value>authcBasic</value>
    </param>

<!-- AD groups of users to allow -->
<param>
  <name>main.ldapRealm.searchBase</name>
  <value>ou=CorpUsers,dc=lab,dc=hortonworks,dc=net</value>
</param>
<param>
  <name>main.ldapRealm.userObjectClass</name>
  <value>person</value>
</param>
<param>
  <name>main.ldapRealm.userSearchAttributeName</name>
  <value>sAMAccountName</value>
</param>

<!-- changes needed for group sync-->
<param>
  <name>main.ldapRealm.authorizationEnabled</name>
  <value>>true</value>
</param>
<param>
  <name>main.ldapRealm.groupSearchBase</name>
  <value>ou=CorpUsers,dc=lab,dc=hortonworks,dc=net</value>
</param>
<param>
  <name>main.ldapRealm.groupObjectClass</name>
  <value>group</value>
</param>
<param>
  <name>main.ldapRealm.groupIdAttribute</name>
  <value>cn</value>
</param>

    </provider>

    <provider>
      <role>identity-assertion</role>
      <name>Default</name>
      <enabled>true</enabled>
    </provider>

    <provider>
      <role>authorization</role>
      <name>XASecurePDPKnox</name>
      <enabled>true</enabled>
    </provider>

  </gateway>

  <service>
    <role>NAMENODE</role>
    <url>hdfs://{{namenode_host}}:{{namenode_rpc_port}}</url>
  </service>

```

```

    <service>
      <role>JOBTRACKER</role>
      <url>rpc://{rm_host}::{jt_rpc_port}</url>
    </service>

    <service>
      <role>WEBHDFS</role>
      <url>http://{namenode_host}::{namenode_http_port}/webhdfs/
url>
    </service>

    <service>
      <role>WEBHCAT</role>
      <url>http://{webhcat_server_host}::{templeton_port}/
templeton</url>
    </service>

    <service>
      <role>OOZIE</role>
      <url>http://{oozie_server_host}::{oozie_server_port}/
oozie</url>
    </service>

    <service>
      <role>WEBHBASE</role>
      <url>http://{hbase_master_host}::{hbase_master_port}</url>
    </service>

    <service>
      <role>HIVE</role>
      <url>http://{hive_server_host}::{hive_http_port}}/
{{hive_http_path}}</url>
    </service>

    <service>
      <role>RESOURCEMANAGER</role>
      <url>http://{rm_host}::{rm_port}}/ws</url>
    </service>
  </topology>

```

2.7.6.4. Example OpenLDAP Configuration

```

<provider>
  <role>authentication</role>
  <name>ShiroProvider</name>
  <enabled>true</enabled>
  <param>
    <name>main.ldapRealm</name>
    <value>org.apache.hadoop.gateway.shiorealm.KnoxLdapRealm</value>
  </param>
  <param>
    <name>main.ldapContextFactory</name>
    <value>org.apache.hadoop.gateway.shiorealm.KnoxLdapContextFactory</
value>
  </param>
  <param>
    <name>mainLdapRealm.contextFactory</name>
    <value>$ldapContextFactory</value>
  </param>

```

```
</provider>
```

2.7.6.5. Testing an LDAP Provider

Using cURL, you can test your LDAP configuration as follows:

1. Open the command line on an external client.



Note

cURL is not a built-in command line utility in Windows.

2. Enter the following command to list the contents of the directory `tmp/test`:

```
curl -i -k -u ldap_user : password -X GET / 'https:// gateway_host :8443/
gateway_path / cluster_name /webhdfs/api/v1/tmp/test?op=LISTSTATUS
```

If the directory exists, a content list displays; if the user cannot be authenticated, the request is rejected with an HTTP status of **401 unauthorized**.

2.7.6.6. Setting Up HTTP Header Authentication for Federation_SSO

The Knox Gateway supports federation solution providers by accepting HTTP header tokens. This section explains how to configure HTTP header fields for SSO or Federation solutions that have simple HTTP header-type tokens. For further information, see the [Authentication](#) chapter of the Apache Knox 0.6.0 User's Guide.

The gateway extracts the user identifier from the HTTP header field. The gateway can also extract the group information and propagate it to the Identity-Assertion provider.



Important

The Knox Gateway federation plug-in, `HeaderPreAuth`, trusts that the content provided in the authenticated header is valid. Using this provider requires proper network security.

Only use the `HeaderPreAuth` federation provider in environments where the identity system does not allow direct access to the Knox Gateway. Allowing direct access exposes the gateway to identity spoofing. Hortonworks recommends defining the `preauth.ip.addresses` parameter to ensure requests come from a specific IP addresses only.

To configure the HTTP header tokens:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a `HeaderPreAuth` federation provider to `topology/gateway` as follows:

```
<provider>
  <role>federation</role>
  <name>HeaderPreAuth</name>
  <enabled>>true</enabled>
  <param>
    <name>preauth.validation.method</name>
    <value>$validation_type</value>
```

```

    </param>
    <param>
      <name>preauth.ip.addresses</name>
      <value>$trusted_ip</value>
    </param>
    <param>
      <name>preauth.custom.header</name>
      <value>$user_field</value>
    </param>
    <param>
      <name>preauth.custom.group.header</name>
      <value>$group_field</value>
    </param>
  </provider>

```

where the values of the parameters are specific to your environment:

- `$validation_type` (Optional, recommended)

Indicates the type of trust, use either `preauth.ip.validation` indicating to trust only connections from the address defined in `preauth.ip.addresses` OR null (omitted) indicating to trust all IP addresses.

- `$trusted_ip` (Required when the pre-authentication method is set to `preauth.ip.validation`)

A comma-separated list of IP addresses, addresses may contain a wild card to indicate a subnet, such as `10.0.0.*`.

- `$user_field`

The name of the field in the header that contains the user name that the gateway extracts. Any incoming request that is missing the field is refused with **HTTP status 401, unauthorized**. If not otherwise specified, the default value is `SM_USER`.

- `$group_field` (Optional)

The name of the field in the header that contains the group name that the gateway extracts. Any incoming request that is missing the field results in no group name being extracted and the connection is allowed.

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.

2.7.6.7. Example SiteMinder Configuration

The following example is the bare minimum configuration for SiteMinder (with no IP address validation):

```

<provider>
  <role>federation</role>
  <name>HeaderPreAuth</name>
  <enabled>true</enabled>
  <param>

```

```

    <name>preauth.custom.header</name>
    <value>SM_USER</value>
  </param>
  <param>
    <name>preauth.ip.addresses</name>
    <value>10.10.0.*</value>
  </param>
</provider>

```

2.7.6.8. Testing HTTP Header Tokens

Use following cURL command to request a directory listing from HDFS while passing in the expected header `SM_USER`, note that the example is specific to sandbox:

```
curl -k -i --header "SM_USER: guest" -v 'https://localhost:8443/gateway/sandbox/webhdfs/v1/tmp?op=LISTSTATUS'
```

Omitting the `SM_USER: guest` above results in a **HTTP status 401 unauthorized**

2.7.6.9. Setting Up 2-Way SSL Authentication

Mutual authentication with SSL provides the Knox gateway with the means to establish a strong trust relationship with another party. This is especially useful when applications that act on behalf of end-users send requests to Knox. While this feature does establish an authenticated trust relationship with the client application, it does not determine the end-user identity through this authentication. It will continue to look for credentials or tokens that represent the end-user within the request and authenticate or federate the identity accordingly.

To configure your Knox Gateway for 2-way SSL authentication, you must first configure the trust related elements within `gateway-site.xml` file. The table below lists the different elements that you can configure related to 2-way mutual authentication. Use following cURL command to request a directory listing from HDFS while passing in the expected header `SM_USER`, note that the example is specific to sandbox:

Table 2.22. gateway-site.xml Configuration Elements

Name	Description	Possible Values	Default Value
<code>gateway.client.auth.needed</code>	Flag used to specify whether authentication is required for client communications to the server.	TRUE/FALSE	FALSE
<code>gateway.truststore.path</code>	The fully-qualified path to the truststore that will be used.		<code>gateway.jks</code>
<code>gateway.truststore.type</code>	The type of keystore used for the truststore.		JKS
<code>gateway.trust.allcerts</code>	Flag used to specify whether certificates passed by the client should be automatically trusted.	TRUE/FALSE	FALSE

Once you have configured the `gateway-site.xml` file, all topologies deployed within the Knox gateway with mutual authentication enabled will require all incoming connections to

present trusted client certificates during the SSL handshake process; otherwise, the server will be refuse the connection request.

2.7.7. Configuring Identity Assertion

The Knox Gateway `identity-assertion` provider maps an authenticated user to an internal cluster user and/or group. This allows the Knox Gateway accept requests from external users without requiring internal cluster user names to be exposed.

The gateway evaluates the authenticated user against the `identity-assertion` provider to determine the following:

1. Does the user match any user mapping rules:
 - **True:**The first matching `$cluster_user` is asserted, that is it becomes the authenticated user.
 - **False:**The authenticated user is asserted.
2. Does the authenticated user match any group mapping rules:
 - **True:**The authenticated user is a member of all matching groups (for the purpose of authorization).
 - **False:**The authenticated user is not a member of any mapped groups.



Note

When authenticated by an SSO provider, the authenticated user is a member of all groups defined in the request as well as any that match the `group.principal.mapping`.

2.7.7.1. Structure of the Identity-Assertion Provider

All cluster topology descriptors must contain an `identity-assertion` provider in the `topology/gateway` definition.

The following is the complete structure of the `identity-assertion` provider. The parameters are optional.

```
<provider>
  <role>identity-assertion</role>
  <name>Pseudo</name>
  <enabled>>true</enabled>
  <param>
    <name>principal.mapping</name>
    <value> $user_ids = $cluster_user [; $user_ids = $cluster_user1 ;...]</value>
  </param>
  <param>
    <name>group.principal.mapping</name>
    <value> $cluster_users = $group1 ; $cluster_users = $group2 </value>
  </param>
</provider>
```

where:

- `$user_ids` is a comma-separated list of external users or the wildcard (*) indicates all users.
- `$cluster_user` the Hadoop cluster user name the gateway asserts, that is the authenticated user name.



Note

Note that identity-assertion rules are not required; however, whenever an authentication provider is configured an `identity-assertion` provider is also required.

2.7.7.2. Define Pseudo Identity Assertion

When you define the `Pseudo` `identity-assertion` provider without parameters, the authenticated user is asserted as the authenticated user. For example, using simple assertion if a user authenticates as "guest", the user's identity for grouping, authorization, and running the request is "guest".

To define a basic identity-assertion provider:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a `Pseudo` `identity-assertion` provider to `topology/gateway` as follows:

```
<provider>
  <role>identity-assertion</role>
  <name>Pseudo</name>
  <enabled>true</enabled>
</provider>
```

```
<provider> <role>identity-assertion</role> <name>Pseudo</name>
<enabled>true</enabled> </provider>
```

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.

2.7.7.3. Mapping Authenticated User to Cluster

The `principal.mapping` parameter of an `identity-assertion` provider determines the user name that the gateway asserts (uses as the authenticated user) for grouping, authorization, and to run the request on the cluster.



Note

If a user does not match a principal mapping definition, the authenticated user becomes the effective user.

To add user mapping rule to an identity-assertion provider:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.

2. Add a Pseudo identity-assertion provider to `topology/gateway` with the `principal.mapping` parameter as follows:

```
<provider>
  <role>identity-assertion</role>
  <name>Pseudo</name>
  <enabled>true</enabled>
  <param>
    <name>principal.mapping</name>
    <value>$user_ids=$cluster_user;$user_ids=$cluster_user1;...</value>
  </param>
</provider>
```

where the value contains a semi-colon-separated list of external to internal user mappings, and the following variables match the names in your environment:

- `$user_ids`
is a comma-separated list of external users or the wildcard (*) indicates all users.
- `$cluster_user`
is the Hadoop cluster user name the gateway asserts, that is the authenticated user name.

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.

2.7.7.3.1. Principal Mapping Enhancements

Concat Identity Assertion is a new provider for the Knox Gateway that enables you to map principals by concatenating strings to either the front or the back of a specified username. The Identity Assertion Provider provides the critical function of determining the Identity Principal that you will want to use in your Hadoop cluster to represent the identity that has been authenticated at the gateway. For more information on the Identity Assertion Provider and how it is used in the Knox Gateway, refer to the Identity Assertion chapter in the Apache Knox 0.6.x User Guide. If you would like to convert the user principal into a value that represents an identity from a particular user domain, use a configuration similar to the below example.

```
<provider>
  <role>identity-assertion</role>
  <name>Concat</name>
  <enabled>true</enabled>
  <param>
    <name>concat.suffix</name>
    <value>domain1</value>
  </param>
</provider>
```

Notice in this example that the `identity-assertion` role has been named `Concat` and has been enabled (`true`) for the Identity Assertion Provider, with the `concat.suffix` parameter given a value of `domain1` and concatenation will occur at the end of the username (`concat.suffix`). You may also use a parameter called `concat.prefix` to indicate a value to concatenate to the front of the username.

2.7.7.4. Example User Mapping

The gateway evaluates the list in order, from left to right; therefore a user matching multiple entries, resolves to the first matching instance.

In the following example, when a user authenticates as, the gateway asserts the user and all other users as:

```
<provider>
  <role>identity-assertion</role>
  <name>Pseudo</name>
  <enabled>true</enabled>
  <param>
    <name>principal.mapping</name>
    <value>guest=sam</value>
  </param>
</provider>
```

The following example shows how to map multiple users to different cluster accounts:

```
<provider>
  <role>identity-assertion</role>
  <name>Pseudo</name>
  <enabled>true</enabled>
  <param>
    <name>principal.mapping</name>
    <value>guest , joe ,brenda , administrator=same ; janet , adam , sue-dwayne</
value>
  </param>
</provider>
```

2.7.7.5. Mapping Authenticated Users to Groups

The Knox Gateway uses group membership for Service Level Authorization only. The gateway does not propagate the user's group when communicating with the Hadoop cluster.

The `group.principal.mapping` parameter of the identity-assertion provider determines the user's group membership. The gateway evaluates this parameter after the `principal.mapping` parameter using the authenticated user. Unlike `principal.mapping`, the group mapping applies all the matching values. A user is a member of all matching groups.



Note

Although user and group mappings are often used together, the instructions in this section only explain how to add group mappings.

2.7.7.6. Configuring Group Mapping

To map authenticated users to groups:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a `Pseudo identity-assertion provider` to `topology/gateway` with the `group.principal.mapping` parameter as follows:

```
<provider>
  <role>identity-assertion</role>
  <name>Pseudo</name>
  <enabled>true</enabled>
  <param>
    <name>group.principal.mapping</name>
    <value>${group1};${user1},${user2=group2};${user3=group2},group3</value>
  </param>
</provider>
```

where:

- the value is a semi-colon-separated list of user & group mappings and the variables are specific to your environment.
- `user1`, `user2`, `user3` are a comma-separated list of authenticated usernames or the wildcard (*) indicating all users. A username can be specified only once.
- `group1`, `group2`, `group3` are the names of the group that the user is in for Service Level Authorization.

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `gateway/data/deployments`.

2.7.7.7. Examples of Group Mapping

```
<provider>
  <role>identity-assertion</role>
  <name>Pseudo</name>
  <enabled>true</enabled>
  <param>
    <name>principal.mapping</name>
    <value>guest,alice=hdfs;mary=hive</value>
  </param>
  <param>
    <name>group.principal.mapping</name>
    <value>*=users; same,dwayne,brenda-admins;joe=analysts</value>
  </param>
</provider>
```

2.7.8. Configuring Service Level Authorization



Note

Group membership is determined by the `identity-assertion` parameter `group.principal.mapping`.

Group membership is determined by the `identity-assertion` parameter `group.principal.mapping`.

2.7.8.1. Setting Up an Authorization Provider

The `ACLAAuthz` provider determines who is able to access a service through the Knox Gateway by comparing the authenticated user, group, and originating IP address of the request to the rules defined in the authorization provider.

Configure the `AclsAuthz` provider as follows:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a `AclsAuthz` authorization provider to `topology/gateway` with a parameter for each service as follows:

```
<provider>
  <role>authorization</role>
  <name>AclsAuthz</name>
  <enabled>>true</enabled>
  <param>
    <name>$service_name.acl.mode</name>
    <value>$mode</value>
  </param>
  <param>
    <name>$service_Name.acl</name>
    <value>$cluster_users;$groups_field;IP_field</value>
  </param>
  ...
</provider>
```

where:

- `$service_name` matches the name of a service element. For example, `webhdfs`.
- `$mode` determines how the identity context (the effective user, their associated groups, and the original IP address) is evaluated against the fields as follows:
 - `AND` specifies that the request must match an entry in all three fields of the corresponding `$service_name.acl` parameter.
 - `OR` specifies that the request only needs to match an entry in any field, `$users_field OR $groups_field, OR $IP_field`.



Note

The `$service_name.acl.mode` parameter is optional. When it is not defined, the default mode is `AND`; therefore requests to that service must match all three fields.

- `$cluster_users` is a comma-separated list of authenticated users. Use a wildcard (*) to match all users.
- `$groups_field` is a comma-separated list of groups. Use a wildcard (*) to match all groups.
- `$IP_field` is a comma-separated list of IPv4 or IPv6 addresses. An IP address in the list can contain wildcard at the end to indicate a subnet (for example: `192.168.*`). Use a wildcard (*) to match all addresses.

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.

2.7.8.2. Examples of Authorization

The following examples illustrate how to define authorization rule types to restrict access to requests matching:

- **Only users in a specific group and from specific IP addresses**

The following rule is restrictive. It only allows the guest user in the admin group to access WebHDFS from a system with the IP address of either 127.0.0.2 or 127.0.0.3:

```
<provider>
  <role>authorization</role>
  <name>AclsAuthz</name>
  <enabled>true</enabled>
  <param>
    <name>webhdfs.acl</name>
    <value>guest;admin;127.0.0.2,127.0.0.3</value>
  </param>
</provider>
```

When the parameter `acl.mode` is not defined the default behavior is ALL, therefore following rule is the same as the one above:

```
<provider>
  <role>authorization</role>
  <name>AclsAuthz</name>
  <enabled>true</enabled>
  <param>
    <name>webhdfs.acl.mode</name>
    <value>AND</value>
  </param>
  <param>
    <name>webhdfs.acl</name>
    <value>guest;admin;127.0.0.2,127.0.0.3</value>
  </param>
</provider>
```



Note

If Guest is not in the admin group, the request is denied.

- **Two of the three conditions**

The following rule demonstrates how to require two conditions, user and group but not IP address, using the Wildcard. The rule allows the guest user that belongs to the admin group to send requests from anywhere because the IP field contains an asterisk which matches all IP addresses:

```
<provider>
  <role>authorization</role>
  <name>AclsAuthz</name>
  <enabled>true</enabled>
```

```
<param>
  <name>webhdfs.acl</name>
  <value>guest;admin;*</value>
</param>
</provider>
```

- **One of the three conditions**

When the `$service .acl.mode` parameter is set to OR, the request only needs to match one entry in any of the fields. The request fails with HTTP Status 403 unauthorized, if no conditions are met.

The following example allows:

- `guest` to send requests to WebHDFS from anywhere.
- Any user in the admin group to send requests to WebHDFS from anywhere.
- Any user, in any group, to send a request to WebHDFS from 127.0.0.2 or 127.0.0.3.

```
<provider>
  <role>authorization</role>
  <name>AclsAuthz</name>
  <enabled>>true</enabled>
  <param>
    <name>webhdfs.acl.mode</name>
    <value>OR</value>
  </param>
  <param>
    <name>webhdfs.acl</name>
    <value>guest;admin;127.0.0.2,127.0.0.3</value>
  </param>
</provider>
```

- **Allow all requests**

The following rule grants all users, in any group, and from any IP addresses to access WebHDFS:



Note

When a wildcard is used in a field it matches any value. Therefore the Allow all requests example is the same as not defining an ACL.

```
<provider>
  <role>authorization</role>
  <name>AclsAuthz</name>
  <enabled>>true</enabled>
  <param>
    <name>webhdfs.acl</name>
    <value>*,*,*</value>
  </param>
</provider>
```

2.7.9. Audit Gateway Activity

The Knox Gateway Audit Facility tracks actions that are executed by Knox Gateway per user request or that are produced by Knox Gateway internal events, such as topology deployments.



Tip

The Knox Audit module is based on the Apache log4j. You can customize the logger by changing the `log4j.appender.auditfile.Layout` property in `$gateway /conf/gateway-log4j.properties` to another class that extends `Log4j`. For detailed information see [Apache's log4j](#).

2.7.9.1. Audit Log Fields

Auditing events on the gateway are informational, the default auditing level is informational (INFO) and it cannot be changed.

The Audit logs located at `C: /hadoop/logs/knox/gateway-audit.log` have the following structure:

```
EVENT_PUBLISHING_TIMEROOT_REQUEST_ID | PARENT_REQUEST_ID | REQUEST_ID  
| LOGGER_NAME | TARGET_SERVICE_NAME | USER_NAME | PROXY_USER_NAME |  
SYSTEM_USER_NAME | ACTION | RESOURCE_TYPE | RESOURCE_NAME | OUTCOME |  
LOGGING_MESSAGE
```

where:

- `EVENT_PUBLISHING_TIME` : contains the timestamp when record was written.
- `ROOT_REQUEST_ID` : Reserved, the field is empty.
- `PARENT_REQUEST_ID` : Reserved, the field is empty.
- `REQUEST_ID` : contains a unique value representing the request.
- `LOGGER_NAME` : contains the logger name. For example `audit`.
- `TARGET_SERVICE_NAME` : contains the name of Hadoop service. Empty indicates that the audit record is not linked to a Hadoop service. For example, an audit record for topology deployment.
- `USER_NAME` : contains the ID of the user who initiated session with Knox Gateway.
- `PROXY_USER_NAME` : contains the authenticated user name.
- `SYSTEM_USER_NAME` : Reserved, field is empty.
- `ACTION` : contains the executed action type. The value is either authentication, authorization, redeploy, deploy, undeploy, identity-mapping, dispatch, or access.
- `RESOURCE_TYPE` contains the resource type of the action. The value is either `uri`, `topology`, or `principal`.

- `RESOURCE_NAME` : contains the process name of the resource. For example, `topology` shows the inbound or dispatch request path and `principal` shows the name of mapped user.
- `OUTCOME` contains the action results, `success`, `failure`, or `unavailable`.
- `LOGGING_MESSAGE` contains additional tracking information, such as the HTTP status code.

2.7.9.2. Change Roll Frequency of the Audit Log

Audit records are written to the log file `/var/log/knox/gateway-audit.log` and by default roll monthly. When the log rolls, the date that it rolled is appended to the end of the current log file and a new one is created.

To change the frequency:

1. Open the `$gateway /conf/gateway-log4j.properties` file in a text editor.
2. Change the `log4j.appender.auditfile.DatePattern` as follows:

```
log4j.appender.auditfile.DatePattern = $interval
```

where `$interval` is one of the following:

Setting	Description
<code>yyyy-MM</code>	Rollover at the beginning of each month
<code>yyyy-ww</code>	Rollover at the first day of each week. The first day of the week depends on the locale.
<code>yyyy-MM-dd</code>	Rollover at midnight each day.
<code>yyyy-MM-dd-a</code>	Rollover at midnight and midday of each day.
<code>yyyy-MM-dd-HH</code>	Rollover at the top of every hour.
<code>yyyy-MM-dd-HH-mm</code>	Rollover at the beginning of every minute.



Tip

For more examples, see [Apache log4j: Class DailyRollingFileAppender](#).

3. Save the file.
4. Restart the gateway:

```
cd $gateway bin/gateway.sh stop bin/gateway.sh start
```

2.7.10. Gateway Security

The Knox Gateway offers the following security features:

- [Implementing Web Application Security \[120\]](#)
- [Configuring Knox With a Secured Hadoop Cluster \[121\]](#)

2.7.10.1. Implementing Web Application Security

The Knox Gateway is a Web API (REST) Gateway for Hadoop clusters. REST interactions are HTTP based, and therefore the interactions are vulnerable to a number of web application security vulnerabilities. The web application security provider allows you to configure protection filter plugins.



Note

The initial vulnerability protection filter is for Cross Site Request Forgery (CSRF). Others will be added in future releases.

2.7.10.2. Configuring Protection Filter Against Cross Site Request Forgery Attacks

A Cross Site Request Forgery (CSRF) attack attempts to force a user to execute functionality without their knowledge. Typically the attack is initiated by presenting the user with a link or image that when clicked invokes a request to another site with which the user already has an established an active session. CSRF is typically a browser based attack.

The only way to create a HTTP request from a browser is with a custom HTTP header is to use Javascript XMLHttpRequest or Flash, etc. Browsers have built-in security that prevent web sites from sending requests to each other unless specifically allowed by policy. This means that a website `www.bad.com` cannot send a request to `http://bank.example.com` with the custom header `X-XSRF-Header` unless they use a technology such as a XMLHttpRequest. That technology would prevent such a request from being made unless the `bank.example.com` domain specifically allowed it. This then results in a REST endpoint that can only be called via XMLHttpRequest (or similar technology).



Note

After enabling CSRF protection within the gateway, a custom header is required for all clients that interact with it, not just browsers.

To add a CSRF protection filter:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a `WebAppSec` `webappsec` provider to `topology/gateway` with a parameter for each service as follows:

```
<provider>
  <role>webappsec</role>
  <name>WebAppSec</name>
  <enabled>>true</enabled>
  <param>
    <name>csrf.enabled</name>
    <value>$csrf_enabled</value>
  </param>
  <param><!-- Optional -->
    <name>csrf.customHeader</name>
    <value>$header_name</value>
  </param>
  <param><!-- Optional -->
```

```
<name>csrf.methodsToIgnore</name>
  <value>${HTTP_methods}</value>
</param>
</provider>
```

where:

- `$csrf_enabled` is either true or false.
- `$header_name` when the optional parameter `csrf.customHeader` is present the value contains the name of the header that determines if the request is from a trusted source. The default, `X-XSRF-Header`, is described by the NSA in its guidelines for dealing with CSRF in REST.

`$http_methods` when the optional parameter `csrf.methodsToIgnore` is present the value enumerates the HTTP methods to allow without the custom HTTP header. The possible values are GET, HEAD, POST, PUT, DELETE, TRACE, OPTIONS, CONNECT, or PATCH. For example, specifying GET allows GET requests from the address bar of a browser. Only specify methods that adhere to REST principals in terms of being idempotent.

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.



Note

Make sure you have properly set your `$JAVA_HOME` variable in your user environment; otherwise, Java will be used.

2.7.10.3. Validate CSRF Filtering

The following curl command can be used to request a directory listing from HDFS while passing in the expected header `X-XSRF-Header`.

```
curl -k -i --header "X-XSRF-Header: valid" -v -u guest:guest-password https://localhost:8443/gateway/sandbox/webhdfs/v1/tmp?op=LISTSTATUS
```



Note

The above `LISTSTATUS` request only works if you remove the GET method from the `csrf.methodsToIgnore` list.

Omitting the `-header "X-XSRF-Header: valid"` above results in an **HTTP 400 bad_request**. Disabling the provider, by setting `csrf.enabled` to false allows a request that is missing the header.

2.7.10.4. Configuring Knox With a Secured Hadoop Cluster

Once you have a Hadoop cluster that uses Kerberos for authentication, you must configure Knox to work with that cluster.

To enable the Knox Gateway to interact with a Kerberos-protected Hadoop cluster, add a `knox` user and Knox Gateway properties to the cluster.

Do the following:

1. Find the fully-qualified domain name of the host running the gateway:

```
hostname -f
```

If the Knox host does not have a static IP address, you can define the Knox host as `*` for local developer testing.

2. At every Hadoop Master:

- Create a UNIX account for Knox:

```
useradd -g hadoop Knox
```

- Edit `core-site.xml` to include the following lines (near the end of the file):

```
<property>
  <name>hadoop.proxyuser.knox.groups</name>
  <value>users</value>
</property>

<property>
  <name>hadoop.proxyuser.knox.hosts</name>
  <value>${knox-host}</value>
</property>
```

where `${knox-host}` is the fully-qualified domain name of the host running the gateway.

- Edit `webhcat-site.xml` to include the following lines (near the end of the file):

```
<property>
  <name>hadoop.proxyuser.knox.groups</name>
  <value>users</value>
</property>

<property>
  <name>hadoop.proxyuser.knox.hosts</name>
  <value>${knox-host}</value>
</property>
```

where `${knox_host}` is the fully-qualified domain name of the host running the gateway.

3. At the Oozie host, edit `oozie-site.xml` to include the following lines (near the end of the file):

```
<property>
  <name>oozie.service.ProxyUserService.proxyuser.knox.groups</name>
  <value>users</value>
</property>

<property>
  <name>oozie.service.ProxyUserService.proxyuser.knox.hosts</name>
  <value>${knox-host}</value>
</property>
```

where `${knox-host}` is the fully-qualified domain name of the host running the gateway.

4. At each node running HiveServer2, edit `hive-site.xml` to include the following properties and values:

```
<property>
  <name>hive.server2.enable.doAs</name>
  <value>true</value>
</property>

<property>
  <name>hive.server2.allow.user.substitution</name>
  <value>true</value>
</property>

<property>
  <name>hive.server2.transport.mode</name>
  <value>http</value>
  <description>Server transport mode. "binary" or "http".</description>
</property>

<property>
  <name>hive.server2.thrift.http.port</name>
  <value>10001</value>
  <description>Port number when in HTTP mode.</description>
</property>

<property>
  <name>hive.server2.thrift.http.path</name>
  <value>cliservice</value>
  <description>Path component of URL endpoint when in HTTP mode.</
description>
</property>
```

2.7.11. Setting Up Knox for WebHDFS HA

This chapter describes how to set up the Knox Gateway for WebHDFS HA (high availability).

To set up Knox for WebHDFS HA:

1. [Configure WebHDFS for Knox \[123\]](#)
2. [Configure Knox for WebHDFS HA \[124\]](#)

2.7.11.1. Configure WebHDFS for Knox

REST API access to HDFS in a Hadoop cluster is provided by [WebHDFS](#). The [WebHDFS REST API](#) documentation is available online. The following properties for Knox WebHDFS must be enabled in the `/etc/hadoop/conf/hdfs-site.xml` configuration file. The example values shown in these properties are from an installed instance of the Hortonworks Sandbox.

```
<property>
  <name>dfs.webhdfs.enabled</name>
  <value>true</value>
</property>
<property>
  <name>dfs.namenode.rpc-address</name>
  <value>sandbox.hortonworks.com:8020</value>
```

```

</property>
<property>
  <name>dfs.namenode.http-address</name>
  <value>sandbox.hortonworks.com:50070</value>
</property>
<property>
  <name>dfs.https.namenode.https-address</name>
  <value>sandbox.hortonworks.com:50470</value>
</property>

```

The values above must be reflected in each topology descriptor file deployed to the gateway. The gateway by default includes a sample topology descriptor file located at `{GATEWAY_HOME}/deployments/sandbox.xml`. The values in the following sample are also configured to work with an installed Hortonworks Sandbox VM.

```

<service>
  <role>NAMENODE</role>
  <url>hdfs://localhost:8020</url>
</service>
<service>
  <role>WEBHDFS</role>
  <url>http://localhost:50070/webhdfs</url>
</service>

```

The URL provided for the NAMENODE role does not result in an endpoint being exposed by the gateway. This information is only required so that other URLs can be rewritten that reference the Name Node's RPC address. This prevents clients from needing to be aware of the internal cluster details.

2.7.11.2. Configure Knox for WebHDFS HA



Important

Before you can configure the Knox Gateway for WebHDFS HA (high availability), you must first [configure WebHDFS for Knox](#).

Knox provides basic failover and retry functionality for REST API calls made to WebHDFS when HDFS HA has been configured and enabled.

To enable HA functionality for WebHDFS in Knox the following configuration must be added to the topology file.

```

<provider>
  <role>ha</role>
  <name>HaProvider</name>
  <enabled>true</enabled>
  <param>
    <name>WEBHDFS</name>
    <value>maxFailoverAttempts=3;failoverSleep=1000;maxRetryAttempts=
300;retrySleep=1000;enabled=true</value>
  </param>
</provider>

```

The `<role>` and `<name>` of the provider must be as shown above. The `<name>` in the `<param>` section must match that of the service role name that is being configured for HA, and the `<value>` in the `<param>` section is the configuration for that particular service in HA mode. In this case the `<name>` is `WEBHDFS`.

The various configuration parameters are described below:

- `maxFailoverAttempts` – The maximum number of times a failover will be attempted. The current failover strategy is very simplistic in that the next URL in the list of URLs provided for the service is used, and the one that failed is put at the bottom of the list. If the list is exhausted and the maximum number of attempts has not been reached, the first URL that failed will be tried again (the list will start again from the original top entry).
- `failoverSleep` – The amount of time in milliseconds that the process will wait or sleep before attempting to failover.
- `maxRetryAttempts` – The maximum number of times that a retry request will be attempted. Unlike failover, the retry is done on the same URL that failed. This is a special case in HDFS when the node is in safe mode. The expectation is that the node will come out of safe mode, so a retry is desirable here as opposed to a failover.
- `retrySleep` – The amount of time in milliseconds that the process will wait or sleep before a retry is issued.
- `enabled` - Flag to turn the particular service on or off for HA.

For the service configuration itself, the additional URLs for standby nodes should be added to the list. The active URL (at the time of configuration) should ideally be added at the top of the list. For example:

```
<service>
  <role>WEBHDFS</role>
  <url>http://{host1}:50070/webhdfs</url>
  <url>http://{host2}:50070/webhdfs</url>
</service>
```

2.7.12. Knox CLI Testing Tools

This chapter describes how to use the Knox CLI (Command Line Interface) to run diagnostic tests.

The Knox CLI is a command line utility that can be used to manage and test various aspects of a Knox deployment.

The `knoxcli.sh` command line utility script is located in the `{GATEWAY_HOME}/bin` directory.

2.7.12.1. Knox CLI LDAP Authentication and Authorization Testing

You can use the following command format to authenticate a user name and password against LDAP.

```
bin/knoxcli.sh user-auth-test [--cluster c] [--u username] [--p password] [--g] [--d] [--help]
```

This command will test a topology's ability to connect, authenticate, and authorize a user with an LDAP server. The only required argument is the `--cluster` argument to specify the name of the topology you wish to use. The topology must be valid (passes a validate-

topology command). If the `-u` and `-p` arguments are not specified, you will be prompted for a user name and password.

If authentication is successful, the command will attempt to use the topology to do an LDAP group lookup. The topology must be configured correctly to do this. If it is not, groups will not be returned and no errors will be printed unless the `--g` argument is specified. Currently this command only works if a topology supports the use of ShiroProvider for authentication.

Table 2.23. LDAP Authentication and Authorization Arguments

Argument	Description	Required?
<code>-cluster</code>	The name of the cluster to authenticate.	Yes
<code>-u</code>	The user name to authenticate with.	No
<code>-p</code>	The password to authenticate with.	No
<code>-g</code>	Specifies that you want to return a user's groups. If not specified, group lookup errors will not be returned.	No
<code>-d</code>	Print extra debug information for a failed authentication.	No

3. Configuring Authorization in Hadoop

3.1. Installing Ranger Using Ambari

3.1.1. Overview

Apache Ranger can be installed either manually using the Hortonworks Data Platform (HDP) or the Ambari 2.1 User Interface (UI). Unlike the manual installation process, which requires you to perform a number of installation steps, installing Ranger using the Ambari UI is simpler and easier. The Ranger service option will be made available through the Add Service wizard after the HDP cluster is installed using the installation wizard.

Once Ambari has been installed and configured, you can use the Add Service wizard to install the following components:

- Ranger Admin
- Ranger UserSync
- [Installing the Ranger Key Management Service \[369\]](#)

After these components are installed and started, you can enable Ranger plugins by navigating to each individual Ranger service (HDFS, HBase, Hiveserver2, Storm, Knox, YARN, and Kafka) and modifying the configuration under *advanced ranger-<service>-plugin-properties*.

Note that when you enable a Ranger plugin, you will need to restart the component.



Note

Enabling Apache Storm or Apache Kafka requires you to enable Kerberos. To enable Kerberos on your cluster, see [Enabling Kerberos Authentication Using Ambari](#).

3.1.2. Installation Prerequisites

Before you install Ranger, make sure your cluster meets the following requirements:

- It is recommended that you store audits in both HDFS and Solr, so you should [install Apache Solr](#).
- To ensure that LDAP/AD group level authorization is enforced in Hadoop, you should [set up Hadoop group mapping](#) for LDAP.
- A MySQL, Oracle, or PostgreSQL database instance must be running and available to be used by Ranger.

The Ranger installation will create two new users (default names: rangeradmin and rangerlogger) and two new databases (default names: ranger and ranger_audit).

- Configuration of the database instance for Ranger is described in the following sections for some of the databases supported by Ranger.
 - [Configuring MySQL for Ranger \[130\]](#)
 - [Configuring PostgreSQL for Ranger \[131\]](#)
 - [Configuring Oracle for Ranger \[132\]](#)
- If you choose not to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the `dba_script.py` Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger installer. You can then run the normal Ambari Ranger installation without specifying a DBA user name and password. For more information see [Setting up Database Users Without Sharing DBA Credentials](#).

3.1.2.1. Setting Up Hadoop Group Mapping for LDAP/AD

To ensure that LDAP/AD group level authorization is enforced in Hadoop, you should set up Hadoop group mapping for LDAP/AD.

Prerequisites: Access to LDAP and the connection details. Note that LDAP settings can vary depending on what LDAP implementation you are using.

There are three ways to set up Hadoop group mapping:

- [Configure Hadoop Group Mapping for LDAP/AD Using SSSD \(Recommended\) \[128\]](#)
- [Configure Hadoop Group Mapping in core-site.xml \[129\]](#)
- [Manually Create the Users and Groups in the Linux Environment \[130\]](#)

3.1.2.1.1. Configure Hadoop Group Mapping for LDAP/AD Using SSSD (Recommended)

The recommended method for group mapping is to use [SSSD](#) or one of the following services to connect the Linux OS with LDAP:

- Centrify
- NSLCD
- Winbind
- SAMBA

Note that most of these services allow you to not only look up a user and enumerate their groups, but also allow you to perform other actions on the host. None of these features are required for LDAP group mapping on Hadoop – all that is required is the ability to lookup (or "validate") a user within LDAP and enumerate their groups. Therefore, when evaluating these services, take the time to understand the difference between the NSS module (which performs user/group resolution) and the PAM module (which performs user authentication). NSS is required. PAM is not required, and may represent a security risk.

3.1.2.1.2. Configure Hadoop Group Mapping in core-site.xml

You can use the following steps to configure Hadoop to use LDAP-based group mapping in `core-site.xml`.

1. Add the properties shown in the example below to the `core-site.xml` file. You will need to provide the value for the bind user, the bind password, and other properties specific to your LDAP instance, and make sure that object class, user, and group filters match the values specified in your LDAP instance.

```
<property>
<name>hadoop.security.group.mapping</name>
<value>org.apache.hadoop.security.LdapGroupsMapping</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.bind.user</name>
<value>cn=Manager,dc=hadoop,dc=apache,dc=org</value>
</property>

<!--
<property>
<name>hadoop.security.group.mapping.ldap.bind.password.file</name>
<value>/etc/hadoop/conf/ldap-conn-pass.txt</value>
</property>
-->

<property>
<name>hadoop.security.group.mapping.ldap.bind.password</name>
<value>hadoop</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.url</name>
<value>ldap://localhost:389/dc=hadoop,dc=apache,dc=org</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.url</name>
<value>ldap://localhost:389/dc=hadoop,dc=apache,dc=org</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.base</name>
<value></value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.search.filter.user</name>
<value>(&(|(objectclass=person)(objectclass=applicationProcess))(cn={0})</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.search.filter.group</name>
<value>(objectclass=groupOfNames)</value>
</property>

<property>
```

```
<name>hadoop.security.group.mapping.ldap.search.attr.member</name>
<value>member</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.search.attr.group.name</name>
<value>cn</value>
</property>
```

2. Depending on your configuration, you may be able to refresh user and group mappings using the following HDFS and YARN commands:

```
hdfs dfsadmin -refreshUserToGroupsMappings
yarn radmin -refreshUserToGroupsMappings
```

If a restart is required, you can use the applicable instructions on [this page](#) to re-start the HDFS NameNode and the YARN ResourceManager.

3. Verify LDAP group mapping by running the `hdfs groups` command. This command will fetch groups from LDAP for the current user. Note that with LDAP group mapping configured, the HDFS permissions can leverage groups defined in LDAP for access control.

3.1.2.1.3. Manually Create the Users and Groups in the Linux Environment

You can also [manually create users and groups](#) in your Linux environment.

3.1.2.2. Configuring MySQL for Ranger

1. The MySQL database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the `rangerdba` user with password `rangerdba`.

- a. Log in as the root user, then use the following commands to create the `rangerdba` user and grant it adequate privileges.

```
CREATE USER 'rangerdba'@'localhost' IDENTIFIED BY 'rangerdba';
GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'localhost';
CREATE USER 'rangerdba'@'%' IDENTIFIED BY 'rangerdba';
GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'%';
GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'localhost' WITH GRANT OPTION;
GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'%' WITH GRANT OPTION;
FLUSH PRIVILEGES;
```

- b. Use the `exit` command to exit MySQL.
- c. You should now be able to reconnect to the database as `rangerdba` using the following command:

```
mysql -u rangerdba -prangerdba
```

After testing the `rangerdba` login, use the `exit` command to exit MySQL.

2. Use the following command to confirm that the `mysql-connector-java.jar` file is in the Java share directory. This command must be run on the server where Ambari server is installed.

```
ls /usr/share/java/mysql-connector-java.jar
```

If the file is not in the Java share directory, use the following command to install the MySQL connector .jar file.

RHEL/CentOS/Oracle Linux

```
yum install mysql-connector-java*
```

SLES

```
zypper install mysql-connector-java*
```

3. Use the following command format to set the `jdbc/driver/path` based on the location of the MySQL JDBC driver .jar file. This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={/jdbc/driver/path}
```

For example:

```
ambari-server setup --jdbc-db=mysql --jdbc-driver=/usr/share/java/mysql-connector-java.jar
```

3.1.2.3. Configuring PostgreSQL for Ranger

1. On the PostgreSQL host, install the applicable PostgreSQL connector.

RHEL/CentOS/Oracle Linux

```
yum install postgresql-jdbc*
```

SLES

```
zypper install -y postgresql-jdbc
```

2. Confirm that the .jar file is in the Java share directory.

```
ls /usr/share/java/postgresql-jdbc.jar
```

3. Change the access mode of the .jar file to 644.

```
chmod 644 /usr/share/java/postgresql-jdbc.jar
```

4. The PostgreSQL database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the `rangerdba` user and grant it adequate privileges.

```
echo "CREATE DATABASE $dbname;" | sudo -u $postgres psql -U postgres
```

```
echo "CREATE USER $rangerdba WITH PASSWORD '$passwd';" | sudo -u $postgres
psql -U postgres
echo "GRANT ALL PRIVILEGES ON DATABASE $dbname TO $rangerdba;" | sudo -u
postgres psql -U $postgres
```

Where:

- \$postgres is the Postgres user.
 - \$dbname is the name of your PostgreSQL database
5. Use the following command format to set the jdbc/driver/path based on the location of the PostgreSQL JDBC driver .jar file. This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={/jdbc/driver/
path}
```

For example:

```
ambari-server setup --jdbc-db=postgres --jdbc-driver=/usr/share/java/
postgresql.jar
```

6. Run the following command:

```
export HADOOP_CLASSPATH=${HADOOP_CLASSPATH}:${JAVA_JDBC_LIBS}:/connector jar
path
```

7. Add Allow Access details for Ranger users:

- change listen_addresses='localhost' to listen_addresses='*' ('*' = any) to listen from all IPs in postgresql.conf.
- Make the following changes to the Ranger db user and Ranger audit db user in the pg_hba.conf file.

```
# TYPE DATABASE USER CIDR-ADDRESS METHOD
# "local" is for Unix domain socket connections only
local all postgres,rangeradmin,rangerlogger trust
# IPv4 local connections:
host all postgres,rangeradmin,rangerlogger 0.0.0.0/0 trust
# IPv6 local connections:
host all postgres,rangeradmin,rangerlogger ::/0 trust
"/var/lib/pgsql/data/pg_hba.conf" 74L, 3445C
```

8. After editing the pg_hba.conf file, run the following command to refresh the PostgreSQL database configuration:

```
sudo -u postgres /usr/bin/pg_ctl -D $PGDATA reload
```

For example, if the pg_hba.conf file is located in the /var/lib/pgsql/data directory, the value of \$PGDATA is /var/lib/pgsql/data.

3.1.2.4. Configuring Oracle for Ranger

1. On the Oracle host, install the appropriate JDBC .jar file.
- Download the Oracle JDBC (OJDBC) driver from <http://www.oracle.com/technetwork/database/features/jdbc/index-091264.html>.

- For **Oracle Database 11g**: select Oracle Database 11g Release 2 drivers > ojdbc6.jar.
- For **Oracle Database 12c**: select Oracle Database 12c Release 1 driver > ojdbc7.jar.
- Copy the .jar file to the Java share directory. For example:

```
cp ojdbc7.jar /usr/share/java
```



Note

Make sure the .jar file has the appropriate permissions. For example:

```
chmod 644 /usr/share/java/ojdbc7.jar
```

2. The Oracle database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the RANGERDBA user and grant it permissions using SQL*Plus, the Oracle database administration utility:

```
# sqlplus sys/root as sysdba
CREATE USER $RANGERDBA IDENTIFIED BY $RANGERDBAPASSWORD;
GRANT SELECT_CATALOG_ROLE TO $RANGERDBA;
GRANT CONNECT, RESOURCE TO $RANGERDBA;
QUIT;
```

3. Use the following command format to set the jdbc/driver/path based on the location of the Oracle JDBC driver .jar file. This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={jdbc/driver/path}
```

For example:

```
ambari-server setup --jdbc-db=oracle --jdbc-driver=/usr/share/java/ojdbc6.jar
```

3.1.3. Ranger Installation

To install Ranger using Ambari:

1. [Start the Installation \[138 \]](#)
2. [Customize Services \[138\]](#)
3. [Complete the Ranger Installation \[164\]](#)


Related Topics

- [Setting up Database Users Without Sharing DBA Credentials \[168\]](#)
- [Updating Ranger Admin Passwords \[169\]](#)

3.1.3.1. Start the Installation


1. Log into your Ambari cluster with your designated user credentials. The main Ambari Dashboard page will be displayed.

Figure 3.1. Installing Ranger - Main Dashboard View



2. In the left navigation menu, click **Actions**, then select **Add Service**.

Figure 3.2. Installing Ranger - Add Service



3. On the Choose Services page, select **Ranger**, then click **Next**.


Figure 3.3. Installing Ranger - Choose Service

The screenshot shows the 'Add Service Wizard' window with a list of services. The 'Ranger' service is selected and highlighted with a red box. The 'Next' button is also highlighted with a red box.

Service	Version	Description
<input checked="" type="checkbox"/> Pig	0.15.0.2.3	Scripting platform for analyzing large datasets
<input checked="" type="checkbox"/> Sqoop	1.4.6.2.3	Tool for transferring bulk data between Apache Hadoop and structured data stores such as relational databases
<input checked="" type="checkbox"/> Oozie	4.2.0.2.3	System for workflow coordination and execution of Apache Hadoop jobs. This also includes the installation of the optional Oozie Web Console which relies on and will install the ExUS Library.
<input checked="" type="checkbox"/> ZooKeeper	3.4.6.2.3	Centralized service which provides highly reliable distributed coordination
<input checked="" type="checkbox"/> Falcon	0.6.1	Data management and processing platform
<input checked="" type="checkbox"/> Storm	0.10.0	Apache Hadoop Stream processing framework
<input checked="" type="checkbox"/> Flume	1.5.2.2.3	A distributed service for collecting, aggregating, and moving large amounts of streaming data into HDFS
<input checked="" type="checkbox"/> Accumulo	1.7.0.2.3	Robust, scalable, high performance distributed key/value store.
<input checked="" type="checkbox"/> Ambari Metrics	0.1.0	A system for metrics collection that provides storage and retrieval capability for metrics collected from the cluster
<input checked="" type="checkbox"/> Atlas	0.5.0.2.3	Atlas Metadata and Governance platform
<input checked="" type="checkbox"/> Kafka	0.8.2.2.3	A high-throughput distributed messaging system
<input checked="" type="checkbox"/> Knox	0.6.0.2.3	Provides a single point of authentication and access for Apache Hadoop services in a cluster
<input checked="" type="checkbox"/> Mahout	1.0.0.2.3	Project of the Apache Software Foundation to produce free implementations of distributed or otherwise scalable machine learning algorithms focused primarily in the areas of collaborative filtering, clustering and classification
<input checked="" type="checkbox"/> Ranger	0.5.0.2.3	Comprehensive security for Hadoop
<input type="checkbox"/> Ranger KMS	0.5.0.2.3	Key Management Server
<input checked="" type="checkbox"/> Slider	0.80.0.2.3	A framework for deploying, managing and monitoring existing distributed applications on YARN.
<input checked="" type="checkbox"/> Spark	1.3.1.2.3	Apache Spark is a fast and general engine for large-scale data processing.

Next →

4. The Ranger Requirements page appears. Ensure that you have met all of the installation requirements, then select the "I have met all the requirements above" check box and click **Proceed**.

Figure 3.4. Installing Ranger - Ranger Requirements

Ranger Requirements

1. You must have an **MySQL/Oracle/Postgres/MSSQL Server** database instance running to be used by Ranger.
2. In Assign Masters step of this wizard, you will be prompted to specify which host for the Ranger Admin. On that host, you **must have DB Client installed** for Ranger to access to the database. (Note: This is only applicable for only Ranger 0.4.0)
3. Ensure that the access for the DB Admin user is enabled in DB server from any host.
4. Execute the following command on the Ambari Server host. Replace `database-type` with `mysql|oracle|postgres|mssql` and `/jdbc/driver/path` based on the location of corresponding JDBC driver:

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={/jdbc/driver/path}
```

I have met all the requirements above.

Cancel Proceed

5. You are then prompted to select the host where Ranger Admin will be installed. This host should have DB admin access to the Ranger DB host and User Sync. Notice in the figure below that both the Ranger Admin and Ranger User Sync services will be installed on the primary node in the cluster (c6401.ambari.apache.org in the example shown below).


Make a note of the Ranger Admin host for use in subsequent installation steps. Click **Next** when finished to continue with the installation.



Note

The Ranger Admin and Ranger User Sync services must be installed on the same cluster node.

Figure 3.5. Installing Ranger Assign Masters



6. The Customize Services page appears. These settings are described in the next section.


3.1.3.2. Customize Services

The next step in the installation process is to specify Ranger settings on the Customize Services page.

- [Ranger Admin Settings \[138\]](#)
- [Ranger Audit Settings \[148\]](#)
- [Configure Ranger User Sync \[149\]](#)
- [Configure Ranger Authentication \[156\]](#)

3.1.3.2.1. Ranger Admin Settings

1. On the Customize Services page, select the Ranger Admin tab, then use the **DB Flavor** drop-down to select the database type that you are using with Ranger.



2. Enter the database server address in the **Ranger DB Host** box.

Table 3.1. Ranger DB Host

DB Flavor	Host	Example
MySQL	<HOST[:PORT]>	c6401.ambari.apache.org
		or c6401.ambari.apache.org:3306
Oracle	<HOST:PORT:SID>	c6401.ambari.apache.org:1521:ORCL
	<HOST:PORT/Service>	c6401.ambari.apache.org:1521/XE
PostgreSQL	<HOST[:PORT]>	c6401.ambari.apache.org
		or c6401.ambari.apache.org:5432
MS SQL	<HOST[:PORT]>	c6401.ambari.apache.org

DB Flavor	Host	Example
		or c6401.ambari.apache.org:1433
SQLA	<HOST[:PORT]>	c6401.ambari.apache.org or c6401.ambari.apache.org:2638

- Ranger DB name** – The name of the Ranger Policy database, i.e. ranger_db. Please note that if you are using Oracle, you must specify the Oracle tablespace name here.
- Driver class name for a JDBC Ranger database – the driver class name is automatically generated based on the selected DB Flavor. The table below lists the default driver class settings. Currently Ranger does not support any third party JDBC driver.

Table 3.2. Driver Class Name

DB Flavor	Driver class name for a JDBC Ranger database
MySQL	com.mysql.jdbc.Driver
Oracle	oracle.jdbc.driver.OracleDriver
PostgreSQL	org.postgresql.Driver
MS SQL	com.microsoft.sqlserver.jdbc.SQLServerDriver
SQLA	sap.jdbc4.sqlanywhere.IDriver

- Ranger DB username and Ranger DB Password** – Enter the user name and passwords for your Ranger database server. The following table describes these settings in more detail. You can use the MySQL database that was installed with Ambari, or an external MySQL, Oracle, PostgreSQL, MS SQL or SQL Anywhere database.

Table 3.3. Ranger DB Username Settings

Property	Description	Default Value	Example Value	Required?
Ranger DB username	The username for the Policy database.	rangeradmin	rangeradmin	Yes
Ranger DB password	The password for the Ranger Policy database user.		PassWORD	Yes

6. JDBC connect string



Important

Currently the Ambari installer generates the JDBC connect string using the `jdbc:oracle:thin:@//host:port/db_name` format. You must replace the connection string as described in the following table:

Table 3.4. JDBC Connect String

DB Flavor	Syntax	Example Value
MySQL	<code>jdbc:mysql://DB_HOST:PORT/db_name</code>	<code>jdbc:mysql://c6401.ambari.apache.org:3306/ranger_db</code>

DB Flavor	Syntax	Example Value
Oracle	For Oracle SID: jdbc:oracle:thin:@DB_HOST:PORT:SID	jdbc:oracle:thin:@c6401.ambari.apache.org:1521:ORCL
	For Oracle Service Name: jdbc:oracle:thin:@//DB_HOST[:PORT] [/ServiceName]	jdbc:oracle:thin:@// c6401.ambari.apache.org:1521/XE
PostgreSQL	jdbc:postgresql://DB_HOST/ db_name	jdbc:postgresql:// c6401.ambari.apache.org:5432/ ranger_db
MS SQL	jdbc:sqlserver:// DB_HOST;databaseName=db_name	jdbc:sqlserver:// c6401.ambari.apache.org:1433;databaseName=ranger_db
SQLA	jdbc:sqlanywhere:host=DB_HOST;data	jdbc:sqlanywhere:host=c6401.ambari.apache.org:2638;data

7. Setup Database and Database User

- If set to **Yes** – The Database Administrator (DBA) user name and password will need to be provided as described in the next step.



Note

Ranger does not store the DBA user name and password after setup. Therefore, you can clear these values in the Ambari UI after the Ranger setup is complete.

- If set to **No** – A **No** indicates that you do not wish to provide Database Administrator (DBA) account details to the Ambari Ranger installer. Setting this to No continues the Ranger installation process without providing DBA account details. In this case, you must perform the system database user setup as described in [Setting up Database Users Without Sharing DBA Credentials](#), and then proceed with the installation.



Note

If **No** is selected and the UI still requires you to enter a user name and password in order to proceed, you can enter any value – the values do not need to be the actual DBA user name and password.

- ## 8. Database Administrator (DBA) username and Database Administrator (DBA) password
- The DBA username and password are set when the database server is installed. If you do not have this information, contact the database administrator who installed the database server.

Table 3.5. DBA Credential Settings

Property	Description	Default Value	Example Value	Required?
Database Administrator (DBA) username	The Ranger database user that has administrative privileges to create database schemas and users.	root	root	Yes
Database Administrator (DBA) password	The root password for the Ranger database user.		root	Yes

If the Oracle DB root user Role is SYSDBA, you must also specify that in the **Database Administrator (DBA) username** parameter. For example, if the DBA user name is `orcl_root` you must specify `orcl_root AS SYSDBA`.



Note

As mentioned in the note in the previous step, if **Setup Database and Database User** is set to **No**, a placeholder DBA username and password may still be required in order to continue with the Ranger installation.

The following images show examples of the DB settings for each Ranger database type.



Note

To test the DB settings, click **Test Connection**. If a Ranger database has not been pre-installed, **Test Connection** will fail even for a valid configuration.

MySQL

Ranger Admin [Ranger User Info](#) [Ranger Plugin](#) [Ranger Audit](#) [Advanced](#)

Ranger Admin

<p>DB FLAVOR</p> <p>MYSQL <input type="button" value="v"/></p>	<p>Ranger DB host</p> <p>c6401.ambari.apache.org</p>
<p>Ranger DB name</p> <p>ranger</p>	<p>Driver class name for a JDBC Ranger database</p> <p>com.mysql.jdbc.Driver</p>
<p>Ranger DB username</p> <p>rangeradmin</p>	<p>Ranger DB password</p> <p>.....</p> <p>.....</p>
<p>JDBC connect string</p> <p>jdbc:mysql://c6401.ambari.apache.org/ranger</p>	

Setup Database and Database User

Yes

<p>Database Administrator (DBA) username</p> <p>root</p>	<p>Database Administrator (DBA) password</p> <p>.....</p> <p>.....</p>
<p>JDBC connect string for root user</p> <p>jdbc:mysql://c6401.ambari.apache.org</p>	

Oracle – if the Oracle instance is running with a Service name.

Ranger Admin [Ranger User Info](#) [Ranger Plugin](#) [Ranger Audit](#) [Advanced](#)

Ranger Admin

DB FLAVOR

Ranger DB name

Ranger DB username

JDBC connect string

Ranger DB host


Driver class name for a JDBC Ranger database

Ranger DB password

Setup Database and Database User
 Yes

Database Administrator (DBA) username

Database Administrator (DBA) password

JDBC connect string for root user
 

Oracle – if the Oracle instance is running with a SID.

Ranger Admin [Ranger User Info](#) [Ranger Plugin](#) [Ranger Audit](#) [Advanced](#)

Ranger Admin

DB FLAVOR

Ranger DB name

Ranger DB username

JDBC connect string

Ranger DB host

Driver class name for a JDBC Ranger database

Ranger DB password

Setup Database and Database User
 Yes

Database Administrator (DBA) username

JDBC connect string for root user

Database Administrator (DBA) password

PostgreSQL

Ranger Admin [Ranger User Info](#) [Ranger Plugin](#) [Ranger Audit](#) [Advanced](#)

Ranger Admin

DB FLAVOR

Ranger DB name

Ranger DB username

JDBC connect string

Ranger DB host

Driver class name for a JDBC Ranger database

Ranger DB password

Setup Database and Database User
 Yes

Database Administrator (DBA) username

Database Administrator (DBA) password

JDBC connect string for root user

MS SQL

Ranger Admin [Ranger User Info](#) [Ranger Plugin](#) [Ranger Audit](#) [Advanced](#)

Ranger Admin

DB FLAVOR
MSSQL

Ranger DB name
ranger

Ranger DB username
rangeradmin

JDBC connect string
r1.ambari.apache.org:1433;databaseName=ranger

Ranger DB host
c6401.ambari.apache.org:1433

Driver class name for a JDBC Ranger database
com.microsoft.sqlserver.jdbc.SQLServerDriver

Ranger DB password
.....

Setup Database and Database User
 Yes

Database Administrator (DBA) username
administrator

JDBC connect string for root user
jdbc:sqlserver://c6401.ambari.apache.org:1433;

Database Administrator (DBA) password
.....

SQL Anywhere

Ranger Admin **Ranger User Info** Ranger Plugin Ranger Audit Advanced

Ranger Admin

DB FLAVOR
SQL Anywhere ▾

Ranger DB name
ranger

Ranger DB username
rangeradmin

JDBC connect string
=c6401.ambari.apache.org:2638;database=ranger

Ranger DB host
c6401.ambari.apache.org:2638

Driver class name for a JDBC Ranger database
sap.jdbc4.sqlanywhere.IDriver

Ranger DB password
.....

Setup Database and Database User
 Yes

Database Administrator (DBA) username
dba

JDBC connect string for root user
jdbc:sqlanywhere:host=c6401.ambari.apache.org::

Database Administrator (DBA) password
.....

3.1.3.2.2. Ranger Audit Settings

1. On the Customize Services page, select the Ranger Audit tab.

It is recommended that you store audits in Solr and HDFS, and disable Audit to DB.

The screenshot shows the 'Add Service Wizard' for Ranger Audit. The 'Ranger Audit' tab is selected, and the 'Advanced' sub-tab is active. The 'Audit to Solr' section has 'Audit to Solr' set to 'ON' and 'SolrCloud' also set to 'ON' (highlighted with a red box). Below these are fields for 'ranger.audit.solr.zookeepers' (c6403.ambari.apache.org:2181/ranger_...), 'ranger.audit.solr.username' (ranger_solr), and 'ranger.audit.solr.password' (two masked input fields). The 'Audit to HDFS' section has 'Audit to HDFS' set to 'ON' and a 'Destination HDFS Directory' field with the value 'hdfs://c6403.ambari.apache.org:8020/h...'. The 'Audit to DB' section has 'Audit to DB' set to 'OFF', 'Ranger Audit DB name' (ranger_audit), and 'Ranger Audit DB username' (rangerlogger). The 'Ranger Audit DB password' fields are highlighted with a red box and show a warning icon.

- Under Audit to Solr, click **OFF** under SolrCloud to enable SolrCloud. The button label will change to ON, and the SolrCloud configuration settings will be loaded automatically.



Note

Audits to Solr requires that you have already [installed Solr](#) and [configured SolrCloud](#).

- Under Audit to DB, enter a password in the **Ranger Audit DB password** boxes. Audit to DB is set to **OFF** by default. (The password must be entered to preserve backward compatibility)

3.1.3.2.3. Configure Ranger User Sync

This section describes how to configure Ranger User Sync for either UNIX or LDAP/AD.

- [Test Run Ranger Usersync \[150\]](#)

- [Configuring Ranger User Sync for UNIX \[150\]](#)
- [Configuring Ranger User Sync for LDAP/AD \[151\]](#)

3.1.3.2.3.1. Test Run Ranger Usersync

Steps

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended.

To test-run loading User and Group data into Ranger before committing to the changes:

1. Set `ranger.usersync.policymanager.mockrun=true`. This parameter can be found in Ambari > Ranger > Configs > Advanced > Advanced `ranger-ugsync-site`.
2. View the Users and Groups that will be loaded into Ranger: `tail -f /var/log/ranger/usersync/usersync.log`.
3. After confirming that the users and groups are retrieved as intended, set `ranger.usersync.policymanager.mockrun=false` and restart Ranger Usersync.

This will sync the users shown in the usersync log to the Ranger database.

3.1.3.2.3.2. Configuring Ranger User Sync for UNIX

Before you begin

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).


Steps

Use the following steps to configure Ranger User Sync for UNIX.

1. On the Customize Services page, select the Ranger User Info tab.
2. Click **Yes** under Enable User Sync.
3. Use the Sync Source drop-down to select UNIX, then set the following properties.

Table 3.6. UNIX User Sync Properties

Property	Description	Default Value
Sync Source	Only sync users above this user ID.	500
Password File	The location of the password file on the Linux server.	/etc/passwd
Group File	The location of the groups file on the Linux server.	/etc/group



3.1.3.2.3.3. Configuring Ranger User Sync for LDAP/AD



Important

To ensure that LDAP/AD group level authorization is enforced in Hadoop, you should [set up Hadoop group mapping for LDAP/AD](#).



Note

You can use the [LDAP Connection Check tool](#) to determine User Sync settings for LDAP/AD.

Before you begin

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).


Steps

Use the following steps to configure Ranger User Sync for LDAP/AD.

1. On the Customize Services page, select the Ranger User Info tab.
2. Click **Yes** under Enable User Sync.
3. Use the Sync Source drop-down to select LDAP/AD.
4. Set the following properties on the Common Configs tab.

Table 3.7. LDAP/AD Common Configs

Property	Description	Default Value	Sample Values
LDAP/AD URL	Add URL depending upon LDAP/AD sync source	ldap://{host}:{port}	ldap:// ldap.example.com:389 or ldaps:// ldap.example.com:636
Bind Anonymous	If Yes is selected, the Bind User and Bind User Password are not required.	NO	
Bind User	The location of the groups file on the Linux server.	The full distinguished name (DN), including common name (CN), of an LDAP/AD user account that has privileges to search for users. The LDAP bind DN is used to connect to LDAP and query for users and groups.	cn=admin,dc=example,dc=com or admin@example.com
Bind User Password	The password of the Bind User.		



5. Set the following properties on the User Configs tab.

Table 3.8. LDAP/AD User Configs

Property	Description	Default Value	Sample Values
Group User Map Sync	Sync specific groups for users.	No	Yes
Username Attribute	The LDAP user name attribute.		sAMAccountName for AD, uid or cn for OpenLDAP
User Object Class	Object class to identify user entries.	person	top, person, organizationalPerson, user, or posixAccount
User Search Base	Search base for users.		cn=users,dc=example,dc=com
User Search Filter	Optional additional filter constraining the users selected for syncing.		Sample filter to retrieve all the users: cn=* Sample filter to retrieve all the users who are members

Property	Description	Default Value	Sample Values
			of groupA or groupB: ((memberof=CN=GroupA,OU=groups,DC=example.com) (memberof=CN=GroupB,OU=groups,DC=example.com)
User Search Scope	This value is used to limit user search to the depth from search base.	sub	base, one, or sub
User Group Name Attribute	Attribute from user entry whose values would be treated as group values to be pushed into the Access Manager database. You can provide multiple attribute names separated by commas.	memberof,ismemberof	memberof, ismemberof, or gidNumber

Add Service Wizard

Ranger User Info

Enable User Sync
 Yes

Sync Source
 LDAP/AD

Common Configs | **User Configs** | Group Configs

Group User Map Sync
 Yes

Username Attribute

User Object Class

User Search Base

User Search Filter

User Search Scope

User Group Name Attribute

6. Set the following properties on the Group Configs tab.

Table 3.9. LDAP/AD Group Configs

Property	Description	Default Value	Sample Values
Enable Group Sync	<p>If Enable Group Sync is set to No, the group names the users belong to are derived from "User Group Name Attribute". In this case no additional group filters are applied.</p> <p>If Enable Group Sync is set to Yes, the groups the users belong to are retrieved from LDAP/AD using the following group-related attributes.</p>	No	Yes
Group Member Attribute	The LDAP group member attribute name.		member
Group Name Attribute	The LDAP group name attribute.		distinguishedName for AD, cn for OpenLdap
Group Object Class	LDAP Group object class.		group, groupofnames, or posixGroup
Group Search Base	Search base for groups.		ou=groups,DC=example,DC=com
Group Search Filter	Optional additional filter constraining the groups selected for syncing.		<p>Sample filter to retrieve all groups: cn=*</p> <p>Sample filter to retrieve only the groups whose cn is Engineering or Sales: (& (cn=Engineering)(cn=Sales))</p>

The screenshot shows the 'Add Service Wizard' interface with the 'Ranger User Info' tab selected. The 'Enable User Sync' toggle is set to 'Yes'. The 'Sync Source' dropdown is set to 'LDAP/AD'. Below this, there are three sub-tabs: 'Common Configs', 'User Configs', and 'Group Configs', with 'Group Configs' being the active one. Under 'Group Configs', the following fields are visible: 'Enable Group Sync' (Yes), 'Group Member Attribute' (member), 'Group Name Attribute' (ou), 'Group Object Class' (groupOfNames), 'Group Search Base' (dc=qa,dc=hortonworks,dc=com), and 'Group Search Filter' (ou=*).

3.1.3.2.4. Configure Ranger Authentication

This section describes how to configure Ranger authentication for UNIX, LDAP, and AD.

- [Configuring Ranger UNIX Authentication \[156\]](#)
- [Configuring Ranger LDAP Authentication \[158\]](#)
- [Configuring Ranger Active Directory Authentication \[161\]](#)

3.1.3.2.4.1. Configuring Ranger UNIX Authentication

Use the following steps to configure Ranger authentication for UNIX.

1. Select the Advanced tab on the Customize Services page.
2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the **External URL** box in the format `http://<your_ranger_host>:6080`.

3. Under Ranger Settings, select **UNIX**.

HTTP is enabled by default – if you disable HTTP, only HTTPS is allowed.

4. Under UNIX Authentication Settings, set the following properties.

Table 3.10. UNIX Authentication Settings

Property	Description	Default Value	Example Value
Allow remote Login	Flag to enable/disable remote login. Only applies to UNIX authentication.	true	true
ranger.unixauth.service.hostname	The address of the host where the UNIX authentication service is running.	{{ugsync_hostname}}	{{ugsync_host}}
ranger.unixauth.service.port	The port number on which the UNIX authentication service is running.	5151	5151



Note

Properties with value `{{xyz}}` are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

Add Service Wizard

Ranger Settings

External URL:

Authentication method: LDAP
 ACTIVE_DIRECTORY
 UNIX
 NONE

HTTP enabled:

Unix Authentication Settings

Allow remote Login:

ranger.unixauth.service.hostname:

ranger.unixauth.service.port:

Knox SSO Settings

Advanced ranger-admin-site

3.1.3.2.4.2. Configuring Ranger LDAP Authentication



Note

You can use the [LDAP Connection Check tool](#) to determine authentication settings for LDAP.

Use the following steps to configure Ranger authentication for LDAP.

1. Select the Advanced tab on the Customize Services page.
2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the **External URL** box in the format `http://<your_ranger_host>:6080`.
3. Under Ranger Settings, select **LDAP**.
4. Under LDAP Settings, set the following properties.

Table 3.11. LDAP Authentication Settings

Property	Description	Default Value	Example Value
ranger.ldap.base.dn	The Distinguished Name (DN) of the starting point for directory server searches.	dc=example,dc=com	dc=example,dc=com
Bind User	The full Distinguished Name (DN), including Common Name (CN) of an LDAP user account that has privileges to search for users. This is a macro variable value that is derived from the Bind User value from Ranger User Info > Common Configs .	{{ranger_ug_ldap_bind_dn}}ranger_ug_ldap_bind_dn}}	
Bind User Password	Password for the Bind User. This is a macro variable value that is derived from the Bind User Password value from Ranger User Info > Common Configs .		

Property	Description	Default Value	Example Value
ranger.ldap.group.roleattribute	The LDAP group role attribute.	cn	cn
ranger.ldap.referral	See description below.	ignore	follow ignore throw
LDAP URL	The LDAP server URL. This is a macro variable value that is derived from the LDAP/AD URL value from Ranger User Info > Common Configs .	{{ranger_ug_ldap_url}}	{{ranger_ug_ldap_url}}
ranger.ldap.user.dnpattern	The user DN pattern is expanded when a user is being logged in. For example, if the user "ldapadmin" attempted to log in, the LDAP Server would attempt to bind against the DN "uid=ldapadmin,ou=users,dc=example,dc=com" using the password the user provided>	uid={0},ou=users,dc=xasecure,dc=net	cn=ldapadmin,ou=Users,dc=example,dc=com
User Search Filter	The search filter used for Bind Authentication. This is a macro variable value that is derived from the User Search Filter value from Ranger User Info > User Configs .	{{ranger_ug_ldap_user_searchfilter}}	{{ranger_ug_ldap_user_searchfilter}}



Note

Properties with value `{{xyz}}` are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

There are three possible values for `ranger.ldap.referral`: `follow`, `throw`, and `ignore`. The recommended setting is `follow`.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

- When this property is set to `follow`, the LDAP service provider processes all of the normal entries first, and then follows the continuation references.
- When this property is set to `throw`, all of the normal entries are returned in the enumeration first, before the `ReferralException` is thrown. By contrast, a "referral" error response is processed immediately when this property is set to `follow` or `throw`.
- When this property is set to `ignore`, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search.

3.1.3.2.4.3. Configuring Ranger Active Directory Authentication



Note

You can use the [LDAP Connection Check tool](#) to determine authentication settings for Active Directory.

Use the following steps to configure Ranger authentication for Active Directory.

1. Select the Advanced tab on the Customize Services page.
2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the **External URL** box in the format `http://<your_ranger_host>:6080`.
3. Under Ranger Settings, select **ACTIVE_DIRECTORY**.
4. Under AD Settings, set the following properties.

Table 3.12. AD Settings

Property	Description	Default Value	Example Value
ranger.ldap.ad.base.dn	The Distinguished Name (DN) of the starting point for directory server searches.	dc=example,dc=com	dc=example,dc=com
ranger.ldap.ad.bind.dn	The full Distinguished Name (DN), including Common Name (CN) of an LDAP user account that has privileges to search for users. This is a macro variable value that is derived from the Bind User value from Ranger User Info > Common Configs .	{{ranger_ug_ldap_bind_dn}}	{{ranger_ug_ldap_bind_dn}}
ranger.ldap.ad.bind.password	Password for the bind.dn. This is a macro variable value that is derived from the Bind User Password value from Ranger User Info > Common Configs .		
Domain Name (Only for AD)	The domain name of the AD Authentication service.		dc=example,dc=com
ranger.ldap.ad.referral	See description below.	ignore	follow ignore throw
ranger.ldap.ad.url	The AD server URL. This is a macro variable value that is derived from the LDAP/AD URL value from Ranger User Info > Common Configs .	{{ranger_ug_ldap_url}}	{{ranger_ug_ldap_url}}
ranger.ldap.ad.user.searchfilter	The search filter used for Bind Authentication. This is a macro variable value that is derived from the User Search Filter value from Ranger User Info > User Configs .	{{ranger_ug_ldap_user_searchfilter}}	{{ranger_ug_ldap_user_searchfilter}}



Note

Properties with value `{{xyz}}` are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

There are three possible values for `ranger.ldap.ad.referral`: `follow`, `throw`, and `ignore`. The recommended setting is `follow`.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

- When this property is set to `follow`, the AD service provider processes all of the normal entries first, and then follows the continuation references.

- When this property is set to `throw`, all of the normal entries are returned in the enumeration first, before the `ReferralException` is thrown. By contrast, a "referral" error response is processed immediately when this property is set to `follow` or `throw`.
- When this property is set to `ignore`, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search. In the case of AD, a `PartialResultException` is returned when referrals are encountered while search results are processed.

The screenshot shows the 'Add Service Wizard' dialog box. It has two main sections: 'Ranger Settings' and 'AD Settings'.

Ranger Settings:

- External URL: `http://05403.ambari.apache.org:6080`
- Authentication method: ACTIVE_DIRECTORY, LDAP, UNIX, NONE
- HTTP enabled:

AD Settings:

- ranger ldap.ad.base.dn: `dc=example,dc=com`
- ranger ldap.ad.bind.dn: `{{ranger_ug_ldap_bind_dn}}`
- ranger ldap.ad.bind.password: [Redacted]
- Domain Name (Only for AD): `dc=hwqe,dc=hortonworks,dc=com`
- ranger ldap.ad.referral: `ignore`
- ranger ldap.ad.uri: `{{ranger_ug_ldap_uri}}`
- ranger ldap.ad.user.searchfilter: `{{ranger_ug_ldap_user_searchfilter}}`

Below the AD Settings are sections for 'Knox SSO Settings' and 'Advanced ranger-admin-site'.

When you have finished configuring all of the Customize Services Settings, click **Next** at the bottom of the page to continue with the installation.

5. When you save the authentication method as Active Directory, a Dependent Configurations pop-up may appear recommending that you set the authentication method as LDAP. This recommended configuration should not be applied for AD, so you should clear (un-check) the `ranger.authentication.method` check box, then click **OK**.

The screenshot shows the 'Dependent Configurations' dialog box. It contains a message: "Based on your configuration changes, Ambari is recommending the following dependent configuration changes. Ambari will update all checked configuration changes to the Recommended Value. Uncheck any configuration to retain the Current Value."

<input type="checkbox"/>	Property	Service	Config Group	File Name	Current Value	Recommended Value
<input checked="" type="checkbox"/>	ranger.authentication.method	Ranger	Default	ranger-admin-site	UNIX	LDAP

At the bottom right, there are 'Cancel' and 'OK' buttons.

3.1.3.3. Complete the Ranger Installation

1. On the Review page, carefully review all of your settings and configurations. If everything looks good, click **Deploy** to install Ranger on the Ambari server.

Add Service Wizard

ADD SERVICE WIZARD

- Choose Services
- Assign Masters
- Assign Slaves and Clients
- Customize Services
- Configure Identities
- Review**
- Install, Start and Test
- Summary

Review

Please review the configuration before installation

Admin Name : admin
 Cluster Name : Thomas1
 Total Hosts : 3 (0 new)

Repositories:

- redhat5 (HDP-2.2):
http://public-repo-1.hortonworks.com/HDP/centos5/2.x/updates/2.2.6.0
- redhat5 (HDP-UTILS-1.1.0.20):
http://public-repo-1.hortonworks.com/HDP-UTILS-1.1.0.20/repos/centos5
- redhat6 (HDP-2.2):
http://public-repo-1.hortonworks.com/HDP/centos6/2.x/updates/2.2.6.0
- redhat6 (HDP-UTILS-1.1.0.20):
http://public-repo-1.hortonworks.com/HDP-UTILS-1.1.0.20/repos/centos6
- suse11 (HDP-2.2):
http://public-repo-1.hortonworks.com/HDP/suse11sp3/2.x/updates/2.2.6.0
- suse11 (HDP-UTILS-1.1.0.20):
http://public-repo-1.hortonworks.com/HDP-UTILS-1.1.0.20/repos/suse11sp3
- ubuntu12 (HDP-2.2):
http://public-repo-1.hortonworks.com/HDP/ubuntu12/2.x/updates/2.2.6.3

← Back Print **Deploy** →

2. When you click **Deploy**, Ranger is installed on the specified host on your Ambari server. A progress bar displays the installation progress.

Add Service Wizard

ADD SERVICE WIZARD

- Choose Services
- Assign Masters
- Assign Slaves and Clients
- Customize Services
- Configure Identities
- Review
- Install, Start and Test**
- Summary

Install, Start and Test

Please wait while the selected services are installed and started.

24 % overall

Show: **All (3)** | In Progress (0) | Warning (0) | Success (0) | Fail (0)

Host	Status	Message
c6401.ambari.apache.org	6%	Installing Ranger Admin
c6402.ambari.apache.org	33%	Install complete (Waiting to start)
c6403.ambari.apache.org	33%	Install complete (Waiting to start)

3 of 3 hosts showing - Show All Show: 25 | 1 - 3 of 3

Next →

3. When the installation is complete, a Summary page displays the installation details. You may need to restart services for cluster components after installing Ranger.



Note

If the installation fails, you should complete the installation process, then reconfigure and reinstall Ranger.

3.1.3.4. Advanced Usersync Settings

To access Usersync settings, select the Advanced tab on the Customize Service page. Usersync pulls in users from UNIX, LDAP, or AD and populates Ranger's local user tables with these users.



Important

To ensure that LDAP/AD group level authorization is enforced in Hadoop, you must first [set up Hadoop group mapping](#) for LDAP.

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

3.1.3.4.1. UNIX Usersync Settings

If you are using UNIX authentication, the default values for the Advanced ranger-ugsync-site properties are the settings for UNIX authentication.

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

▼ Advanced ranger-ugsync-site

ranger.usersync.idap.bindkeystore	<input type="text"/>	🔒	➕	
ranger.usersync.idap.idapbindpassword	Type password <input type="password"/>	🔒	➕	🔒
ranger.usersync.group.memberattributename	<input type="text"/>	🔒	➕	🔄
ranger.usersync.group.nameattribute	<input type="text"/>	🔒	➕	🔄
ranger.usersync.group.objectclass	<input type="text"/>	🔒	➕	🔄
ranger.usersync.group.searchbase	<input type="text"/>	🔒	➕	🔄
ranger.usersync.group.searchenabled	false	🔒	➕	🔄
ranger.usersync.group.searchfilter	<input type="text"/>	🔒	➕	🔄
ranger.usersync.group.searchscope	<input type="text"/>	🔒	➕	🔄
ranger.usersync.group.usermapsyncenabled	false	🔒	➕	🔄
ranger.usersync.idap.searchBase	dc=hadoop,dc=apache,dc=org	🔒	➕	🔄
ranger.usersync.source.impl.class	org.apache.ranger.unixusersync.process.UnixUserGroupBuilder	🔒	➕	🔄
ranger.usersync.credstore.filename	/usr/hdp/current/ranger-usersync/conf/ugsync.jceks	🔒	➕	🔄
ranger.usersync.enabled	true	🔒	➕	🔄
ranger.usersync.filesource.file	/tmp/usergroup.txt	🔒	➕	🔄
ranger.usersync.filesource.text.delimiter	,	🔒	➕	🔄
ranger.usersync.keystore.file	/usr/hdp/current/ranger-usersync/conf/unixauthservice.jks	🔒	➕	🔄

3.1.3.4.2. Required LDAP and AD Usersync Settings

If you are using LDAP authentication, you must update the following Advanced ranger-ugsync-site properties.

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

Table 3.13. LDAP Advanced ranger-ugsync-site Settings

Property Name	LDAP Value
ranger.usersync.ldap.bindkeystore	Set this to the same value as the <code>ranger.usersync.credstore.filename</code> property, i.e, the default value is <code>/usr/hdp/current/ranger-usersync/conf/ugsync.jceks</code>
ranger.usersync.ldap.bindalias	ranger.usersync.ldap.bindalias
ranger.usersync.source.impl.class	ldap

Table 3.14. AD Advanced ranger-ugsync-site Settings

Property Name	LDAP Value
ranger.usersync.source.impl.class	ldap

3.1.3.4.3. Additional LDAP and AD Usersync Settings

If you are using LDAP or Active Directory authentication, you may need to update the following properties, depending upon your specific deployment characteristics.

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

Table 3.15. Advanced ranger-ugsync-site Settings for LDAP and AD

Property Name	LDAP ranger-ugsync-site Value	AD ranger-ugsync-site Value
ranger.usersync.ldap.url	ldap://127.0.0.1:389	ldap://ad-conrowoller-hostname:389
ranger.usersync.ldap.binddn	cn=ldapadmin,ou=users,dc=example,dc=com	cn=adadmin,cn=Users,dc=example,dc=com
ranger.usersync.ldap.ldapbindpassword	secret	secret
ranger.usersync.ldap.searchBase	dc=example,dc=com	dc=example,dc=com
ranger.usersync.source.impl.class	org.apache.ranger.ladpusersync.process.LdapUserGroupBuilder	
ranger.usersync.ldap.user.searchbase	ou=users, dc=example, dc=com	dc=example,dc=com
ranger.usersync.ldap.user.searchscope	sub	sub
ranger.usersync.ldap.user.objectclass	person	person
ranger.usersync.ldap.user.searchfilter	Set to single empty space if no value. Do not leave it as "empty"	(objectcategory=person)
ranger.usersync.ldap.user.nameattribute	uid or cn	sAMAccountName
ranger.usersync.ldap.user.groupnameattribute	memberof,ismemberof	memberof,ismemberof
ranger.usersync.ldap.username.caseconversion	none	none
ranger.usersync.ldap.groupname.caseconversion	none	none

Property Name	LDAP ranger-ugsync-site Value	AD ranger-ugsync-site Value
ranger.usersync.group.searchenabled *	false	false
ranger.usersync.group.usermapsyncenabled *	false	false
ranger.usersync.group.searchbase *	ou=groups, dc=example, dc=com	dc=example,dc=com
ranger.usersync.group.searchscope *	sub	sub
ranger.usersync.group.objectclass *	groupofnames	groupofnames
ranger.usersync.group.searchfilter *	needed for AD authentication	(member=CN={0}, OU=MyUsers, DC=AD-HDP, DC=COM)
ranger.usersync.group.nameattribute *	cn	cn
ranger.usersync.group.memberattributename *	member	member
ranger.usersync.pagedresultsenabled *	true	true
ranger.usersync.pagedresultssize *	500	500
ranger.usersync.user.searchenabled *	false	false
ranger.usersync.group.search.first.enabled *	false	false

* Only applies when you want to filter out groups.

After you have finished specifying all of the settings on the Customize Services page, click **Next** at the bottom of the page to continue with the installation.

3.1.3.5. Configuring Ranger for LDAP SSL

You can use the following steps to configure LDAP SSL using self-signed certs in the default Ranger User Sync TrustStore.

1. The default location is `/usr/hdp/current/ranger-usersync/conf/mytruststore.jks` for the `ranger.usersync.truststore.file` property.
2. Alternatively, copy and edit the self-signed ca certs.
3. Set the `ranger.usersync.truststore.file` property to that new cacert file.

```
cd /usr/hdp/<version>/ranger-usersync
service ranger-usersync stop
service ranger-usersync start
```

Where `cert.pem` has the LDAPS cert.

3.1.3.6. Setting up Database Users Without Sharing DBA Credentials

If do not wish to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the `dba_script.py` Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger

installer. You can then run the normal Ambari Ranger installation without specifying a DBA user name and password.

To create Ranger DB users using the `dba_script.py` script:

1. Download the Ranger rpm using the yum install command.

```
yum install ranger-admin
```

2. You should see one file named `dba_script.py` in the `/usr/hdp/current/ranger-admin` directory.
3. Get the script reviewed internally and verify that your DBA is authorized to run the script.
4. Execute the script by running the following command:

```
python dba_script.py
```

5. Pass all values required in the argument. These should include `db flavor`, `JDBC jar`, `db host`, `db name`, `db user`, and other parameters.

- If you would prefer not to pass runtime arguments via the command prompt, you can update the `/usr/hdp/current/ranger-admin/install.properties` file and then run:

```
python dba_script.py -q
```

When you specify the `-q` option, the script will read all required information from the `install.properties` file

- You can use the `-d` option to run the script in "dry" mode. Running the script in dry mode causes the script to generate a database script.

```
python dba_script.py -d /tmp/generated-script.sql
```

Anyone can run the script, but it is recommended that the system DBA run the script in dry mode. In either case, the system DBA should review the generated script, but should only make minor adjustments to the script, for example, change the location of a particular database file. No major changes should be made that substantially alter the script – otherwise the Ranger install may fail.

The system DBA must then run the generated script.


6. Run the Ranger Ambari install procedure, but set **Setup Database and Database User** to **No** in the Ranger Admin section of the Customize Services page.

3.1.3.7. Updating Ranger Admin Passwords

For the following users, if you update the passwords on the Ranger Configs page, you must also update the passwords on the Configs page of each Ambari component that has the Ranger plugin enabled. Individual Ambari component configurations are not automatically updated – the service restart will fail if you do not update these passwords on each component.

- Ranger Admin user – The credentials for this user are set in **Configs > Advanced ranger-env** in the fields labeled **admin_username** (default value: `admin`) and **admin_password** (default value: `admin`).
- Admin user used by Ambari to create repo/policies – The user name for this user is set in **Configs > Admin Settings** in the field labeled **Ranger Admin username for Ambari** (default value: `amb_ranger_admin`). The password for this user is set in the field labeled **Ranger Admin user's password for Ambari**. This password is specified during the Ranger installation.

The following image shows the location of these settings on the Ranger Configs page:



3.1.4. Enabling Ranger Plugins

Ranger plugins can be enabled for several HDP services. This section describes how to enable each of these plugins. For performance reasons, it is recommended that you store audits in Solr and HDFS, and not in a database.

If you are using a Kerberos-enabled cluster, there are a number of additional steps you must follow to ensure that you can use the Ranger plugins on a Kerberos cluster.

The following Ranger plugins are available:


- [HDFS \[171\]](#)
- [Hive \[175\]](#)

- [HBase \[178\]](#)
- [Kafka \[181\]](#)
- [Knox \[185\]](#)
- [YARN \[188\]](#)
- [Storm \[192\]](#)

3.1.4.1. HDFS

Use the following steps to enable the Ranger HDFS plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.




The screenshot shows the Ambari interface for the Ranger Configs page. The top navigation bar includes 'Ambari', 'c6401_TEST', 'ops', '15 alerts', 'Dashboard', 'Services', 'Hosts 1', 'Alerts', 'Admin', and 'admin'. The left sidebar lists various services, with 'Ranger' selected. The main content area shows the 'Ranger Configs' page with tabs for 'Summary', 'Configs', 'Quick Links', and 'Service Actions'. The 'Configs' tab is active, showing a 'Group' dropdown set to 'Default (1)' and a 'Manage Config Groups' button. Below this, there are three config groups: 'V3 admin 6 days ago HDP-2.3', 'V2 admin 7 days ago HDP-2.3', and 'V1 admin 13 days ago HDP-2.3'. A black menu bar at the bottom of the config groups shows 'V3' selected, a checkmark, and the text 'admin authored on Wed, Feb 03, 2016 11:28', with 'Discard' and 'Save' buttons. The 'Ranger Plugin' tab is selected, showing a grid of plugins with their status:

Plugin Name	Status
HDFS Ranger Plugin	ON
Hbase Ranger Plugin	ON
Knox Ranger Plugin	ON
YARN Ranger Plugin	ON
Storm Ranger Plugin	OFF
Kafka Ranger Plugin	ON
Hive Ranger Plugin	ON


2. Under HDFS Ranger Plugin, select **On**, then click **Save** in the black menu bar.




3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.




4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.




- 5. Click **OK** on the Save Configuration Changes pop-up.



- 6. Select **HDFS** in the navigation menu, then select **Restart > Restart All Affected** to restart the HDFS service and load the new configuration.



7. Click **Confirm Restart All** on the confirmation pop-up to confirm the HDFS restart.




8. After HDFS restarts, the Ranger plugin for HDFS will be enabled. Other components may also require a restart.


3.1.4.2. Hive

Use the following steps to enable the Ranger Hive plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.



2. Under Hive Ranger Plugin, select **On**, then click **Save** in the black menu bar.




3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



Save Configuration X

Notes

4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.




Dependent Configurations X


Based on your configuration changes, Ambari is recommending the following dependent configuration changes.
Ambari will update all checked configuration changes to the Recommended Value. Uncheck any configuration to retain the Current Value.

<input checked="" type="checkbox"/>	Property	Service	Config Group	File Name	Current Value	Recommended Value
<input checked="" type="checkbox"/>	hive_security_authorization	Hive	Default	hive-env	None	Ranger
<input checked="" type="checkbox"/>	hive.security.authorization.enabled	Hive	Default	hive-site	false	true
<input checked="" type="checkbox"/>	hive.server2.enable.doAs	Hive	Default	hive-site	true	false
<input checked="" type="checkbox"/>	hive.security.authorization.enabled	Hive	Default	hiveserver2-site	false	true
<input checked="" type="checkbox"/>	hive.conf.restricted.list	Hive	Default	hiveserver2-site		hive.security.authorization.enabled,hive.security.authorization.manager,hive.security.authenticator.manager
<input checked="" type="checkbox"/>	hive.security.authenticator.manager	Hive	Default	hiveserver2-site		org.apache.hadoop.hive.qj.security.SessionStateUserAuthenticator
<input checked="" type="checkbox"/>	hive.security.authorization.manager	Hive	Default	hiveserver2-site		org.apache.ranger.authorization.hive.authorizer.RangerHiveAuthorizerFactory


5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **Hive** in the navigation menu, then select **Restart > Restart All Affected** to restart the Hive service and load the new configuration.



7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Hive restart.



8. After Hive restarts, the Ranger plugin for Hive will be enabled.

3.1.4.3. HBase




Note


When HBase is configured with Ranger, and specifically XASecure Authorizer, you may only grant and revoke privileges.

Use the following steps to enable the Ranger HBase plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.




2. Under HBase Ranger Plugin, select **On**, then click **Save** in the black menu bar.




3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



- 4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.



- 5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **HBase** in the navigation menu, then select **Restart > Restart All Affected** to restart the HBase service and load the new configuration.

The screenshot shows the Ambari web interface for the HBase service. The left sidebar contains a navigation menu with various services like HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger, Slider, and Spark. The main content area is titled 'Summary' and shows a notification: 'Restart Required: 3 Components on 1 Host'. Below this, there are configuration groups for 'HBase Default (1)'. A 'Restart' button is visible, and a 'Restart All Affected' button is highlighted with a red box. Below the configuration groups, there are sections for 'HBase Master' and 'RegionServer' with various configuration parameters like 'HBase Master hosts', 'HBase Master Maximum Memory', 'HBase RegionServer Maximum Memory', 'Number of Handlers per RegionServer', 'HBase Region Major Compaction Interval', 'HBase Region Block Multiplier', and 'Memstore Flush Size'.

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the HBase restart.


The screenshot shows a 'Confirmation' dialog box with the title 'Confirmation' and a close button (X). The main text reads: 'You are about to restart HBase'. Below this, there is a yellow warning box containing the text: 'This will trigger alerts as the service is restarted. To suppress alerts, turn on Maintenance Mode for HBase prior to running restart all'. At the bottom of the dialog, there are two buttons: 'Cancel' and 'Confirm Restart All', with the 'Confirm Restart All' button highlighted by a red box.

8. After HBase restarts, the Ranger plugin for HBase will be enabled.


3.1.4.4. Kafka

Use the following steps to enable the Ranger Kafka plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.



2. Under Kafka Ranger Plugin, select **On**, then click **Save** in the black menu bar.




3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.




5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **Kafka** in the navigation menu, then select **Restart > Restart All Affected** to restart the Kafka service and load the new configuration.

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Kafka restart.




8. After Kafka restarts, the Ranger plugin for Kafka will be enabled.


3.1.4.5. Knox

Use the following steps to enable the Ranger Knox plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.



2. Under Knox Ranger Plugin, select **On**, then click **Save** in the black menu bar.



3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.

Dependent Configurations

Based on your configuration changes, Ambari is recommending the following dependent configuration changes.
Ambari will update all checked configuration changes to the Recommended Value. Uncheck any configuration to retain the Current Value.

Property	Service	Config Group	File Name	Current Value	Recommended Value
<input checked="" type="checkbox"/> ranger-knox-plugin-enabled	Knox	Default	ranger-knox-plugin-properties	No	Yes
<input checked="" type="checkbox"/> content	Knox	Default	topology	<topology> <gateway> <provider> <role><authentication><role> <name> a2ShcProvider<name> <enable> d=true</enable> <param> <name> a-sessionTimeout<name> <valu> e=30</value> </param> </param> <name>main.idapRealm</name> <v> alio-org.apache.hadoop.gateway.s horealm.KnoxIdapRealm</value> </param> </param> <name>main.id< apRealm.userDnTemplate<name> <value>uid=%%ou=people,dc=had< op,dc=apache,dc=org</value> </pa< ram> </param> <name>main.idapRe< alm.contextFactory.uri</name> <val</> ue=idap://knox_host_name[:3333</> /value> </param> </param> <name> a-main.idapRealm.contextFactory.a</> uthenticationMechanism</name> <v</> alue=simple</value> </param> </par</> am> <name>url_1</name> <valu</> e=szthcBasic</value> </param> </provider> </provider> </value>	<topology> <gateway> <provider> <role><authentication><role> <name> a2ShcProvider<name> <enable> d=true</enable> <param> <name> a-sessionTimeout<name> <valu> e=30</value> </param> </param> <name>main.idapRealm</name> <v> alio-org.apache.hadoop.gateway.s horealm.KnoxIdapRealm</value> </param> </param> <name>main.id< apRealm.userDnTemplate<name> <value>uid=%%ou=people,dc=had< op,dc=apache,dc=org</value> </pa< ram> </param> <name>main.idapRe< alm.contextFactory.uri</name> <val</> ue=idap://knox_host_name[:3333</> /value> </param> </param> <name> a-main.idapRealm.contextFactory.a</> uthenticationMechanism</name> <v</> alue=simple</value> </param> </par</> am> <name>url_1</name> <valu</> e=szthcBasic</value> </param> </provider> </provider> </value>

Cancel **OK**


5. Click **OK** on the Save Configuration Changes pop-up.

Save Configuration Changes


Service configuration changes saved successfully.

OK

6. Select **Knox** in the navigation menu, then select **Restart > Restart All Affected** to restart the Knox service and load the new configuration.



7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Knox restart.




8. After Knox restarts, the Ranger plugin for Knox will be enabled.


3.1.4.6. YARN

Use the following steps to enable the Ranger YARN plugin.

1. On the Ranger Configs page, select the **Ranger Plugin** tab.



2. Under YARN Ranger Plugin, select **On**, then click **Save** in the black menu bar.



3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.

6. Select **YARN** in the navigation menu, then select **Restart > Restart All Affected** to restart the YARN service and load the new configuration.

The screenshot shows the Ambari interface for the YARN service. At the top, a yellow banner indicates "Restart Required: 4 Components on 1 Host". A red box highlights the "Restart All Affected" button in the "Service Actions" menu. Below this, the configuration page is displayed with tabs for "Summary", "Hostmaps", and "Configs". The "Configs" tab is active, showing various configuration sliders for Memory, CPU, and YARN Features. The "Memory" section includes sliders for Node memory (set to 612 MB) and Container memory (Minimum: 172 MB, Maximum: 612 MB). The "CPU" section includes sliders for Node CPU Scheduling (Disabled) and Container CPU Scheduling (set to 1). The "YARN Features" section includes sliders for Node Labels (Disabled) and Pre-emption (Disabled).

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the YARN restart.

The screenshot shows a "Confirmation" dialog box with the title "Confirmation" and a close button (X). The main text reads "You are about to restart YARN". Below this, a yellow box contains the warning: "This will trigger alerts as the service is restarted. To suppress alerts, turn on Maintenance Mode for YARN prior to running restart all". At the bottom of the dialog, there are two buttons: "Cancel" and "Confirm Restart All". The "Confirm Restart All" button is highlighted with a red box.


8. After YARN restarts, the Ranger plugin for YARN will be enabled. Other components may also require a restart.

3.1.4.7. Storm

Before you can use the Storm plugin, you must first enable Kerberos on your cluster. To enable Kerberos on your cluster, see [Enabling Kerberos Authentication Using Ambari](#).

Use the following steps to enable the Ranger Storm plugin.

1. On the Ranger Configs page, select the **Ranger Plugin** tab.




The screenshot shows the Ambari interface for configuring Ranger. The top navigation bar includes 'Ambari c6401_TEST', 'Dashboard', 'Services', 'Hosts 1', 'Alerts', and 'Admin'. The left sidebar lists various services, with 'Ranger' highlighted. The main content area is titled 'Ranger Configs' and shows a list of configuration groups. The 'Ranger Plugin' tab is selected, displaying a grid of plugin status toggles:


Plugin Name	Status
HDFS Ranger Plugin	ON
Hbase Ranger Plugin	ON
Knox Ranger Plugin	ON
YARN Ranger Plugin	ON
Storm Ranger Plugin	OFF
Kafka Ranger Plugin	ON
Hive Ranger Plugin	ON

A black menu bar at the bottom of the plugin configuration area contains 'Discard' and 'Save' buttons. The 'Save' button is highlighted, indicating it is the next step in the process.


2. Under Storm Ranger Plugin, select **On**, then click **Save** in the black menu bar.




3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.




4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.




5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **Storm** in the navigation menu, then select **Restart > Restart All Affected** to restart the Storm service and load the new configuration.



7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Storm restart.



8. After Storm restarts, the Ranger plugin for Storm will be enabled.

3.1.5. Ranger Plugins - Kerberos Overview

If you are using a Kerberos-enabled cluster, there are a number of steps you need to follow to ensure you can use the different Ranger plugins on a Kerberos cluster. These plugins are:

1. [HDFS \[195\]](#)
2. [Hive \[196\]](#)
3. [HBase \[197\]](#)
4. [Knox \[197\]](#)



Note

These procedures assume that you have already [enabled Ranger plugins](#).

3.1.5.1. HDFS

To enable the Ranger HDFS plugin on a Kerberos-enabled cluster, perform the steps described below.

1. Create the system (OS) user `rangerhdfslookup`. Make sure this user is synced to Ranger Admin (under *Settings>Users/Groups* tab in the Ranger Admin User Interface).
2. Create a Kerberos principal for `rangerhdfslookup` by entering the following command:

```
• kadmin.local -q 'addprinc -pw rangerhdfslookup  
rangerhdfslookup@example.com'
```



Note

A single user/principal (e.g., `rangerrepouser`) can also be created and used across services.

3. Navigate to the HDFS service.
4. Click the **Config** tab.
5. Navigate to *advanced ranger-hdfs-plugin-properties* and update the properties listed in the table shown below.

Table 3.16. HDFS Plugin Properties

Configuration Property Name	Value
Ranger repository config user	rangerhdfslookup@example.com
Ranger repository config password	rangerhdfslookup
common.name.for.certificate	blank

6. After updating these properties, click **Save** and restart the HDFS service.

3.1.5.2. Hive

To enable the Ranger Hive plugin on a Kerberos-enabled cluster, perform the steps described below.

1. Create the system (OS) user `rangerhivelookup`. Make sure this user is synced to Ranger Admin (under *Settings>Users/Groups* tab in the Ranger Admin UI).
2. Create a Kerberos principal for `rangerhivelookup` by entering the following command:
 - `kadmin.local -q 'addprinc -pw rangerhivelookup rangerhivelookup@example.com'`
3. Navigate to the Hive service.
4. Click the **Config** tab and navigate to *advanced ranger-hive-plugin-properties*.
5. Update the following properties with the values listed in the table below.

Table 3.17. Hive Plugin Properties

Configuration Property Name	Value
Ranger service config user	rangerhivelookup@example.com
Ranger service config password	rangerhivelookup
common.name.for.certificate	blank

6. After updating these properties, click **Save** and then restart the Hive service.

3.1.5.3. HBase

To enable the Ranger HBase plugin on a Kerberos-enabled cluster, perform the steps described below.

1. Create the system (OS) user `rangerhbaselookup`. Make sure this user is synced to Ranger Admin (under *users/groups* tab in the Ranger Admin UI).
2. Create a Kerberos principal for `rangerhbaselookup` by entering the following command:
 - `kadmin.local -q 'addprinc -pw rangerhbaselookup rangerhbaselookup@example.com'`
3. Navigate to the HBase service.
4. Click the **Config** tab and go to *advanced ranger-hbase-plugin-properties*.
5. Update the following properties with the values listed in the table below.

Table 3.18. HBase Plugin Properties

Configuration Property Name	Value
Ranger service config user	rangerhbaselookup@example.com
Ranger service config password	rangerhbaselookup
common.name.for.certificate	blank

6. After updating these properties, click **Save** and then restart the HBase service.

3.1.5.4. Knox

To enable the Ranger Knox plugin on a Kerberos-enabled cluster, perform the steps described below.

1. Create the system (OS) user `rangerknoxlookup`. Make sure this user is synced to Ranger Admin (under *Settings>Users/Groups* tab in the Ranger Admin UI).
2. Create a Kerberos principal for `rangerknoxlookup` by entering the following command:
 - `kadmin.local -q 'addprinc -pw rangerknoxlookup rangerknoxlookup@example.com'`
3. Navigate to the Knox service.
4. Click the **Config** tab and navigate to *advanced ranger-knox-plugin-properties*.
5. Update the following properties with the values listed in the table below.


Table 3.19. Knox Plugin Properties

Configuration Property Name	Value
Ranger service config user	rangerknoxlookup@example.com
Ranger service config password	rangerknoxlookup

Configuration Property Name	Value
common.name.for.certificate	blank


- After updating these properties, click **Save** and then restart the Knox service.
- Open the Ranger Admin UI by entering the following information:
 - `http://ranger-host>:6080`
 - username/password** - `admin/admin`. or use `username` as shown in *advanced ranger-env* under the **Config** tab of the Ranger service, and `password` as shown in **Admin Settings**.
- After you have successfully logged into the system, you will be redirected to the Access Manager page.

Figure 3.6. Knox Service Manager



- Click the repository (`clusterName_hadoop`) **Edit** option under the HDFS box.

Figure 3.7. Knox Service Edit



- Update the following properties listed in the table below under the Config Properties section:

Table 3.20. Knox Configuration Properties

Configuration Property Name	Value
fs.default.name	hdfs
hadoop.rpc.protection	blank
common.name.for.certificate	blank

- Click **Named Test Connection**. You should see a *Connected Successfully* dialog box appear.

12. Click **Save**.

3.2. Using Ranger to Provide Authorization in Hadoop


Once a user has been authenticated, their access rights must be determined. Authorization defines access rights to resources, or privileges of use (permissions) for users. For example, a user may be allowed to create a policy and view reports, but not allowed to edit users and groups. Ranger authorization controls this access rights process for:

- [Configuring Services \[201\]](#)
- [Policy Management \[218\]](#)
- [Users/Groups and Permissions Administration \[236\]](#)
- [Reports Administration \[246\]](#)


For more information on Ranger authorization, see the [Authorization](#) overview.

3.2.1. Opening and Closing the Ranger Console

To open the Ranger Console, log in to the Ranger portal at `http://<your_ranger_server_address>:6080`. To log in, enter your username and password, then click **Sign In**.




Ranger Console Home Page



Ranger Login Console

Once you log in, your user name is also displayed on the Ranger Console home page.




To log out of the Ranger Console, click your user name in the top menu, then select **Log Out**.




3.2.2. Console Operations Summary

The Ranger console controls four types of functions:


- **Service Manager** - (displayed when you log in). You can use the Service Manager page to create and administer resource-based services and policies.




The Access Manager menu includes the Resource Based Policies and Reports menu options.




- **Access Manager > Resource Based Policies** - opens the Service Manager page for resource-based policies. You can use the Service Manager page to create and administer resource-based services and policies.



- **The Audit tab** - monitors user activity at the resource level, and conditional auditing based on users, groups, or time. The Audit page includes the Access, Admin, Login Sessions, and Plugins tabs.



- **The Settings tab** - manages users and groups, and assigns policy permissions to users and groups. The dropdown menu includes the Users/Groups and Permissions menu options.




3.2.3. Configuring Services

The Ranger Access Manager is open by default in the Ranger Console. To return to the Access Manager from any tab in the Ranger Console, go to the top left corner of the console and click **Ranger, Access Manager, Service Manager, or Access Manager>Resource Based Policies**.



Note

The Ambari Ranger installation procedure automatically configures these services, so there should be no need to add a service manually.



- **To add a new service** to Resource Based Policies, click the



icon in the applicable box on the Service Manager page.

Enter the required configuration settings, then click **Add**



).

- To edit a service, click




to the right of the entry for that service. Resource Based Policies displays an expanded view of that service, including a list of the policies it contains, their status, and the groups designated to administer those policies.

- To delete a service from Resource Based Policies, click



to the right of the entry for that service. Deleting a service also deletes all the policies within that service.



Ranger Service Manager Console

This section describes how to configure services in:

- [Configure an HBase Service \[202\]](#)
- [Configure an HDFS Service \[204\]](#)
- [Configure a Hive Service \[207\]](#)
- [Configure a Kafka Service \[208\]](#)
- [Configure a Knox Service \[210\]](#)
- [Configure a Solr Service \[212\]](#)
- [Configure a Storm Service \[214\]](#)
- [Configure a YARN Service \[216\]](#)

3.2.3.1. Configure an HBase Service

Use the following steps to add a service to HBase:

1. On the Service Manager page, click the



icon next to HBase.

The Create Service page appears.

2. Enter the following information on the Create Service page:

Table 3.21. Service Details

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.

Field name	Description
Active Status	Enabled or Disabled.

Table 3.22. Config Properties

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
hadoop.security.authorization	The complete connection URL, including port and database name. (Default port: 10000.) For example, on the sandbox, jdbc:hive2://sandbox:10000/.
hbase.master.kerberos.principal	The Kerberos principal for the HBase Master. (Required only if Kerberos authentication is enabled.)
hbase.security.authentication	As noted in the hadoop configuration file hbase-site.xml.
hbase.zookeeper.property.clientPort	As noted in the hadoop configuration file hbase-site.xml.
hbase.zookeeper.quorum	As noted in the hadoop configuration file hbase-site.xml.
zookeeper.znode.parent	As noted in the hadoop configuration file hbase-site.xml.
Common Name for Certificate	The name of the certificate. This field is interchangeably named Common Name For Certificate and Ranger Plugin SSL CName in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.



4. Click **Add**.



3.2.3.2. Configure an HDFS Service

Use the following steps to add a service to HDFS:

1. On the Service Manager page, click the



icon next to HDFS.

The Create Service page appears.

2. Enter the following information on the Create Service page:

Table 3.23. Service Details

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

Table 3.24. Config Properties

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
Namenode URL	<code>hdfs://NAMENODE_FQDN:8020</code> The location of the Hadoop HDFS service, as noted in the hadoop configuration file <code>core-site.xml</code> OR (if this is a HA environment) the path for the primary NameNode. This field was formerly named <code>fs.defaultFS</code> .
Authorization Enabled	Authorization involves restricting access to resources. If enabled, user need authorization credentials.
Authentication Type	The type of authorization in use, as noted in the hadoop configuration file <code>core-site.xml</code> ; either <code>simple</code> or <code>Kerberos</code> . (Required only if authorization is enabled). This field was formerly named <code>hadoop.security.authorization</code> .
<code>hadoop.security.auth_to_local</code>	Maps the login credential to a username with Hadoop; use the value noted in the hadoop configuration file, <code>core-site.xml</code> .
<code>dfs.datanode.kerberos.principal</code>	The principal associated with the datanode where the service resides, as noted in the hadoop configuration file <code>hdfs-site.xml</code> . (Required only if Kerberos authentication is enabled).
<code>dfs.namenode.kerberos.principal</code>	The principal associated with the NameNode where the service resides, as noted in the hadoop configuration file <code>hdfs-site.xml</code> . (Required only if Kerberos authentication is enabled).
<code>dfs.secondary.namenode.kerberos.principal</code>	The principal associated with the secondary NameNode where the service resides, as noted in the hadoop configuration file <code>hdfs-site.xml</code> . (Required only if Kerberos authentication is enabled).
RPC Protection Type	Only authorised user can view, use, and contribute to a dataset. A list of protection values for secured SASL connections. Values: Authentication, Integrity, Privacy
Common Name For Certificate	The name of the certificate. This field is interchangeably named Common Name For Certificate and Ranger Plugin SSL CName in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click Test Connection.**4. Click Add.**

3.2.3.3. Configure a Hive Service

Use the following steps to add a service to Hive:

1. On the Service Manager page, click the



next to Hive.

The Create Service page appears.

2. Enter the following information on the Create Service page:

Table 3.25. Service Details

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

Table 3.26. Config Properties

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
jdbc.driver ClassName	The full classname of the driver used for Hive connections. Default: org.apache.hive.jdbc.HiveDriver
jdbc.url	The complete connection URL, including port and database name. (Default port: 10000.) For example, on the sandbox, jdbc:hive2://sandbox:10000/.
Common Name For Certificate	The name of the certificate. This field is interchangeably named Common Name For Certificate and Ranger Plugin SSL CName in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.



4. Click **Add**.



3.2.3.4. Configure a Kafka Service

Use the following steps to add a service to Kafka:

1. On the Service Manager page, click the



next to Kafka.

The Create Service page appears.

2. Enter the following information on the Create Service page:

Table 3.27. Service Details

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

Table 3.28. Config Properties

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
ZooKeeper Connect String	Defaults to localhost:2181 (Provide FQDN of zookeeper host : 2181).
Ranger Plugin SSL CName	Provide common.name.for.certificate which is registered with Ranger (in Wire Encryption environment).

Field name	Description
	This field is interchangeably named Common Name For Certificate and Ranger Plugin SSL CName in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.



4. Click **Add**.



3.2.3.5. Configure a Knox Service

Use the following steps to add a service to Knox:

1. On the Service Manager page, click the



next to Knox.

The Create Service page appears.

2. Enter the following information on the Create Service page:

Table 3.29. Service Details

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

Table 3.30. Config Properties

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
knox.url	The Gateway URL for Knox.
Common Name For Certificate	The name of the certificate.

Field name	Description
	This field is interchangeably named Common Name For Certificate and Ranger Plugin SSL CName in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.



4. Click **Add**.



3.2.3.6. Configure a Solr Service

Use the following steps to add a service to Solr:

1. On the Service Manager page, click the



next to Solr.

The Create Service page appears.

2. Enter the following information on the Create Service page:

Table 3.31. Service Details

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

Table 3.32. Config Properties

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
Solr URL	http://Solr_host:6083
Ranger Plugin SSL CName	Provide common.name.for.certificate which is registered with Ranger (in Wire Encryption environment).

Field name	Description
	This field is interchangeably named Common Name For Certificate and Ranger Plugin SSL CName in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.



4. Click **Add**.



3.2.3.7. Configure a Storm Service

Use the following steps to add a service to Storm:

1. On the Service Manager page, click the



next to Storm.

The Create Service page appears.

2. Enter the following information on the Create Service page:

Table 3.33. Service Details

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

Table 3.34. Config Properties

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
Nimbus URL	Hostname of nimbus format, in the form: <code>http://ipaddress:8080</code> . This field was formerly named nimbus.url.
Common Name For Certificate	The name of the certificate.

Field name	Description
	This field is interchangeably named Common Name For Certificate and Ranger Plugin SSL CName in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.



4. Click **Add**.



3.2.3.8. Configure a YARN Service

Use the following steps to add a service to YARN:

1. On the Service Manager page, click the



next to YARN.

The Create Service page appears.

2. Enter the following information on the Create Service page:

Table 3.35. Service Details

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

Table 3.36. Config Properties

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
YARN REST URL	Http or <code>https://RESOURCEMANAGER_FQDN:8088</code> .
Authentication Type	The type of authorization in use, as noted in the hadoop configuration file <code>core-site.xml</code> ; either <code>simple</code> or <code>Kerberos</code> . (Required only if authorization is enabled).

Field name	Description
	This field was formerly named hadoop.security.authorization.
Common Name For Certificate	The name of the certificate. This field is interchangeably named Common Name For Certificate and Ranger Plugin SSL CName in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.



4. Click **Add**.



3.2.4. Policy Management

To examine the policies associated with each service, go to the service where the service resides and click



The Ranger Service Manager view appears and an expanded view of that service displays, with the policies listed beneath. The policy view includes a search window.

- To add a new policy to the service, click **Add New Policy**



(

The form looks slightly different, depending on the type of service to which you are adding the policy.

- To edit a policy, click




to the right of the entry for that service. Resource Based Policies displays an expanded view of that policy.

- To delete a policy, click



Delete icon to the right of the entry for that service.

the




This section describes the requirements for policy creation in

- [Create an HBase Policy \[219\]](#)
- [Create an HDFS Policy \[221\]](#)
- [Create a Hive Policy \[224\]](#)
- [Create a Kafka Policy \[227\]](#)
- [Create a Knox Policy \[228\]](#)
- [Create a Solr Policy \[230\]](#)
- [Create a Storm Policy \[232\]](#)
- [Create a YARN Policy \[234\]](#)


3.2.4.1. Create an HBase Policy

To add a new policy to an existing HBase service:

1. On the Service Manager page, select an existing service under HBase.




The List of Policies page appears.



2. Click **Add New Policy**.



The Create Policy console appears.



3. Complete the Create Policy page as follows:

Table 3.37. Policy Details

Label	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
HBase Table	Select the appropriate database. Multiple databases can be selected for a particular policy. This field is mandatory.
HBase Column-family	For the selected table, specify the column families to which the policy applies.
HBase Column	For the selected table and column families, specify the columns to which the policy applies.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 3.38. User and Group Permissions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).

Label	Description
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- * indicates zero or more occurrences of characters
- ? indicates a single character

4. Click **Add**.



3.2.4.2. Provide User Access to HBase Database Tables from the Command Line

HBase provides the means to manage user access to HBase database tables directly from the command line. The most commonly-used commands are:

- GRANT

Syntax: `grant '<user-or-group>' , '<permissions>' , '<table>`

For example, to create a policy that grants user1 read/write permission on the table usertable, the command is `grant 'user1' , 'RW' , 'usertable'`

The syntax is the same for granting CREATE and ADMIN rights.

- REVOKE

Syntax: `revoke '<user-or-group>','<usertable>'`

For example, to revoke the read/write access of user1 to the table usertable, the command is `revoke 'user1' , 'usertable'`



Note

Unlike Hive, HBase has no specific revoke commands for each user privilege.

3.2.4.3. Create an HDFS Policy


Through configuration, Apache Ranger enables both Ranger policies and HDFS permissions to be checked for a user request. When the NameNode receives a user request, the Ranger

plugin checks for policies set through the Ranger Service Manager. If there are no policies, the Ranger plugin checks for permissions set in HDFS.


We recommend that permissions be created at the Ranger Service Manager, and to have restrictive permissions at the HDFS level.

To add a new policy to an existing HDFS service:

1. On the Service Manager page, select an existing service under HDFS.




The List of Policies page appears.



2. Click **Add New Policy**.



The Create Policy page appears.



3. Complete the Create Policy page as follows:

Table 3.39. Policy Details

Field	Description
Policy Name	Enter a unique name for this policy. The name cannot be duplicated anywhere in the system.
Resource Path	Define the resource path for the policy folder/file. To avoid the need to supply the full path OR to enable the policy for all subfolders or files, you can either complete this path using wildcards (for example, /home*) or specify that the policy should be recursive. (See below.)
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 3.40. User and Group Permissions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.

Label	Description
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- * indicates zero or more occurrences of characters
- ? indicates a single character


4. Click **Add**.




3.2.4.4. Create a Hive Policy

To add a new policy to an existing Hive service:

1. On the Service Manager page, select an existing service under Hive.




The List of Policies page appears.



2. Click **Add New Policy**.



The Create Policy console appears.



3. Complete the Create Policy page as follows:

Table 3.41. Policy Details

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Hive Database	Select the appropriate database. Multiple databases can be selected for a particular policy. This field is mandatory.
Table/UDF Drop-down	To continue adding a table-based policy, keep Table selected. To add a User Defined Function (UDF), select UDF.
Hive Column	For the selected database, select table(s) for which the policy will be applicable.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 3.42. User and Group Permissions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).

Label	Description
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- * indicates zero or more occurrences of characters
- ? indicates a single character

4. Click **Add**.



Note

The Ranger Hive plugin only protects HiveServer2; Hive CLI is not supported by Ranger.

3.2.4.5. Provide User Access to Hive Database Tables from the Command Line

Hive provides the means to manage user access to Hive database tables directly from the command line. The most commonly-used commands are:

- GRANT

Syntax: `grant <permissions> on table <table> to user <user or group>;`

For example, to create a policy that grants user1 SELECT permission on the table default-hivesmoke22074, the command is `grant select on table default.hivesmoke22074 to user user1;`

The syntax is the same for granting UPDATE, CREATE, DROP, ALTER, INDEX, LOCK, ALL and ADMIN rights.

- REVOKE

Syntax: `revoke <permissions> on table <table> from user <user or group>;`


For example, to revoke the SELECT rights of user1 to the table default.hivesmoke22074, the command is `revoke select on table default.hivesmoke22074 from user user1;`

The syntax is the same for revoking UPDATE, CREATE, DROP, ALTER, INDEX, LOCK, ALL and ADMIN rights.


3.2.4.6. Create a Kafka Policy

To add a new policy to an existing Kafka service:

1. On the Service Manager page, select an existing service under Kafka.




The List of Policies page appears.



2. Click **Add New Policy**.



The Create Policy console appears.



3. Complete the Create Policy page as follows:

Table 3.43. Policy Details

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Topic	A topic is a category or feed name to which messages are published.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 3.44. User and Group Permissions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Policy Conditions	Specify IP address range,
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- * indicates zero or more occurrences of characters
- ? indicates a single character


4. Click **Add**.




3.2.4.7. Create a Knox Policy

To add a new policy to an existing Knox service:

1. On the Service Manager page, select an existing service under Knox.




The List of Policies page appears.



2. Click **Add New Policy**.



The Create Policy console appears.



3. Complete the Create Policy page as follows:

Table 3.45. Policy Details

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Knox Topology	Enter an appropriate Topology Name.

Field	Description
Knox Service	Enter an appropriate Service Name.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 3.46. User and Group Permissions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Policy Conditions	Specify IP address range,
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Since Knox does not provide a command line methodology for assigning privileges or roles to users, the User and Group Permissions portion of the Knox Create Policy form is especially important.

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- * indicates zero or more occurrences of characters
- ? indicates a single character


4. Click **Add**.




3.2.4.8. Create a Solr Policy

To add a new policy to an existing Solr service:

1. On the Service Manager page, select an existing service under Solr.




The List of Policies page appears.



2. Click **Add New Policy**.



The Create Policy console appears.



3. Complete the Create Policy page as follows:

Table 3.47. Policy Details

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Solr Collection	<code>http:host_ip:6083/solr</code>
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 3.48. User and Group Permissions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen

Label	Description
	resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Policy Conditions	Specify IP address range,
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- * indicates zero or more occurrences of characters
- ? indicates a single character


4. Click **Add**.




3.2.4.9. Create a Storm Policy

To add a new policy to an existing Storm service:

1. On the Service Manager page, select an existing service under Storm.




The List of Policies page appears.



2. Click **Add New Policy**.



The Create Policy console appears.



3. Complete the Create Policy page as follows:

Table 3.49. Policy Details

Label	Description
Policy Name	Enter an appropriate policy name. This name is cannot be duplicated across the system. This field is mandatory.
Storm Topology	Enter an appropriate Topology Name.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 3.50. User and Group Permissions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Since Storm does not provide a command line methodology for assigning privileges or roles to users, the User and Group Permissions portion of the Storm Create Policy form is especially important.

Table 3.51. Knox User and Group Permissions

Actions	Description
File upload	Allows a user to upload files.
Get Nimbus Conf	Allows a user to access Nimbus configurations.
Get Cluster Info	Allows a user to get cluster information.
File Download	Allows a user to download files.
Kill Topology	Allows a user to kill the topology.
Rebalance	Allows a user to rebalance topologies.
Activate	Allows a user to activate a topology.
Deactivate	Allows a user to deactivate a topology.
Get Topology Conf	Allows a user to access a topology configuration.
Get Topology	Allows a user to access a topology.
Get User Topology	Allows a user to access a user topology.
Get Topology Info	Allows a user to access topology information.
Upload New Credential	Allows a user to upload a new credential.
Admin	Provides a user with delegated admin access.

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- * indicates zero or more occurrences of characters
- ? indicates a single character


4. Click **Add**.




3.2.4.10. Create a YARN Policy

To add a new policy to an existing YARN service:

1. On the Service Manager page, select an existing service under YARN.




The List of Policies page appears.



2. Click **Add New Policy**.



The Create Policy console appears.



3. Complete the Create Policy page as follows:

Table 3.52. Policy Details

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Queue	The fundamental unit of scheduling in yarn.
Recursive	You can indicate whether all files or folders within the existing folder comes under the policy. Can be used instead of wildcard characters.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

Table 3.53. User and Group Permissions

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:


- * indicates zero or more occurrences of characters
- ? indicates a single character

4. Click **Add**.




3.2.5. Users/Groups and Permissions Administration

To examine the list of users and groups who can access the Ranger portal or its services, click **Settings>Users/Groups** at the top of the Ranger Console.



The User/sGroup view displays:


- Internal users who can log in to the Ranger portal; created by the Ranger console Service Manager
- External users who can access services controlled by the Ranger portal; created at other systems like Active Directory, LDAP or UNIX, and synced with those systems
- Admins who are the only users with permission to create users and create services, run reports, and perform other administrative tasks. Admins can also create child policies based on the original policy (base policy).




3.2.5.1. Add a User

To add a new user to the user list:

1. Click **Settings>Users/Groups**.




The Users/Groups page appears.



2. Click **Add New User**.



The Ranger User Detail page appears.



The screenshot shows the Ranger web interface. At the top, there is a green navigation bar with the 'Ranger' logo and menu items: 'Access Manager', 'Audit', and 'Settings'. A user profile icon labeled 'admin' is in the top right. Below the navigation bar, there are two breadcrumb-style tabs: 'Users/Groups' and 'User Create'. The main content area is titled 'User Detail' and contains a form with the following fields:

- User Name * (text input)
- New Password * (text input)
- Password Confirm * (text input)
- First Name * (text input)
- Last Name (text input)
- Email Address (text input)
- Select Role * (dropdown menu with 'Admin' selected)
- Group (text 'Please select' with a '+' icon to its right)

At the bottom of the form, there are two buttons: a green 'Save' button and a black 'Cancel' button.

3. Add the appropriate user details, then click **Save**.




The user is immediately added to the list.


3.2.5.2. Edit a User

To edit a user:


1. Click **Settings>Users/Groups**.



The Users/Groups page opens to the Users tab.



2. Choose to edit yourself or another user:



- To edit another user: in the User Name column, select the user you wish to edit.

The User Detail page appears.




Note

You can only fully edit internal users. For external users, you can only edit the user role.


You can change everything except the User Name when editing an internal user.

You can only change the user role when editing an external user.

- To edit your user profile, click *Username*>**Profile**.



The User Profile page appears.




3. Edit the appropriate details and click **Save**.




3.2.5.3. Add a Group

To add a group:


1. Click **Settings>Users/Groups**.




The Users/Groups page opens to the Users tab.



2. Click the **Groups** sub-tab.




The Groups page appears.



3. Click **Add New Group**



The Group Create page appears.




4. Enter a unique name for the group, and an optional description, then click **Save**.




3.2.5.4. Edit a Group

To edit a group:


1. Click **Settings>Users/Groups**.




The Users/Groups page opens to the Users tab.




2. Click the **Groups** sub-tab.



The Groups page appears.




3. Select the group name you wish to edit.



The screenshot shows the Ranger interface with the 'Users/Groups' section selected. The 'Groups' tab is active, displaying a 'Group List' table. The table has columns for Group Name, Group Source, and Visibility. The 'public' group is highlighted with a red box. The table also includes a search bar, a 'Set Visibility' dropdown, and an 'Add New Group' button.

<input type="checkbox"/>	Group Name	Group Source	Visibility
<input type="checkbox"/>	public	Internal	Visible
<input type="checkbox"/>	group01	Internal	Visible
<input type="checkbox"/>	group02	Internal	Visible
<input type="checkbox"/>	group03	Internal	Visible

4. The Group Edit page appears.



The screenshot shows the 'Group Edit' page in the Ranger interface. The 'Group Detail' section contains a 'Group Name' field with the value 'public' and a 'Description' field with the value 'public group'. Below the fields are 'Save' and 'Cancel' buttons.


5. Edit the appropriate details, then click **Save**.



3.2.5.5. Add or Edit Permissions

To add or edit user or group:

1. Click **Settings>Permissions**.



The Users/Groups page opens to the Permissions page.

Permissions	Groups	Users	Action
Resource Based Policies		admin rangensersync keyadmin hive + More...	
Users/Groups		admin rangensersync amb ranger admin	
Reports		admin rangensersync keyadmin hive + More...	
Audit		admin rangensersync amb ranger admin	
Key Manager		keyadmin	

2. Click



beside the permission you wish to edit.

The Edit Permission page appears.

Policy Details:

Module Name *

User and Group Permissions:

Permissions	Select Group	Select User	Allow Access
	<input type="text" value="Select Group"/>	<input type="text" value="keyadmin"/> <input type="text" value="hive"/> <input type="text" value="kms"/> <input type="text" value="ambari-qa"/> <input type="text" value="hdfs"/> <input type="text" value="knox"/> <input type="text" value="ranger"/>	<input type="text" value="all"/>

3. Edit the necessary fields and click **Save**.




You can select multiple users and groups from the dropdown menus.

3.2.6. Reports Administration


The Reports module is used to manage the policies more efficiently as the number of policies grow. The page lists all HDFS, HBase, Hive, YARN, Knox, Storm, Solr, and Kafka policies.

You can edit policies from the Reports module by selecting the Policy ID.



3.2.6.1. View Reports

To view reports on one or more policies, click **Access Manager>Reports**.



The screenshot shows the Ranger User Access Report interface. At the top, there is a navigation bar with 'Ranger', 'Access Manager', 'Audit', and 'Settings' menus, and a user profile for 'admin'. Below this is a 'User Access Report' header and a 'Reports' section. The 'Search Criteria' section includes input fields for 'Policy Name' and 'Resource', a 'Search By' dropdown set to 'Group', and a 'Select Group' dropdown. A green 'Search' button is located below these fields. The 'HDFS' section contains a table with the following data:

Policy ID	Policy Name	Status	Audit Logging	Groups	Users
1	test-hdfs-1-20160202213734	Enabled	Enabled		admin
4	c6401_TEST_hadoop-1-201602022306...	Enabled	Enabled		

The 'HBASE' section contains a table with the following data:

Policy ID	Policy Name	Status	Audit Logging	Groups	Users
2	hbase-test-1-20160202224128	Enabled	Enabled		admin
3	c6401_TEST_hbase-1-20160202225955	Enabled	Enabled		

3.2.6.2. Search Reports

You can search:

- **Policy Name** - The policy name assigned to the policy while creating it.
- **Resource** - The resource path used while creating the policy.
- **Group, Username** - The group and the users to which the policy is assigned.

The screenshot shows the Ranger User Access Report interface. At the top, there is a green navigation bar with 'Ranger', 'Access Manager', 'Audit', and 'Settings' menus, and a user profile for 'admin'. Below this is a 'User Access Report' header and a 'Reports' section. The 'Search Criteria' section contains input fields for 'Policy Name' and 'Resource', a 'Search By' dropdown set to 'Group', and a 'Select Group' dropdown. A green 'Search' button is below these fields. The 'HDFS' section contains a table with the following data:

Policy ID	Policy Name	Status	Audit Logging	Groups	Users
1	test-hdfs-1-20160202213734	Enabled	Enabled		admin
4	c6401_TEST_hadoop-1-201602022306...	Enabled	Enabled		

The 'HBASE' section contains a table with the following data:

Policy ID	Policy Name	Status	Audit Logging	Groups	Users
2	hbase-test-1-20160202224128	Enabled	Enabled		admin
3	c6401_TEST_hbase-1-20160202225955	Enabled	Enabled		

3.2.7. Special Requirements for High Availability Environments

Special Requirements for High Availability Environments In a HA environment, primary and secondary NameNodes must be configured as described in the HDP System Administration Guide.

To enable Ranger in the HDFS HA environment, the HDFS plugin must be set up in each NameNode, and then pointed to the same HDFS service set up in the Security Manager. Any policies created within that HDFS service are automatically synchronized to the primary and secondary NameNodes through the installed Apache Ranger plugin. That way, if the primary NameNode fails, the secondary namenode takes over and the Ranger plugin at that NameNode begins to enforce the same policies for access control.

When creating the service, you must include the `fs.default.name` property must be set to the full hostname of the primary NameNode. If the primary NameNode fails during policy creation, you can then temporarily use the `fs.default.name` of the secondary NameNode in the service details to enable directory lookup for policy creation.

If, while the primary node is down, you wish to create new policies, there is a slight difference in user experience when specifying the resource path. If everything is normal, this is a drop-down menu with selectable paths; however, if your cluster is running from the failover node, there will be no drop-down menu, and you will need to manually enter the path.

Primary NameNode failure does not affect the actual policy enforcement. In this setup for HA, access control is enforced during primary NameNode failure, by the Ranger plugs at the secondary NameNodes.

For **Test Connection** to be successful for HBase and HDFS in a Ranger HA environment, complete the following: In `/etc/ranger/admin`, create a symbolic link between `hbase-site.xml` and `hdfs-site.xml`:

```
cd /etc/ranger/admin
ln -s /etc/hadoop/conf/hdfs-site.xml hdfs-site.xml
ln -s /etc/hbase/conf/hbase-site.xml hbase-site.xml
```

3.2.8. Adding a New Component to Apache Ranger

This document provides a general description of how to add a new component to Apache Ranger.

Apache Ranger has three main components:

- **Admin Tool** – Provides web interface & REST API for managing security policies
- **Custom Authorization Module for components** – Provides custom authorization within the (Hadoop) component to enforce the policies defined in Admin Tool
- **UserGroup synchronizer** – Enables the user/group information in Apache Ranger to synchronize with the Enterprise user/group information stored in LDAP or Active directory.

For supporting new component authorization using Apache Ranger, the component details needs to be added to Apache Ranger as follows:

- Add component details to the Admin Tool
- Develop a custom authorization module for the new component

Adding Component Details to the Admin Tool

The Apache Ranger Admin tool supports policy management via both a web interface (UI) and support for (public) REST API. In order to support a new component in both the UI and the Server, the Admin Tool needs to be modified.

Required UI changes to support the new component:

1. Add a new component template to the Access Manager page (console home page):

Show new component on the Access Manager page i.e home page[#!/policymanager]. Apache Ranger needs to add table template to Service Manager page and make changes in corresponding JS files. Ranger also needs to create a new service type enum to distinguish the component for which the service/policy is created/updated.

For example: Add a table template to PolicyManagerLayout_tmpl.html file to view the new component on the Access Manager page and make changes in the PolicyManagerLayout.js file related to the new componen, such as passing Knox service collection data to the PolicyManagerLayout_tmpl template. Also create a new service type enum (for example, ASSET_KNOX) in the XAEnums.js file.

2. Add new configuration information to the Service Form:

Add new configuration fields to Service Form [AssetForm.js] as per new component configuration information. This will cause the display of new configuration fields in the corresponding service Create/Update page. Please note that the AssetForm.js is a common file for every component to create/update the service.

For example: Add new field(configuration) information to AssetForm.js and AssetForm_tmpl.js.

3. Add a new Policy Listing page:

Add a new policy listing page for the new component in the View Policy list. For example: Create a new KnoxTableLayout.js file and add JS-related changes as per the old component[HiveTableLayout.js] to the View Policy listing. Also create a template page, KnoxTableLayout_tmpl.html.

4. Add a new Policy Create/Update page:

Add a Policy Create/Update page for the new component. Also add a policy form JS file and its template to handle all policy form-related actions for the new component. For example: Create a new KnoxPolicyCreate.js file for Create/Update Knox Policy. Create a KnoxPolicyForm.js file to add Knox policy fields information. Also create a corresponding KnoxPolicyForm_tmpl.html template.

5. Other file changes, as needed:

Make changes in existing common files as per our new component like Router.js, Controller.js, XAUtils.js, FormInputList.js, UserPermissionList.js, XAEnums.js, etc.

Required server changes for the new component:

Let's assume that Apache Ranger has three components supported in their portal and we want to introduce one new component, Knox:

1. Create New Service Type

If Apache Ranger is introducing new component i.e Knox, then they will add one new service type for Knox. i.e serviceType = "Knox". On the basis of service type, while creating/updating service/policy, Apache Ranger will distinguish for which component this service/policy is created/updated.

2. Add new required parameters in existig objects and populate objects

For Policy Creation/Update of any component (i.e HDFS, Hive, Hbase), Apache Ranger uses only one common object, `VXPolicy`. The same goes for the Service Creation/Update of any component: Apache Ranger uses only one common object `VXService`. As Apache Ranger has three components, it will have all the required parameters of all of those three components in `VXPolicy/VXService`. But for Knox, Apache Ranger requires some different parameters which are not there in previous components. Thus, it will add only required parameters into `VXPolicy/VXService` object. When a user sends a request to the Knox create/update policy, they will only send the parameters that are required for Knox to create/update the VXPolicy object.

After adding new parameters into VXPolixy/VXService, Apache Ranger populates the newly-added parameters in corresponding services, so that it can map those objects with Entity Object.

3. Add newly-added fields (into database table) related parameters into entity object and populate them

As Apache Ranger is using JPA-EclipseLink for database mapping into java, it is necessary to update the Entity object. For example, if for Knox policy Apache Ranger has added two new fields (`topology` and `service`) into db table `x_resource`, it will also have to update the entity object of table (i.e `XXResource`), since it is altering table structure.

After updating the entity object Apache Ranger will populate newly-added parameters in corresponding services (i.e XResourceService), so that it can communicate with the client using the updated entity object.

4. Change middleware code business logic

After adding and populating newly required parameters for new component, Apache Ranger will have to write business logic into file `AssetMgr`, where it may also need to do some minor changes. For example, if it wants to create a default policy while creating the Service, then on the basis of serviceType, Apache Ranger will create one default policy for the given service. Everything else will work fine, as it is common for all components.

Required database changes for the new component:

For service and policy management, Apache Ranger includes the following tables:

- x_asset (for service)
- x_resource (for service)

As written above, if Apache Ranger is introducing new component then it is not required to create individual table in database for each component. Apache Ranger has common tables for all components.

If Apache Ranger has three components and wants to introduce a fourth one, then it will add required fields into these two tables and will map accordingly with java object. For example, for Knox, Apache Ranger will add two fields (`topology`, `service`) into `x_resource`. After this, it will be able to perform CRUD operation of policy and service for our new component, and also for previous components.

3.2.9. Developing a Custom Authorization Module

In the Hadoop ecosystem, each component (i.e., Hive, HBase) has its own authorization implementation and ability to plug in a custom authorization module. To implement the centralized authorization and audit feature for a component, the component should support a customizable (or pluggable) authorization module.

The custom component Authorization Plugin should do the following:

- Provide authorization based on Policies defined in Policy Admin Tool
- Provide audit information based on the authorization decisions

Implementing Custom Component Authorization

To implement the custom component authorization plugin, the Ranger common agent framework provides the following functionalities:

- Ability to read all policies from Service Manager for a given service-id
- Ability to log audit information

When the custom authorization module is initialized, the module should do the following:

1. Initiate a REST API call to the "Policy Admin Tool" to retrieve all policies associated with the specific component.
2. Once the policies are available, it should:
 - be built into a custom data structure for enabling the authorization module.
 - kick off the policy updater thread to refresh policies from "Policy Admin Tool" at a regular interval.

When the custom authorization module is called to perform authorization of a component action (such as READ action) on a specific component resource (such as /app folder), the authorization module will:

- **Identify authorization decision** - For each policy:policyList:
 - If (resource in policy <match> auth-requested-resource)
 - If (action-in-policy <match>action-requested)
 - If (current-user or current-user-groups or public-group <allowed> for the policy), Return access-allowed
- **Identify auditing needs** - For each policy:policyList
 - If (resource in policy <match> auth-requested-resource), return policy.isAuditEnabled()

3.2.10. Apache Ranger Public REST API

- [Service Definition APIs \[254\]](#)

- [Get Service Definition by ID \[255\]](#)
- [Get Service Definition by Name \[258\]](#)
- [Create Service Definition \[261\]](#)
- [Update Service Definition by ID \[264\]](#)
- [Update Service Definition by Name \[268\]](#)
- [Delete Service Definition by ID \[268\]](#)
- [Delete Service Definition by Name \[268\]](#)
- [Search Service Definitions \[268\]](#)
- [Service APIs \[270\]](#)
 - [Get Service by ID \[270\]](#)
 - [Get Service by Name \[270\]](#)
 - [Create Service \[271\]](#)
 - [Update Service by ID \[271\]](#)
 - [Update Service by Name \[272\]](#)
 - [Delete Service by ID \[272\]](#)
 - [Delete Service by Name \[272\]](#)
 - [Search Services \[273\]](#)
- [Policy APIs \[275\]](#)
 - [Get Policy by ID \[275\]](#)
 - [Get Policy by Service Name and Policy Name \[276\]](#)
 - [Create Policy \[277\]](#)
 - [Update Policy by ID \[279\]](#)
 - [Update Policy by Service Name and Policy Name \[281\]](#)
 - [Delete Policy by ID \[284\]](#)
 - [Delete Policy by Service Name and Policy Name \[284\]](#)
 - [Search Policies in a Service \[284\]](#)

3.2.10.1. Service Definition APIs

- [Get Service Definition by ID \[255\]](#)

- [Get Service Definition by Name \[258\]](#)
- [Create Service Definition \[261\]](#)
- [Update Service Definition by ID \[264\]](#)
- [Update Service Definition by Name \[268\]](#)
- [Delete Service Definition by ID \[268\]](#)
- [Delete Service Definition by Name \[268\]](#)
- [Search Service Definitions \[268\]](#)

3.2.10.1.1. Get Service Definition by ID

API Name	Get Service Definition
Request Type	GET
Request URL	service/public/v2/api/servicedef/{id}
Request Params	
Response	<pre>{ "accessTypes": [{ "impliedGrants": [], "itemId": 1, "label": "Read", "name": "read" }, { "impliedGrants": [], "itemId": 2, "label": "Write", "name": "write" }, { "impliedGrants": [], "itemId": 3, "label": "Execute", "name": "execute" }], "configs": [{ "itemId": 1, "label": "Username", "mandatory": true, "name": "username", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 2, "label": "Password", "mandatory": true, "name": "password", "subType": "", "type": "password", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 3, "label": "Namenode URL", "mandatory": true, "name": "fs.default.name", "subType": "", "type": "string", </pre>

API Name	Get Service Definition
	<pre> "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "defaultValue": "false", "itemId": 4, "label": "Authorization Enabled", "mandatory": true, "name": "hadoop.security.authorization", "subType": "YesTrue:NoFalse", "type": "bool", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "defaultValue": "simple", "itemId": 5, "label": "Authentication Type", "mandatory": true, "name": "hadoop.security.authentication", "subType": "authnType", "type": "enum", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 6, "mandatory": false, "name": "hadoop.security.auth_to_local", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 7, "mandatory": false, "name": "dfs.datanode.kerberos.principal", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 8, "mandatory": false, "name": "dfs.namenode.kerberos.principal", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 9, "mandatory": false, "name": "dfs.secondary.namenode.kerberos.principal", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "defaultValue": "authentication", "itemId": 10, </pre>

API Name	Get Service Definition
	<pre> "label": "RPC Protection Type", "mandatory": false, "name": "hadoop.rpc.protection", "subType": "rpcProtection", "type": "enum", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 11, "label": "Common Name for Certificate", "mandatory": false, "name": "commonNameForCertificate", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "contextEnrichers": [], "createTime": 1450756476000, "description": "HDFS Repository", "enums": [{ "defaultIndex": 0, "elements": [{ "itemId": 1, "label": "Simple", "name": "simple" }, { "itemId": 2, "label": "Kerberos", "name": "kerberos" }] }, { "itemId": 1, "name": "authnType" }, { "defaultIndex": 0, "elements": [{ "itemId": 1, "label": "Authentication", "name": "authentication" }, { "itemId": 2, "label": "Integrity", "name": "integrity" }, { "itemId": 3, "label": "Privacy", "name": "privacy" }] }, { "itemId": 2, "name": "rpcProtection" }] }, "guid": "0d047247-bafe-4cf8-8e9b- d5d377284b2d", "id": 1, "implClass": "org.apache.ranger.services.hdfs. RangerServiceHdfs", "isEnabled": true, "label": "HDFS Repository", "name": "hdfs", "options": {}, "policyConditions": [], "resources": [</pre>

API Name	Get Service Definition
	<pre> { "description": "HDFS file or directory path", "excludesSupported": false, "itemId": 1, "label": "Resource Path", "level": 10, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerPathResourceMatcher", "matcherOptions": { "ignoreCase": "false", "wildCard": "true" }, "name": "path", "recursiveSupported": true, "type": "path", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "updateTime": 1450756477000, "version": 1 } </pre>

3.2.10.1.2. Get Service Definition by Name

API Name	Get Service Definition
Request Type	GET
Request URL	service/public/v2/api/servicedef/name/{name}
Request Params	
Response	<pre> { "accessTypes": [{ "impliedGrants": [], "itemId": 1, "label": "select", "name": "select" }, { "impliedGrants": [], "itemId": 2, "label": "update", "name": "update" }, { "impliedGrants": [], "itemId": 3, "label": "Create", "name": "create" }, { "impliedGrants": [], "itemId": 4, "label": "Drop", "name": "drop" }, { "impliedGrants": [], "itemId": 5, "label": "Alter", "name": "alter" }, { "impliedGrants": [], "itemId": 6, "label": "Index", "name": "index" }, { "impliedGrants": [], </pre>

API Name	Get Service Definition
	<pre> "itemId": 7, "label": "Lock", "name": "lock" }, { "impliedGrants": ["select", "update", "create", "drop", "alter", "index", "lock"], "itemId": 8, "label": "All", "name": "all" }], "configs": [{ "itemId": 1, "label": "Username", "mandatory": true, "name": "username", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 2, "label": "Password", "mandatory": true, "name": "password", "type": "password", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "defaultValue": "org.apache.hive.jdbc. HiveDriver", "itemId": 3, "mandatory": true, "name": "jdbc.driverClassName", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "defaultValue": "", "itemId": 4, "mandatory": true, "name": "jdbc.url", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 5, "label": "Common Name for Certificate", "mandatory": false, "name": "commonNameForCertificate", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" } }], "contextEnrichers": [], "createTime": 1450756479000, "description": "Hive Server2", "enums": [], </pre>

API Name	Get Service Definition
	<pre> "guid": "3e1afb5a-184a-4e82-9d9c-87a5cacc243c", "id": 3, "implClass": "org.apache.ranger.services.hive. RangerServiceHive", "isEnabled": true, "label": "Hive Server2", "name": "hive", "options": {}, "policyConditions": [{ "description": "List of Hive resources", "evaluator": "org.apache. ranger.plugin.conditionevaluator. RangerHiveResourcesAccessedTogetherCondition", "evaluatorOptions": {}, "itemId": 1, "label": "Hive Resources Accessed Together?", "name": "resources-accessed-together" }], "resources": [{ "description": "Hive Database", "excludesSupported": true, "itemId": 1, "label": "Hive Database", "level": 10, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "database", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "description": "Hive Table", "excludesSupported": true, "itemId": 2, "label": "Hive Table", "level": 20, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "table", "parent": "database", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "description": "Hive UDF", "excludesSupported": true, "itemId": 3, "label": "Hive UDF", "level": 20, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", </pre>

API Name	Get Service Definition
	<pre> "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "udf", "parent": "database", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "description": "Hive Column", "excludesSupported": true, "itemId": 4, "label": "Hive Column", "level": 30, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "column", "parent": "table", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "updateTime": 1450756479000, "version": 1 } </pre>

3.2.10.1.3. Create Service Definition

API Name	Create Service Definition
Request Type	Post
Request URL	service/public/v2/api/servicedef
Request Params	<pre> { "accessTypes": [{ "impliedGrants": [], "itemId": 1, "label": "select", "name": "select" }, { "impliedGrants": [], "itemId": 2, "label": "update", "name": "update" }, { "impliedGrants": [], "itemId": 3, "label": "Create", "name": "create" }, { "impliedGrants": [], "itemId": 4, "label": "Drop", "name": "drop" }], { "impliedGrants": ["select", "update",] } } </pre>

API Name	Create Service Definition
	<pre> "create", "drop"], "itemId": 5, "label": "All", "name": "all" }], "configs": [{ "itemId": 1, "label": "Username", "mandatory": true, "name": "username", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 2, "label": "Password", "mandatory": true, "name": "password", "type": "password", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "contextEnrichers": [], "description": "Test Component", "enums": [], "implClass": "org.apache.ranger.services.test. RangerServiceTest", "isEnabled": true, "label": "Test Component", "name": "test", "options": {}, "policyConditions": [], "resources": [{ "description": "Root Of Resource Hierarchy for Test Component", "excludesSupported": true, "itemId": 1, "label": "Test Root Resource", "level": 10, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "description": "Sub Resource for Test Component", "excludesSupported": true, "itemId": 2, "label": "Test sub resource", "level": 20, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" } }] </pre>

API Name	Create Service Definition
	<pre> }, "name": "sub", "parent": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "version": 1 } </pre>
Response	<pre> { "accessTypes": [{ "impliedGrants": [], "itemId": 1, "label": "select", "name": "select" }, { "impliedGrants": [], "itemId": 2, "label": "update", "name": "update" }, { "impliedGrants": [], "itemId": 3, "label": "Create", "name": "create" }, { "impliedGrants": [], "itemId": 4, "label": "Drop", "name": "drop" }, { "impliedGrants": ["select", "update", "create", "drop"], "itemId": 5, "label": "All", "name": "all" }], "configs": [{ "itemId": 1, "label": "Username", "mandatory": true, "name": "username", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 2, "label": "Password", "mandatory": true, "name": "password", "type": "password", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "contextEnrichers": [], "createTime": 1451347300617, "createdBy": "Admin", "description": "Test Component", "enums": [], </pre>

API Name	Create Service Definition
	<pre> "guid": "f889f2d3-920a-4504-9905-809bbc417902", "id": 101, "implClass": "org.apache.ranger.services.test. RangerServiceTest", "isEnabled": true, "label": "Test Component", "name": "test", "options": {}, "policyConditions": [], "resources": [{ "description": "Root Of Resource Hierarchy for Test Component", "excludesSupported": true, "itemId": 1, "label": "Test Root Resource", "level": 10, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "description": "Sub Resource for Test Component", "excludesSupported": true, "itemId": 2, "label": "Test sub resource", "level": 20, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "sub", "parent": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": "" }], "updateTime": 1451347300618, "updatedBy": "Admin", "version": 1 } </pre>

3.2.10.1.4. Update Service Definition by ID

API Name	Update Service Definition
Request Type	PUT
Request URL	service/public/v2/api/servicedef/{id}
Request Params	<pre> { "accessTypes": [{ "impliedGrants": [], "itemId": 1, "label": "select", "name": "select" }] } </pre>

API Name	Update Service Definition
	<pre> }, { "impliedGrants": [], "itemId": 2, "label": "update", "name": "update" }, { "impliedGrants": [], "itemId": 3, "label": "Create", "name": "create" }, { "impliedGrants": [], "itemId": 4, "label": "Drop", "name": "drop" }, { "impliedGrants": [], "itemId": 5, "label": "Index", "name": "index" }, { "impliedGrants": ["select", "update", "create", "drop", "index"], "itemId": 6, "label": "All", "name": "all" }], "configs": [{ "itemId": 1, "label": "Username", "mandatory": true, "name": "username", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 2, "label": "Password", "mandatory": true, "name": "password", "type": "password", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "contextEnrichers": [], "description": "Test Component", "enums": [], "implClass": "org.apache.ranger.services.test. RangerServiceTest", "isEnabled": true, "label": "Test Component", "name": "test", "options": {}, "policyConditions": [], "resources": [{ "description": "Root Of Resource Hierarchy for Test Component", "excludesSupported": true, "itemId": 1, "label": "Test Root Resource", </pre>

API Name	Update Service Definition
	<pre> "level": 10, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "description": "Sub Resource for Test Component", "excludesSupported": true, "itemId": 2, "label": "Test sub resource", "level": 20, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "sub", "parent": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }] } </pre>
<p>Response</p>	<pre> { "accessTypes": [{ "impliedGrants": [], "itemId": 1, "label": "select", "name": "select" }, { "impliedGrants": [], "itemId": 2, "label": "update", "name": "update" }, { "impliedGrants": [], "itemId": 3, "label": "Create", "name": "create" }, { "impliedGrants": [], "itemId": 4, "label": "Drop", "name": "drop" }, { "impliedGrants": [], "itemId": 5, "label": "Index", "name": "index" }], { "impliedGrants": ["select", "update", </pre>

API Name	Update Service Definition
	<pre> "create", "drop", "index"], "itemId": 6, "label": "All", "name": "all" }], "configs": [{ "itemId": 1, "label": "Username", "mandatory": true, "name": "username", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "itemId": 2, "label": "Password", "mandatory": true, "name": "password", "type": "password", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "contextEnrichers": [], "createTime": 1451347301000, "createdBy": "Admin", "description": "Test Component", "enums": [], "guid": "f889f2d3-920a-4504-9905-809bbc417902", "id": 101, "implClass": "org.apache.ranger.services.test. RangerServiceTest", "isEnabled": true, "label": "Test Component", "name": "test", "options": {}, "policyConditions": [], "resources": [{ "description": "Root Of Resource Hierarchy for Test Component", "excludesSupported": true, "itemId": 1, "label": "Test Root Resource", "level": 10, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, { "description": "Sub Resource for Test Component", "excludesSupported": true, "itemId": 2, "label": "Test sub resource", "level": 20, "lookupSupported": true, </pre>

API Name	Update Service Definition
	<pre> "mandatory": true, "matcher": "org.apache.ranger.plugin. resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "sub", "parent": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "updateTime": 1451351474321, "updatedBy": "Admin", "version": 2 } </pre>

3.2.10.1.5. Update Service Definition by Name

API Name	Update Service Definition
Request Type	PUT
Request URL	service/public/v2/api/servicedef/{name}
Request Params	Application/json • Example:
Response	200-Application/json

3.2.10.1.6. Delete Service Definition by ID

API Name	Delete Service Definition
Request Type	DELETE
Request URL	service/public/v2/api/servicedef/{id}
Request Param	
Response	204-No Content

3.2.10.1.7. Delete Service Definition by Name

API Name	Delete Service Definition
Request Type	DELETE
Request URL	service/public/v2/api/servicedef/name/{name}
Request Param	
Response	204-No Content

3.2.10.1.8. Search Service Definitions

API Name	Search Service Definitions
Request Type	GET
Request URL	service/public/v2/api/servicedef
Request Params	Query Params pageSize int <i>The page size required</i> startIndex int <i>The startrecord index</i>

API Name	Search Service Definitions
	<p>serviceType string <i>The service definition names("hdfs","hive","hbase","knox","storm","solr","kafka","yarn")</i></p> <p>isEnabled boolean <i>The enabled status : true if enabled; false otherwise</i></p> <p>Example :</p> <p>pageSize=25&startIndex=0</p>
Response	<pre>[{ "accessTypes": [{ "impliedGrants": [], "itemId": 1, "label": "Read", "name": "read" }, { "impliedGrants": [], "itemId": 2, "label": "Write", "name": "write" }, { "impliedGrants": [], "itemId": 3, "label": "Execute", "name": "execute" }], "configs": [{ "itemId": 1, "label": "Username", "mandatory": true, "name": "username", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }, ... { "description": "Sub Resource for Test Component", "excludesSupported": true, "itemId": 2, "label": "Test sub resource", "level": 20, "lookupSupported": true, "mandatory": true, "matcher": "org. apache.ranger.plugin.resourcematcher. RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "sub", "parent": "root", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegex": "" }], "updateTime": 1451351474000, "updatedBy": "Admin", "version": 2 }]</pre>

3.2.10.2. Service APIs

- [Get Service by ID \[270\]](#)
- [Get Service by Name \[270\]](#)
- [Create Service \[271\]](#)
- [Update Service by ID \[271\]](#)
- [Update Service by Name \[272\]](#)
- [Delete Service by ID \[272\]](#)
- [Delete Service by Name \[272\]](#)
- [Search Services \[273\]](#)

3.2.10.2.1. Get Service by ID

API Name	Get Service
Request Type	GET
Request URL	service/public/v2/api/service/{id}
Request Params	
Response	<pre>{ "configs": { "fs.default.name": "hdfs://akulkarni-etp-real-final-1.novalocal:8020", "hadoop.security.auth_to_local": "DEFAULT", "hadoop.security.authentication": "simple", "hadoop.security.authorization": "false", "password": "*****", "username": "hadoop" }, "createTime": 1450757397000, "createdBy": "amb_ranger_admin", "description": "hdfs repo", "guid": "ec082eea-0c22-43b8-84e0-129422f689b9", "id": 1, "isEnabled": true, "name": "c11_hadoop", "policyUpdateTime": 1450757398000, "policyVersion": 2, "tagVersion": 1, "type": "hdfs", "updateTime": 1450757398000, "updatedBy": "amb_ranger_admin", "version": 3 }</pre>

3.2.10.2.2. Get Service by Name

API Name	Get Service
Request Type	GET
Request URL	service/public/v2/api/service/name/{name}
Request Params	
Response	{

API Name	Get Service
	<pre> "configs": { "jdbc.driverClassName": "org.apache.hive. jdbc.HiveDriver", "jdbc.url": "jdbc:hive2://akulkarni-etp- real-final-1.novalocal:10000", "password": "*****", "username": "hive" }, "createTime": 1450757992000, "createdBy": "amb_ranger_admin", "description": "hive repo", "guid": "2bca8f98-4859-43c3-a8f4- d31a15f28793", "id": 3, "isEnabled": true, "name": "cl1_hive", "policyUpdateTime": 1450757995000, "policyVersion": 4, "tagUpdateTime": 1450916660000, "tagVersion": 74, "type": "hive", "updateTime": 1450757995000, "updatedBy": "amb_ranger_admin", "version": 78 </pre>

3.2.10.2.3. Create Service

API Name	Create Service
Request Type	Post
Request URL	service/public/v2/api/service
Request Params	<pre> { "configs": { "password": "*****", "username": "hadoop" }, "description": "test service", "isEnabled": true, "name": "cl1_test", "type": "test", "version": 1 } </pre>
Response	<pre> { "configs": { "password": "*****", "username": "hadoop" }, "createTime": 1451348710255, "createdBy": "Admin", "description": "test service", "guid": "e72cb64d-66d7-4632-b5ae- c6966cb52105", "id": 6, "isEnabled": true, "name": "cl1_test", "tagVersion": 1, "type": "test", "updateTime": 1451348710256, "updatedBy": "Admin", "version": 1 } </pre>

3.2.10.2.4. Update Service by ID

API Name	Update Service
Request Type	PUT

API Name	Update Service
Request URL	service/public/v2/api/service/{id}
Request Params	Application/json • Example:
Response	200-Application/json

3.2.10.2.5. Update Service by Name

API Name	Update Service
Request Type	PUT
Request URL	service/public/v2/api/service/name/{name}
Request Params	<pre>{ "configs": { "password": "*****", "username": "admin" }, "description": "test service", "isEnabled": true, "name": "cl1_test", "type": "test" }</pre>
Response	<pre>{ "configs": { "password": "*****", "username": "admin" }, "createTime": 1451348710000, "createdBy": "Admin", "description": "test service", "guid": "e72cb64d-66d7-4632-b5ae-c6966cb52105", "id": 6, "isEnabled": true, "name": "cl1_test", "policyUpdateTime": 1451351474000, "policyVersion": 3, "tagVersion": 1, "type": "test", "updateTime": 1451352016713, "updatedBy": "Admin", "version": 5 }</pre>

3.2.10.2.6. Delete Service by ID

API Name	Delete Service
Request Type	DELETE
Request URL	service/public/v2/api/service/{id}
Request Param	
Response	204-No Content

3.2.10.2.7. Delete Service by Name

API Name	Delete Service
Request Type	DELETE
Request URL	service/public/v2/api/service/name/{name}
Request Param	
Response	204-No Content

3.2.10.2.8. Search Services

API Name	Search Services
Request Type	GET
Request URL	service/public/v2/api/service
Request Params	<p>Query Parameters:</p> <p>pageSize int <i>The page size required</i></p> <p>startIndex int <i>The startrecord index</i></p> <p>serviceName string <i>The service name</i></p> <p>serviceNamePartial string <i>Partial service name</i></p> <p>serviceType string <i>The service types(such as "hdfs","hive","hbase","knox","storm")</i></p> <p>isEnabled boolean <i>The enabled status (true/false): true is enabled, false otherwise</i></p> <p>Example :</p> <p>pageSize=25&startIndex=0</p>
Response	<pre>[{ "configs": { "fs.default.name": "hdfs://akulkarni- etp-real-final-1.novalocal:8020", "hadoop.security.auth_to_local": "DEFAULT", "hadoop.security.authentication": "simple", "hadoop.security.authorization": >false", "password": "*****", "username": "hadoop" }, "createTime": 1450757397000, "createdBy": "amb_ranger_admin", "description": "hdfs repo", "guid": "ec082eea-0c22-43b8-84e0-129422f689b9", "id": 1, "isEnabled": true, "name": "cll_hadoop", "policyUpdateTime": 1450757398000, "policyVersion": 2, "tagVersion": 1, "type": "hdfs", "updateTime": 1450757398000, "updatedBy": "amb_ranger_admin", "version": 3 }, { "configs": { "password": "*****", "username": "yarn", "yarn.url": "http://akulkarni-etp- real-final-1.novalocal:8088" }, "createTime": 1450757747000, "createdBy": "amb_ranger_admin", "description": "yarn repo", "guid": "080970a9-2216-4660-962e-2b48046bf87e", "id": 2, "isEnabled": true, "name": "cll_yarn", "policyUpdateTime": 1450757747000, "policyVersion": 1, "tagVersion": 1, "type": "yarn", "updateTime": 1450757747000, </pre>

API Name	Search Services
	<pre> "updatedBy": "amb_ranger_admin", "version": 2 }, { "configs": { "jdbc.driverClassName": "org.apache. hive.jdbc.HiveDriver", "jdbc.url": "jdbc:hive2://akulkarni- etp-real-final-1.novalocal:10000", "password": "*****", "username": "hive" }, "createTime": 1450757992000, "createdBy": "amb_ranger_admin", "description": "hive repo", "guid": "2bca8f98-4859-43c3-a8f4- d31a15f28793", "id": 3, "isEnabled": true, "name": "c11_hive", "policyUpdateTime": 1450757995000, "policyVersion": 4, "tagUpdateTime": 1450916660000, "tagVersion": 74, "type": "hive", "updateTime": 1450757995000, "updatedBy": "amb_ranger_admin", "version": 78 }, { "configs": { "hadoop.security.authentication": "simple", "hbase.security.authentication": "simple", "hbase.zookeeper.property.clientPort": "2181", "hbase.zookeeper.quorum": "akulkarni- etp-real-final-1.novalocal", "password": "*****", "username": "hbase", "zookeeper.znode.parent": "/hbase- unsecure" }, "createTime": 1450758200000, "createdBy": "amb_ranger_admin", "description": "hbase repo", "guid": "6495d4c9-cd1b-4bdf-a023- bdc82806186f", "id": 4, "isEnabled": true, "name": "c11_hbase", "policyUpdateTime": 1450758202000, "policyVersion": 2, "tagVersion": 1, "type": "hbase", "updateTime": 1450758202000, "updatedBy": "amb_ranger_admin", "version": 3 }, { "configs": { "password": "*****", "username": "kafka", "zookeeper.connect": "akulkarni-etp- real-final-1.novalocal:2181" }, "createTime": 1450758481000, "createdBy": "amb_ranger_admin", "description": "kafka repo", "guid": "bd25a697-7c45-4c75-b23d- bb02071c98c2", "id": 5, "isEnabled": true, "name": "c11_kafka", "policyUpdateTime": 1450805416000, "policyVersion": 2, </pre>

API Name	Search Services
	<pre> "tagVersion": 1, "type": "kafka", "updateTime": 1450805416000, "updatedBy": "amb_ranger_admin", "version": 3 }, { "configs": { "password": "*****", "username": "admin" }, "createTime": 1451348710000, "createdBy": "Admin", "description": "test service", "guid": "e72cb64d-66d7-4632-b5ae- c6966cb52105", "id": 6, "isEnabled": true, "name": "c11_test", "policyUpdateTime": 1451352708000, "policyVersion": 4, "tagVersion": 1, "type": "test", "updateTime": 1451352708000, "updatedBy": "Admin", "version": 6 }] </pre>

3.2.10.3. Policy APIs

- [Get Policy by ID \[275\]](#)
- [Get Policy by Service Name and Policy Name \[276\]](#)
- [Create Policy \[277\]](#)
- [Update Policy by ID \[279\]](#)
- [Update Policy by Service Name and Policy Name \[281\]](#)
- [Delete Policy by ID \[284\]](#)
- [Delete Policy by Service Name and Policy Name \[284\]](#)
- [Search Policies in a Service \[284\]](#)

3.2.10.3.1. Get Policy by ID

API Name	Get Policy
Request Type	Get
Request URL	<code>service/public/v2/api/policy/{id}</code>
Request Params	
Response	<pre> { "allowExceptions": [], "createTime": 1450757397000, "createdBy": "amb_ranger_admin", "denyExceptions": [], "denyPolicyItems": [], "description": "Default Policy for Service: c11_hadoop", "guid": "4c2f7afb-23fa-45e9-9b41-29bdc7423b65", "id": 1, "isAuditEnabled": true, "isEnabled": true, "name": "c11_hadoop-1-20151222040957", "policyItems": [</pre>

API Name	Get Policy
	<pre> { "accesses": [{ "isAllowed": true, "type": "read" }, { "isAllowed": true, "type": "write" }, { "isAllowed": true, "type": "execute" }], "conditions": [], "delegateAdmin": true, "groups": [], "users": ["ambari-qa"] }, "resourceSignature": "6f95606340leda656fleae8870clafac", "resources": { "path": { "isExcludes": false, "isRecursive": true, "values": ["/*"] } }, "service": "cli_hadoop", "updateTime": 1450757398000, "updatedBy": "amb_ranger_admin", "version": 2 } </pre>

3.2.10.3.2. Get Policy by Service Name and Policy Name

API Name	Get Policy
Request Type	Get
Request URL	service/public/v2/api/service/{service-name}/policy/{policy-name}
Request Params	
Response	<pre> { "allowExceptions": [], "createTime": 1450757992000, "createdBy": "amb_ranger_admin", "denyExceptions": [], "denyPolicyItems": [], "description": "Default Policy for Service: cli_hive", "guid": "d6218120-1b66-43e6-9fef-9c917a8e9e25", "id": 4, "isAuditEnabled": true, "isEnabled": true, "name": "cli_hive-2-20151222041952", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }] }] } </pre>

API Name	Get Policy
	<pre> { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }, { "isAllowed": true, "type": "alter" }, { "isAllowed": true, "type": "index" }, { "isAllowed": true, "type": "lock" }, { "isAllowed": true, "type": "all" }], "conditions": [], "delegateAdmin": true, "groups": [], "users": ["ambari-qa"] }], "resourceSignature": "c834ed2b8c7462d2aa8bbffdb05226c8", "resources": { "database": { "isExcludes": false, "isRecursive": false, "values": ["*"] }, "udf": { "isExcludes": false, "isRecursive": false, "values": ["*"] } }, "service": "cli_hive", "updateTime": 1450757995000, "updatedBy": "amb_ranger_admin", "version": 2 }] } </pre>

3.2.10.3.3. Create Policy

API name	Create Policy
Request Type	POST
Request URL	service/public/v2/api/policy
Request Params	<pre> { "allowExceptions": [], "denyExceptions": [], "denyPolicyItems": [{ "accesses": [{ "isAllowed": true, "type": "drop" }] }], } </pre>

API name	Create Policy
	<pre> "conditions": [], "delegateAdmin": true, "groups": [], "users": ["hadoop"] }], "description": "Policy for Service: cll_test", "isAuditEnabled": true, "isEnabled": true, "name": "c11_test-1", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }, { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": ["public"], "users": [] }] }, "resources": { "root": { "isExcludes": false, "isRecursive": false, "values": ["abc"] }, "sub": { "isExcludes": false, "isRecursive": false, "values": ["*"] } }, "service": "c11_test", "version": 1 } </pre>
<p>Response</p>	<pre> { "allowExceptions": [], "createTime": 1451350456093, "createdBy": "Admin", "denyExceptions": [], "denyPolicyItems": [{ "accesses": [{ "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": [], "users": ["hadoop"] }] } </pre>

API name	Create Policy
	<pre> }], "description": "Policy for Service: cll_test", "guid": "ff0b3c4a-6aa0-4803-9314-17f3b8950482", "id": 8, "isAuditEnabled": true, "isEnabled": true, "name": "c11_test-1", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }, { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": ["public"], "users": [] }], "resourceSignature": "8a2fac99ba72c687defacff39d6354fb", "resources": { "root": { "isExcludes": false, "isRecursive": false, "values": ["abc"] }, "sub": { "isExcludes": false, "isRecursive": false, "values": ["*"] } } }, "service": "c11_test", "updateTime": 1451350456094, "updatedBy": "Admin", "version": 1 } </pre>

3.2.10.3.4. Update Policy by ID

API Name	update policy
Request Type	PUT
Request URL	service/public/v2/api/policy/{id}
Request Params	<pre> { "id": 8, "allowExceptions": [], "denyExceptions": [], "denyPolicyItems": [{ "accesses": [</pre>

API Name	update policy
	<pre> { "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": [], "users": ["admin"] }], "description": "Policy for Service: cl1_test", "isAuditEnabled": true, "isEnabled": true, "name": "cl1_test-1", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }, { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": ["public"], "users": [] }], "resources": { "root": { "isExcludes": false, "isRecursive": false, "values": ["abc"] }, "sub": { "isExcludes": false, "isRecursive": false, "values": ["*"] } }, "service": "cl1_test", "version": 1 } </pre>
<p>Response</p>	<pre> { "allowExceptions": [], "createTime": 1451350456000, "createdBy": "Admin", "denyExceptions": [], "denyPolicyItems": [{ "accesses": [{ "isAllowed": true, "type": "drop" }], "conditions": [], </pre>

API Name	update policy
	<pre> "delegateAdmin": true, "groups": [], "users": ["admin"] }], "description": "Policy for Service: cll_test", "guid": "ff0b3c4a-6aa0-4803-9314-17f3b8950482", "id": 8, "isAuditEnabled": true, "isEnabled": true, "name": "c1l_test-1", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }, { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": ["public"], "users": [] }], "resourceSignature": "8a2fac99ba72c687defacff39d6354fb", "resources": { "root": { "isExcludes": false, "isRecursive": false, "values": ["abc"] }, "sub": { "isExcludes": false, "isRecursive": false, "values": ["*"] } }, "service": "c1l_test", "updateTime": 1451955041580, "updatedBy": "Admin", "version": 3 } </pre>

3.2.10.3.5. Update Policy by Service Name and Policy Name

API Name	update policy
Request Type	PUT
Request URL	service/public/v2/api/service/{service-name}/policy/{policy-name}
Request Params	{

API Name	update policy
	<pre> "allowExceptions": [], "denyExceptions": [], "denyPolicyItems": [{ "accesses": [{ "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": [], "users": ["hadoop", "admin"] }], "description": "Policy for Service: cll_test", "isAuditEnabled": true, "isEnabled": true, "name": "c11_test-1", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }, { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": ["public"], "users": [] }], "resources": { "root": { "isExcludes": false, "isRecursive": false, "values": ["abc"] }, "sub": { "isExcludes": false, "isRecursive": false, "values": ["*"] } }, "service": "c11_test", "version": 1 } </pre>
	200 - Application/json
Response	<pre> { "allowExceptions": [], "createTime": 1451350456000, "createdBy": "Admin", "denyExceptions": [], "denyPolicyItems": [</pre>

API Name	update policy
	<pre> { "accesses": [{ "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": [], "users": ["hadoop", "admin"] }], "description": "Policy for Service: cll_test", "guid": "ff0b3c4a-6aa0-4803-9314-17f3b8950482", "id": 8, "isAuditEnabled": true, "isEnabled": true, "name": "c11_test-1", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }, { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }], "conditions": [], "delegateAdmin": true, "groups": ["public"], "users": [] }], "resourceSignature": "8a2fac99ba72c687defacff39d6354fb", "resources": { "root": { "isExcludes": false, "isRecursive": false, "values": ["abc"] }, "sub": { "isExcludes": false, "isRecursive": false, "values": ["*"] } }, "service": "c11_test", "updateTime": 1451352707567, "updatedBy": "Admin", "version": 2 } </pre>

3.2.10.3.6. Delete Policy by ID

API Name	Delete Policy
Request Type	DELETE
Request URL	service/public/v2/api/policy/{id}
Request Params	
Response	204 - No Content

3.2.10.3.7. Delete Policy by Service Name and Policy Name

API Name	Delete Policy
Request Type	DELETE
Request URL	service/public/v2/api/policy
Request Params	<p><u>Query Parameters:</u></p> <p>servicename string The name of service</p> <p>polycyname string The name of policy</p> <p>Example:</p> <p>servicename=service-name&polycyname=policy-name</p>
Response	204 - No Content

3.2.10.3.8. Search Policies in a Service

API Name	Search Policies in a Service
API Name	Search Policies in a Service
Request Type	GET
Request URL	service/public/v2/api/service/{service-name}/policy
Request Params	<p><u>Query Parameters:</u></p> <p>pageSize int <i>The page size required</i></p> <p>startIndex int <i>The start record index</i></p> <p>policyName string <i>The Exact Name of the policy</i></p> <p>policyNamePartial string <i>The Partial Name of the policy</i></p> <p>policyId string <i>The policy ID</i></p> <p>polResource string <i>The policy resource value</i></p> <p>resource:resource-type string <i>The policy resource value for given resource-type</i></p> <p>user string <i>The user name</i></p> <p>group string <i>The group name</i></p> <p>isRecursive boolean <i>The isRecursive property ("true" or "false")</i></p> <p>isEnabled boolean <i>The enable/disabled property ("true" or "false")</i></p> <p>Example =</p> <p>pageSize=25&startIndex=0&resource:database=finance</p>
Response	[

API Name	Search Policies in a Service
API Name	Search Policies in a Service
	<pre> { "allowExceptions": [], "createTime": 1450757992000, "createdBy": "amb_ranger_admin", "denyExceptions": [], "denyPolicyItems": [], "description": "Default Policy for Service: cll_hive", "guid": "4a322a05-cl7f-4d6c- b291-94cae3e6c353", "id": 3, "isAuditEnabled": true, "isEnabled": true, "name": "c1l_hive-1-20151222041951", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }, { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }, { "isAllowed": true, "type": "alter" }, { "isAllowed": true, "type": "index" }, { "isAllowed": true, "type": "lock" }, { "isAllowed": true, "type": "all" }], "conditions": [], "delegateAdmin": true, "groups": [], "users": ["ambari-qa"] }], "resourceSignature": "6e79c1c989c79b7e53af663d3bdc2de6", "resources": { "column": { "isExcludes": false, "isRecursive": false, "values": ["*"] }, "database": { "isExcludes": false, "isRecursive": false, "values": ["*"] } } } </pre>

API Name	Search Policies in a Service
API Name	Search Policies in a Service
	<pre> "table": { "isExcludes": false, "isRecursive": false, "values": ["*"] }, "service": "c1l_hive", "updateTime": 1450757994000, "updatedBy": "amb_ranger_admin", "version": 2 }, { "allowExceptions": [], "createTime": 1450757992000, "createdBy": "amb_ranger_admin", "denyExceptions": [], "denyPolicyItems": [], "description": "Default Policy for Service: c1l_hive", "guid": "d6218120-1b66-43e6-9fef-9c917a8e9e25", "id": 4, "isAuditEnabled": true, "isEnabled": true, "name": "c1l_hive-2-20151222041952", "policyItems": [{ "accesses": [{ "isAllowed": true, "type": "select" }, { "isAllowed": true, "type": "update" }, { "isAllowed": true, "type": "create" }, { "isAllowed": true, "type": "drop" }, { "isAllowed": true, "type": "alter" }, { "isAllowed": true, "type": "index" }, { "isAllowed": true, "type": "lock" }, { "isAllowed": true, "type": "all" }], "conditions": [], "delegateAdmin": true, "groups": [], "users": ["ambari-ga"] }], "resourceSignature": "c834ed2b8c7462d2aa8bbffdb05226c8", "resources": { "database": { </pre>

API Name	Search Policies in a Service
API Name	<pre> "isExcludes": false, "isRecursive": false, "values": ["*"] }, "udf": { "isExcludes": false, "isRecursive": false, "values": ["*"] } }, "service": "cli_hive", "updateTime": 1450757995000, "updatedBy": "amb_ranger_admin", "version": 2 }] </pre>

4. Data Protection: Wire Encryption

Encryption is applied to electronic information to ensure its privacy and confidentiality. Wire encryption protects data as it moves into, through, and out of an Hadoop cluster over RPC, HTTP, Data Transfer Protocol (DTP), and JDBC:

- *Clients* typically communicate directly with the Hadoop cluster. Data can be protected using RPC encryption or Data Transfer Protocol:
 - **RPC encryption:** Clients interacting directly with the Hadoop cluster through RPC. A client uses RPC to connect to the NameNode (NN) to initiate file read and write operations. RPC connections in Hadoop use Java's Simple Authentication & Security Layer (SASL), which supports encryption.
 - **Data Transfer Protocol:** The NN gives the client the address of the first DataNode (DN) to read or write the block. The actual data transfer between the client and a DN uses Data Transfer Protocol.
- *Users* typically communicate with the Hadoop cluster using a Browser or a command line tools, data can be protected as follows:
 - **HTTPS encryption:** Users typically interact with Hadoop using a browser or component CLI, while applications use REST APIs or Thrift. Encryption over the HTTP protocol is implemented with the support for SSL across a Hadoop cluster and for the individual components such as Ambari.
 - **JDBC:** HiveServer2 implements encryption with Java SASL protocol's quality of protection (QOP) setting. With this the data moving between a HiveServer2 over JDBC and a JDBC client can be encrypted.
- Additionally, within-cluster communication between processes can be protected using HTTPS encryption during MapReduce shuffle:
 - **HTTPS encryption during shuffle:** When data moves between the Mappers and the Reducers over the HTTP protocol, this step is called shuffle. Reducer initiates the connection to the Mapper to ask for data; it acts as an SSL client.

This chapter provides information about configuring and connecting to wire-encrypted components.

For information about configuring HDFS data-at-rest encryption, see [HDFS "Data at Rest" Encryption](#).

4.1. Enabling RPC Encryption

The most common way for a client to interact with a Hadoop cluster is through RPC. A client connects to a NameNode over RPC protocol to read or write a file. RPC connections in Hadoop use the Java Simple Authentication and Security Layer (SASL) which supports encryption. When the `hadoop.rpc.protection` property is set to `privacy`, the data over RPC is encrypted with symmetric keys.

**Note**

RPC encryption covers not only the channel between a client and a Hadoop cluster but also the inter-cluster communication among Hadoop services.

Enable Encrypted RPC by setting the following properties in `core-site.xml`.

```
hadoop.rpc.protection=privacy
```

(Also supported are the 'authentication' and 'integrity' settings.)

4.2. Enabling Data Transfer Protocol

The NameNode gives the client the address of the first DataNode to read or write the block. The actual data transfer between the client and the DataNode is over Hadoop's Data Transfer Protocol. To encrypt this protocol you must set `dfs.encrypt.data.transfer=true` on the NameNode and all DataNodes. The actual algorithm used for encryption can be customized with `dfs.encrypt.data.transfer.algorithm` set to either "3des" or "rc4". If nothing is set, then the default on the system is used (usually 3DES.) While 3DES is more cryptographically secure, RC4 is substantially faster.

Enable Encrypted DTP by setting the following properties in `hdfs-site.xml`:

```
dfs.encrypt.data.transfer=true
dfs.encrypt.data.transfer.algorithm=3des
```

rc4 is also supported.

**Note**

Secondary NameNode is not supported with the HTTPS port. It can only be accessed via `http://<SNN>:50090`.

4.3. Enabling SSL: Understanding the Hadoop SSL Keystore Factory

The Hadoop SSL Keystore Factory manages SSL for core services that communicate with other cluster services over HTTP, such as MapReduce, YARN, and HDFS. Other components that have services that are typically not distributed, or only receive HTTP connections directly from clients, use built-in Java JDK SSL tools. Examples include HBase and Oozie.

The following table shows HDP cluster services that use HTTP and support SSL for wire encryption.

Table 4.1. Components that Support SSL

Component	Service	SSL Management
HDFS	WebHDFS	Hadoop SSL Keystore Factory
MapReduce	Shuffle	Hadoop SSL Keystore Factory
	TaskTracker	Hadoop SSL Keystore Factory
Yarn	Resource Manager	Hadoop SSL Keystore Factory

Component	Service	SSL Management
	JobHistory	Hadoop SSL Keystore Factory
Oozie		Configured in oozie-site.xml
HBase	REST API	Configured in hbase-site.xml
Hive	HiveServer2	Configured in hive-site.xml
Kafka		JDK: User and default
Solr		JDK: User and default
Accumulo		JDK: User and default
Falcon	REST API	JDK: User and default
Knox	Hadoop cluster (REST client)	JDK: default only
	Knox Gateway server	JDK: User and default
HDP Security Administration	Server/Agent	JDK: User and default

When enabling support for SSL, it is important to know which SSL Management method is being used by the Hadoop service. Services that are co-located on a host must configure the server certificate and keys, and in some cases the client truststore, in the Hadoop SSL Keystore Factory and JDK locations. When using CA signed certificates, configure the Hadoop SSL Keystore Factory to use the Java keystore and truststore locations.

The following list describes major differences between certificates managed by the Hadoop SSL Keystore Management Factory and certificates managed by JDK:

- Hadoop SSL Keystore Management Factory:
 - Supports only JKS formatted keys.
 - Supports toggling the shuffle between HTTP and HTTPS.
 - Supports two way certificate and name validation.
 - Uses a common location for both the keystore and truststore that is available to other Hadoop core services.
 - Allows you to manage SSL in a central location and propagate changes to all cluster nodes.
 - Automatically reloads the keystore and truststore without restarting services.
- SSL Management with JDK:
 - Allows either HTTP or HTTPS.
 - Uses hard-coded locations for truststores and keystores that may vary between hosts. Typically, this requires you to generate key pairs and import certificates on each host.
 - Requires the service to be restarted to reload the keystores and truststores.
 - Requires certificates to be installed in the client CA truststore.



Note

For more information on JDK SSL Management, see "Using SSL" in [Monitoring and Managing Using JMX Technology](#).

4.4. Creating and Managing SSL Certificates

This section contains the following topics:

- Obtaining a certificate from a third-party Certificate Authority (CA)
- Creating an internal CA (OpenSSL)
- Installing Certificates in the Hadoop SSL Keystore Factory (HDFS, MapReduce, and YARN)
- Using an internal CA (OpenSSL)



Note

For more information about the `keytool` utility, see the Oracle `keytool` reference: [keytool - Key and Certificate Management Tool](#).

For more information about OpenSSL, see [OpenSSL Documentation](#).



Note

Java-based Hadoop components such as HDFS, MapReduce, and YARN support JKS format, while Python based services such as Hue use PEM format.

4.4.1. Obtain a Certificate from a Trusted Third-Party Certification Authority (CA)

A third-party Certification Authority (CA) accepts certificate requests from entities, authenticates applications, issues certificates, and maintains status information about certificates. Associated cryptography guarantees that a signed certificate is computationally difficult to forge. Thus, as long as the CA is a genuine and trusted authority, clients have high assurance that they are connecting to the machines that they are attempting to connect with.

To obtain a certificate signed by a third-party CA, generate and submit a Certificate Signing Request (CSR) for each cluster node:

1. From the service user account associated with the component (such as `hive`, `hbase`, `oozie`, or `hdfs`, shown below as `<service_user>`), generate the host key:

```
su -l <service_user> -C "keytool -keystore <client-keystore> -genkey -alias <host>"
```

2. At the prompts, enter the information required by the CSR.



Note

Request generation information and requirements vary depending on the certificate authority. Check with your CA for details.

Example using default keystore `keystore.jks`:

```
su -l hdfs -c "keytool -keystore keystore.jks -genkey -alias n3"
```

```
Enter keystore password: *****
What is your first and last name?
[Unknown]: hortonworks.com
What is the name of your organizational unit?
[Unknown]: Development
What is the name of your organization?
[Unknown]: Hortonworks
What is the name of your City or Locality?
[Unknown]: SantaClara
What is the name of your State or Province?
[Unknown]: CA
What is the two-letter country code for this unit?
[Unknown]: US
Is <CN=hortonworks.com, OU=Development, O=Hortonworks, L=SantaClara, ST=CA, C=US correct?
[no]: yes

Enter key password for <host>
(RETURN if same as keystore password):
```

By default, keystore uses JKS format for the keystore and truststore. The keystore file is created in the user's home directory. Access to the keystore requires the password and alias.

3. Verify that the key was generated; for example:

```
su -l hdfs -c "keytool -list -v -keystore keystore.jks"
```

4. Create the CSR file:

```
su -l hdfs -c "keytool -keystore <keystorename> -certreq -alias <host> -keyalg rsa -file <host>.csr"
```

This command generates a certificate signing request that can be sent to a CA. The file `<host>.csr` contains the CSR.

The CSR is created in the user's home directory.

5. Confirm that the `keystore.jks` and `<host>.csr` files exist by running the following command and making sure that the files are listed in the output:

```
su -l hdfs -c "ls ~/"
```

6. Submit the CSR to your Certificate Authority.
7. To import and install keys and certificates, follow the instructions sent to you by the CA.

4.4.2. Create and Set Up an Internal CA (OpenSSL)

OpenSSL provides tools to allow you to create your own private certificate authority.

Considerations:

- The encryption algorithms may be less secure than a well-known, trusted third-party.
- Unknown CAs require that the certificate be installed in corresponding client truststores.



Note

When accessing the service from a client application such as HiveCLI or cURL, the CA must resolve on the client side or the connection attempt may fail. Users accessing the service through a browser will be able to add an exception if the certificate cannot be verified in their local truststore.

Prerequisite: Install `openssl`. For example, on CentOS run `yum install openssl`.

To create and set up a CA:

1. Generate the key and certificate for a component process.

The first step in deploying HTTPS for a component process (for example, Kafka broker) is to generate the key and certificate for each node in the cluster. You can use the Java `keytool` utility to accomplish this task. Start with a temporary keystore, so that you can export and sign it later with the CA.

Use the following `keytool` command to create the key and certificate:

```
$ keytool -keystore <keystore-file> -alias localhost -validity <validity> -genkey
```

where:

`<keystore-file>` is the keystore file that stores the certificate. The keystore file contains the private key of the certificate; therefore, it needs to be kept safely.

`<validity>` is the length of time (in days) that the certificate will be valid.

Make sure that the common name (CN) matches the fully qualified domain name (FQDN) of the server. The client compares the CN with the DNS domain name to ensure that it is indeed connecting to the desired server, not a malicious server.

2. Create the Certificate Authority (CA)

After step 1, each machine in the cluster has a public-private key pair and a certificate that identifies the machine. The certificate is unsigned, however, which means that an attacker can create such a certificate to pretend to be any machine.

To prevent forged certificates, it is very important to sign the certificates for each machine in the cluster.

A CA is responsible for signing certificates, and associated cryptography guarantees that a signed certificate is computationally difficult to forge. Thus, as long as the CA is a genuine and trusted authority, the clients have high assurance that they are connecting to the machines that they are attempting to connect with.

Here is a sample `openssl` command to generate a CA:

```
openssl req -new -x509 -keyout ca-key -out ca-cert -days 365
```

The generated CA is simply a public-private key pair and certificate, intended to sign other certificates.

3. Add the generated CA to the *server's* truststore:

```
keytool -keystore server.truststore.jks -alias CARoot -import -file ca-cert
```

4. Add the generated CA to the *client's* truststore, so that clients know that they can trust this CA:

```
keytool -keystore client.truststore.jks -alias CARoot -import -file ca-cert
```

In contrast to the keystore in step 1 that stores each machine's own identity, the truststore of a client stores all of the certificates that the client should trust. Importing a certificate into one's truststore also means trusting all certificates that are signed by that certificate.

Trusting the CA means trusting all certificates that it has issued. This attribute is called a "chain of trust," and is particularly useful when deploying SSL on a large cluster. You can sign all certificates in the cluster with a single CA, and have all machines share the same truststore that trusts the CA. That way all machines can authenticate all other machines.

5. Sign all certificates generated in Step 1 with the CA generated in Step 2:

a. Export the certificate from the keystore:

```
keytool -keystore server.keystore.jks -alias localhost -certreq -file cert-file
```

b. Sign the certificate with the CA:

```
openssl x509 -req -CA ca-cert -CAkey ca-key -in cert-file -out cert-signed -days <validity> -CAcreateserial -passin pass:<ca-password>
```

6. Import the CA certificate and the signed certificate into the keystore. For example:

```
$ keytool -keystore server.keystore.jks -alias CARoot -import -file ca-cert
$ keytool -keystore server.keystore.jks -alias localhost -import -file cert-signed
```

The parameters are defined as follows:

Parameter	Description
keystore	The location of the keystore
ca-cert	The certificate of the CA
ca-key	The private key of the CA
ca-password	The passphrase of the CA
cert-file	The exported, unsigned certificate of the server
cert-signed	The signed certificate of the server

All of the preceding steps can be placed into a bash script.

In the following example, note that one of the commands assumes a password of `test1234`. Specify your own password before running the script.

```
#!/bin/bash

#Step 1
keytool -keystore server.keystore.jks -alias localhost -validity 365 -genkey
```

```
#Step 2
openssl req -new -x509 -keyout ca-key -out ca-cert -days 365
keytool -keystore server.truststore.jks -alias CARoot -import -file ca-cert
keytool -keystore client.truststore.jks -alias CARoot -import -file ca-cert

#Step 3
keytool -keystore server.keystore.jks -alias localhost -certreq -file cert-
file
openssl x509 -req -CA ca-cert -CAkey ca-key -in cert-file -out cert-signed -
days 365 -CAcreateserial -passin pass:test1234
keytool -keystore server.keystore.jks -alias CARoot -import -file ca-cert
keytool -keystore server.keystore.jks -alias localhost -import -file cert-
signed
```

To finish the setup process:

1. Set up the CA directory structure:

```
mkdir -m 0700 /root/CA /root/CA/certs /root/CA/crl /root/CA/newcerts /root/
CA/private
```

2. Move the CA key to /root/CA/private and the CA certificate to /root/CA/certs.

```
mv ca.key /root/CA/private;mv ca.crt /root/CA/certs
```

3. Add required files:

```
touch /root/CA/index.txt; echo 1000 >> /root/CA/serial
```

4. Set permissions on the ca.key:

```
chmod 0400 /root/ca/private/ca.key
```

5. Open the OpenSSL configuration file:

```
vi /etc/pki/tls/openssl.cnf
```

6. Change the directory paths to match your environment:

```
[ CA_default ]

dir                = /root/CA                # Where everything is kept
certs              = /root/CA/certs          # Where the issued certs are kept
crl_dir            = /root/CA/crl            # Where the issued crl are kept
database           = /root/CA/index.txt     # database index file.
#unique_subject    = no                     # Set to 'no' to allow creation
of                                                         # several certificates with same
subject.
new_certs_dir      = /root/CA/newcerts      # default place for new certs.

certificate        = /root/CA/cacert.pem    # The CA certificate
serial             = /root/CA/serial        # The current serial number
crlnumber          = /root/CA/crlnumber     # the current crl number
                                                         # must be commented out to leave
a V1 CRL
crl                = $dir/crl.pem           # The current CRL
private_key        = /root/CA/private/akey.pem # The private key
```



```

RANDFILE          = /root/CA/private/.rand      # private random number file
x509_extensions = usr_cert                      # The extensions to add to the cert

```

7. Save the changes and restart OpenSSL.

Example of setting up an OpenSSL internal CA:

```

openssl genrsa -out ca.key 8192; openssl req -new -x509 -extensions v3_ca -key
ca.key -out ca.crt -days 365

```

```

Generating RSA private key, 8192 bit long modulus
.....++
.....++
e is 65537 (0x10001)
You are about to be asked to enter information that will be incorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Name or a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.

Country Name (2 letter code) [XX]:US
State or Province Name (full name) []:California
Locality Name (eg, city) [Default City]:SantaClara
Organization Name (eg, company) [Default Company Ltd]:Hortonworks
Organizational Unit Name (eg, section) []:
Common Name (eg, your name or your server's hostname) []:nn
Email Address []:it@hortonworks.com

mkdir -m 0700 /root/CA /root/CA/certs /root/CA/crl /root/CA/newcerts /root/CA/
private
ls /root/CA
certs crl newcerts private

```

4.4.3. Installing Certificates in the Hadoop SSL Keystore Factory (HDFS, MapReduce, and YARN)

HDFS, MapReduce, and YARN use the Hadoop SSL Keystore Factory to manage SSL Certificates. This factory uses a common directory for server keystore and client truststore. The Hadoop SSL Keystore Factory allows you to use CA certificates managed in their own stores.

1. Create a directory for the server and client stores.

```

mkdir -p <SERVER_KEY_LOCATION> ; mkdir -p <CLIENT_KEY_LOCATION>

```

2. Import the server certificate from each node into the HTTP Factory truststore.

```

cd <SERVER_KEY_LOCATION> ; keytool -import -noprompt -alias <remote-
hostname> -file <remote-hostname>.jks -keystore <TRUSTSTORE_FILE> -storepass
<SERVER_TRUSTSTORE_PASSWORD>

```

3. Create a single truststore file containing the public key from all certificates, by importing the public key for each CA or from each self-signed certificate pair:

```

keytool -import -noprompt -alias <host> -file $CERTIFICATE_NAME -keystore
<ALL_JKS> -storepass <CLIENT_TRUSTSTORE_PASSWORD>

```

4. Copy the keystore and truststores to every node in the cluster.
5. Validate the common truststore file on all hosts.

```
keytool -list -v -keystore <ALL_JKS> -storepass <CLIENT_TRUSTSTORE_PASSWORD>
```

6. Set permissions and ownership on the keys:

```
chgrp -R <YARN_USER>:hadoop <SERVER_KEY_LOCATION>
chgrp -R <YARN_USER>:hadoop <CLIENT_KEY_LOCATION>
chmod 755 <SERVER_KEY_LOCATION>
chmod 755 <CLIENT_KEY_LOCATION>
chmod 440 <KEYSTORE_FILE>
chmod 440 <TRUSTSTORE_FILE>
chmod 440 <CERTIFICATE_NAME>
chmod 444 <ALL_JKS>
```



Note

The complete path of the `<SERVER_KEY_LOCATION>` and the `<CLIENT_KEY_LOCATION>` from the root directory `/etc` must be owned by the `yarn` user and the `hadoop` group.

4.4.4. Using a CA-Signed Certificate

To use a CA-signed certificate:

1. Run the following command to create a self-signing rootCA and import the rootCA into the client truststore. This is a private key; it should be kept private. The following command creates a 2048-bit key:

```
openssl genrsa -out <clusterCA>.key 2048
```

2. Self-sign the rootCA. The following command signs for 300 days. It will start an interactive script that requests name and location information.

```
openssl req -x509 -new -key <clusterCA>.key -days 300 -out <clusterCA>
```

3. Import the rootCA into the client truststore:

```
keytool -importcert -alias <clusterCA> -file $clusterCA -keystore
<clustertruststore> -storepass <clustertruststorekey>
```



Note

Make sure that the `ssl-client.xml` file on every host is configured to use this `$clustertrust` store.

When configuring with Hive point to this file; when configuring other services install the certificate in the Java truststore.

4. For each host, sign the `certreq` file with the rootCA:

```
openssl x509 -req -CA $clusterCA.pem -CAkey <clusterCA>.key -in <host>.cert
-out $host.signed -days 300 -CAcreateserial
```

5. On each host, import the rootCA and the signed cert back in:

```
keytool -keystore <hostkeystore> -storepass <hoststorekey> -alias
<clusterCA> -import -file cluster1CA.pem
keytool -keystore <hostkeystore> -storepass <hoststorekey> -alias `hostname
-s` -import -file <host>.signed -keypass <hostkey>
```

4.5. Enabling SSL for HDP Components

The following table contains links to instructions for enabling SSL on specific HDP components.



Note

These instructions assume that you have already created keys and signed certificates for each component of interest, across your cluster. (See [Section 4.3, “Enabling SSL: Understanding the Hadoop SSL Keystore Factory” \[289\]](#) for more information.)

Table 4.2. Configure SSL Data Protection for HDP Components

HDP Component	Notes/Link
Hadoop, MapReduce, YARN	Section 4.1, “Enabling RPC Encryption” [288] ; Section 4.6, “Enable SSL for WebHDFS, MapReduce Shuffle, and YARN” [298]
Oozie	Section 4.8, “Enable SSL on Oozie” [302]
HBase	Section 4.9, “Enable SSL on the HBase REST Server” [303]
Hive (HiveServer2)	Section 4.11, “Enable SSL on HiveServer2” [306]
Kafka	Section 4.12, “Enable SSL for Kafka Clients” [307]
Ambari Server	Set Up SSL for Ambari
Falcon	Enabled by default (see Installing the Falcon Package)
Sqoop	Clients of Hive and HBase, see Data Integration Services with HDP, Apache Sqoop Connectors
Knox Gateway	Knox Administrator Guide, Gateway Security, Configure Wire Encryption
Flume	Apache Flume User Guide, Flume Sources
Accumulo	Apache Foundation Blog, Apache Accumulo: Generating Keystores for configuring Accumulo with SSL
Phoenix	Non-Ambari Cluster Installation, Installing Apache Phoenix: Configuring Phoenix for Security and Apache Phoenix, Flume Plug-in
HUE	Non-Ambari Cluster Installation, Installing Hue, Configure Hue

4.6. Enable SSL for WebHDFS, MapReduce Shuffle, and YARN

This section explains how to set up SSL for WebHDFS, YARN and MapReduce. Before you begin, make sure that the SSL certificate is properly configured, including the keystore and truststore that will be used by WebHDFS, MapReduce, and YARN.

HDP supports the following SSL modes:

- One-way SSL: SSL client validates the server identity only.
- Mutual authentication (2WAY SSL): The server and clients validate each others' identities. 2WAY SSL can cause performance delays and is difficult to set up and maintain.



Note

In order to access SSL enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Apache Knox Gateway Administrator Guide, Gateway Security, Configure Wire Encryption](#).

To enable one-way SSL set the following properties and restart all services:

1. Set the following property values (or add the properties if required) in `core-site.xml`:

```
hadoop.ssl.require.client.cert=false
```

```
hadoop.ssl.hostname.verifier=DEFAULT
```

```
hadoop.ssl.keystores.factory.class=org.apache.hadoop.security.ssl.FileBasedK
```

```
hadoop.ssl.server.conf=ssl-server.xml
```

```
hadoop.ssl.client.conf=ssl-client.xml
```



Note

Specify the `hadoop.ssl.server.conf` and `hadoop.ssl.client.conf` values as the relative or absolute path to Hadoop SSL Keystore Factory configuration files. If you specify only the file name, put the files in the same directory as the `core-site.xml`.

2. Set the following properties (or add the properties if required) in `hdfs-site.xml`:

- `dfs.http.policy=<Policy>`
- `dfs.client.https.need-auth=true` (optional for mutual client/server certificate validation)
- `dfs.datanode.https.address=<hostname>:50475`
- `dfs.namenode.https-address=<hostname>:50470`

where `<Policy>` is either:

- `HTTP_ONLY`: service is provided only on HTTP
- `HTTPS_ONLY`: service is provided only on HTTPS
- `HTTP_AND_HTTPS`: service is provided both on HTTP and HTTPS

3. Set the following properties in `mapred-site.xml`:

```
mapreduce.jobhistory.http.policy=HTTPS_ONLY
```

```
mapreduce.jobhistory.webapp.https.address=<JHS>:<JHS_HTTPS_PORT>
```

4. Set the following properties in `yarn-site.xml`:

```
yarn.http.policy=HTTPS_ONLY
yarn.log.server.url=https://<JHS>:<JHS_HTTPS_PORT>/jobhistory/logs
yarn.resourcemanager.webapp.https.address=<RM>:<RM_HTTPS_PORT>
yarn.nodemanager.webapp.https.address=0.0.0.0:<NM_HTTPS_PORT>
```

5. Create an `ssl-server.xml` file for the Hadoop SSL Keystore Factory:

- a. Copy the example SSL Server configuration file and modify the settings for your environment:

```
cp /etc/hadoop/conf/ssl-server.xml.example /etc/hadoop/conf/ssl-server.xml
```

- b. Configure the server SSL properties:

Table 4.3. Configuration Properties in `ssl-server.xml`

Property	Default Value	Description
<code>ssl.server.keystore.type</code>	JKS	The type of the keystore, JKS = Java Keystore, the de-facto standard in Java
<code>ssl.server.keystore.location</code>	None	The location of the keystore file
<code>ssl.server.keystore.password</code>	None	The password to open the keystore file
<code>ssl.server.truststore.type</code>	JKS	The type of the trust store
<code>ssl.server.truststore.location</code>	None	The location of the truststore file
<code>ssl.server.truststore.password</code>	None	The password to open the truststore

For example:

```
<property>
  <name>ssl.server.truststore.location</name>
  <value>/etc/security/serverKeys/truststore.jks</value>
  <description>Truststore to be used by NN and DN. Must be specified.</description>
</property>

<property>
  <name>ssl.server.truststore.password</name>
  <value>changeit</value>
  <description>Optional. Default value is "<!--
  </description>
</property>

<property>
  <name>ssl.server.truststore.type</name>
  <value>jks</value>
  <description>Optional. The keystore file format, default value is
  "jks".</description>
</property>

<property>
  <name>ssl.server.truststore.reload.interval</name>
```

```

<value>10000</value>
<description>Truststore reload check interval, in milliseconds.
Default value is 10000 (10 seconds).</description>
</property>

<property>
<name>ssl.server.keystore.location</name>
<value>/etc/security/serverKeys/keystore.jks</value>
<description>Keystore to be used by NN and DN. Must be specified.</
description>
</property>

<property>
<name>ssl.server.keystore.password</name>
<value>changeit</value>
<description>Must be specified.</description>
</property>

<property>
<name>ssl.server.keystore.keypassword</name>
<value>changeit</value>
<description>Must be specified.</description>
</property>

<property>
<name>ssl.server.keystore.type</name>
<value>jks</value>
<description>Optional. The keystore file format, default value is
"jks".</description>
</property>

```

6. Create an `ssl-client.xml` file for the Hadoop SSL Keystore Factory:

a. Copy the client truststore example file:

```
cp /etc/hadoop/conf/ssl-server.xml.example /etc/hadoop/conf/ssl-server.xml
```

b. Configure the client trust store values:

```
ssl.client.truststore.location=/etc/security/clientKeys/all.jks
ssl.client.truststore.password=clientTrustStorePassword
ssl.client.truststore.type=jks
```

7. Copy the configuration files (`core-site.xml`, `hdfs-site.xml`, `mapred-site.xml`, `yarn-site.xml`, `ssl-server.xml`, and `ssl-client.xml`), including the `ssl-server` and `ssl-client` store files if the Hadoop SSL Keystore Factory uses its own keystore and truststore files, to all nodes in the cluster.

8. Restart services on all nodes in the cluster.

4.7. Enable SSL for HttpFS

Use the following steps to configure [HttpFS](#) to work over SSL.

1. Edit the `httpfs-env.sh` script in the configuration directory and set `HTTPFS_SSL_ENABLED` to `true`.

In addition, the following 2 properties can be defined (shown here with default values):

- `HTTPFS_SSL_KEYSTORE_FILE=$HOME/.keystore`
- `HTTPFS_SSL_KEYSTORE_PASS=password`

2. In the `HttpFS tomcat/conf` directory, replace the `server.xml` file with the `ssl-server.xml` file.
3. Create an SSL certificate for the `HttpFS` server. As the `httpfs` Unix user, use the Java `keytool` command to create the SSL certificate:

```
$ keytool -genkey -alias tomcat -keyalg RSA
```

You will be asked a series of questions in an interactive prompt. It will create the keystore file, which will be named `.keystore` and located in the `httpfs` user home directory.

The password you enter for “keystore password” must match the value of the `HTTPFS_SSL_KEYSTORE_PASS` environment variable set in the `httpfs-env.sh` script in the configuration directory.

The answer to “What is your first and last name?” (i.e. “CN”) must be the host name of the machine where the `HttpFS` Server will be running.

4. Start `HttpFS`. It should work over `HTTPS`.
5. Utilizing the Hadoop FileSystem API or the Hadoop FS shell, use the `swwebhdfs://` scheme. Make sure the JVM is picking up the truststore containing the public key of the SSL certificate if you are using a self-signed certificate.

4.8. Enable SSL on Oozie

The default SSL configuration makes all Oozie URLs use `HTTPS` except for the `JobTracker` callback URLs. This simplifies the configuration because no changes are required outside of Oozie. Oozie inherently does not trust the callbacks, they are used as hints.



Note

Before you begin ensure that the SSL certificate has been generated and properly configured. By default Oozie uses the user default keystore. In order to access SSL enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Apache Knox Gateway Administrator Guide, Gateway Security, Configure Wire Encryption](#).

1. If Oozie server is running, stop Oozie.
2. Change the Oozie environment variables for `HTTPS` if required:
 - `OOZIE_HTTPS_PORT` set to Oozie `HTTPS` port. The default value is 11443.
 - `OOZIE_HTTPS_KEYSTORE_FILE` set to the keystore file that contains the certificate information. Default value `$(HOME)/.keystore`, that is the home directory of the Oozie user.

- OOZIE_HTTPS_KEYSTORE_PASS set to the password of the keystore file. Default value password.



Note

See [Oozie Environment Setup](#) for more details.

3. Run the following command to enable SSL on Oozie:

```
su -l oozie -c "/usr/hdp/current/oozie-server/bin/oozie-setup.sh prepare-war -secure"
```

4. Start the Oozie server.



Note

To revert back to unsecured HTTP, run the following command:

```
su -l oozie -c "/usr/hdp/current/oozie-server/bin/oozie-setup.sh prepare-war"
```

4.8.1. Configure Oozie HCatalogJob Properties

Integrate Oozie HCatalog by adding following property to `oozie-hcatalog job.properties`. For example if you are using Ambari, set the properties as:

```
hadoop.rpc.protection=privacy
```



Note

This property is in addition to any properties you must set for secure clusters.

4.9. Enable SSL on the HBase REST Server

Perform the following task to enable SSL on an HBase REST API.



Note

In order to access SSL-enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Configure SSL for Knox](#).

1. Create and install an SSL certificate for HBase, for example to use a self-signed certificate:

- a. Create an HBase keystore:

```
su -l hbase -c "keytool -genkey -alias hbase -keyalg RSA -keysize 1024 -keystore hbase.jks"
```

At the keytool command prompt:

- Enter the key password
- Enter the keystore password



Note

Add these two specified values to the corresponding properties in `hbase-site.xml` in step 2.

b. Export the certificate:

```
su -l hbase -c "keytool -exportcert -alias hbase -file certificate.cert -keystore hbase.jks"
```

c. (Optional) Add certificate to the Java keystore:

- If you are not root run:

```
sudo keytool -import -alias hbase -file certificate.cert -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

- If you are root:

```
keytool -import -alias hbase -file certificate.cert -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

2. Add the following properties to the `hbase-site.xml` configuration file on each node in your HBase cluster:

```
<property>
<name>hbase.rest.ssl.enabled</name>
<value>>true</value>
</property>

<property>
<name>hbase.rest.ssl.keystore.store</name>
<value>/path/to/keystore</value>
</property>

<property>
<name>hbase.rest.ssl.keystore.password</name>
<value>keystore-password</value>
</property>

<property>
<name>hbase.rest.ssl.keystore.keypassword</name>
<value>key-password</value>
</property>
```

3. Restart all HBase nodes in the cluster.



Note

For clusters using self-signed certificates: Define the truststore as a custom property on the JVM. If the self-signed certificate is not added to the system truststore (`cacerts`), specify the Java KeyStore (`.jks`) file containing the certificate

in applications by invoking the `javax.net.ssl.trustStore` system property. Run the following command argument in the application client container to use a self-signed certificate in a `.jks` file:

```
-Djavax.net.ssl.trustStore=/path/to/keystore
```

4.10. Enable SSL on the HBase Web UI

Perform the following task to enable SSL and TLS on an HBase Web UI.



Note

In order to access SSL-enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Configure SSL for Knox](#).

1. Create and install an SSL certificate for HBase, for example to use a self-signed certificate:

- a. Create an HBase keystore:

```
su -l hbase -c "keytool -genkey -alias hbase -keyalg RSA -keysize 1024 -keystore hbase.jks"
```

At the keytool command prompt:

- Enter the key password
- Enter the keystore password



Note

Add these two specified values to the corresponding properties in `hbase-site.xml` in step 2.

- b. Export the certificate:

```
su -l hbase -c "keytool -exportcert -alias hbase -file certificate.cert -keystore hbase.jks"
```

- c. (Optional) Add certificate to the Java keystore:

- If you are not root run:

```
sudo keytool -import -alias hbase -file certificate.cert -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

- If you are root:

```
keytool -import -alias hbase -file certificate.cert -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

2. Add the following properties to the `hbase-site.xml` configuration file on each node in your HBase cluster:

```
<property>
<name>hbase.ssl.enabled</name>
<value>>true</value>
</property>

<property>
<name>hadoop.ssl.enabled</name>
<value>>true</value>
</property>

<property>
<name>ssl.server.keystore.keypassword</name>
<value>key-password</value>
</property>

<property>
<name><ssl.server.keystore.password</name>
<value>keystore-password</value>
</property>

<property>
<name>ssl.server.keystore.location</name>
<value>/tmp/server-keystore.jks</value>
</property>
```

3. Restart all HBase nodes in the cluster.



Note

For clusters using self-signed certificates: Define the truststore as a custom property on the JVM. If the self-signed certificate is not added to the system truststore (cacerts), specify the Java KeyStore (.jks) file containing the certificate in applications by invoking the `javax.net.ssl.trustStore` system property. Run the following command argument in the application client container to use a self-signed certificate in a .jks file:

```
-Djavax.net.ssl.trustStore=/path/to/keystore
```

4.11. Enable SSL on HiveServer2

When using HiveServer2 without Kerberos authentication, you can enable SSL.



Note

In order to access SSL enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Apache Knox Gateway Administrator Guide, Gateway Security, Configure Wire Encryption](#).

Perform the following steps on the HiveServer2:

1. Run the following command to create a keystore for hiveserver2::

```
keytool -genkey -alias hbase -keyalg RSA -keysize 1024 -keystore hbase.jks
```

2. Edit the `hive-site.xml`, set the following properties to enable SSL:

```
<property>
```

```

<name>hive.server2.use.SSL</name>
<value>true</value>
<description></description>
</property>

<property>
<name>hive.server2.keystore.path</name>
<value>keystore-file-path</value>
<description></description>
</property>

<property>
<name>hive.server2.keystore.password</name>
<value>keystore-file-password</value>
<description></description>
</property>

```

3. On the client-side, specify SSL settings for Beeline or JDBC client as follows:

```

jdbc:hive2://<host>:<port>/<database>;ssl=true;sslTrustStore=<path-to-truststore>;trustStorePassword=<password>

```

4.12. Enable SSL for Kafka Clients

Kafka allows clients to connect over SSL. By default SSL is disabled, but it can be enabled as needed.

Before you begin, be sure to generate the key, SSL certificate, keystore, and truststore that will be used by Kafka.

4.12.1. Configuring the Kafka Broker

The Kafka Broker supports listening on multiple ports and IP addresses. To enable this feature, specify one or more comma-separated values in the `listeners` property in `server.properties`.

Both PLAINTEXT and SSL ports are required if SSL is not enabled for inter-broker communication (see the following subsection for information about enabling inter-broker communication):

```
listeners=PLAINTEXT://host.name:port,SSL://host.name:port
```

The following SSL configuration settings are needed on the broker side:

```

ssl.keystore.location = /var/private/ssl/kafka.server.keystore.jks
ssl.keystore.password = test1234
ssl.key.password = test1234
ssl.truststore.location = /var/private/ssl/kafka.server.truststore.jks
ssl.truststore.password = test1234

```

The following optional settings are available:

Property	Description	Value(s)
<code>ssl.client.auth</code>	Specify whether client authentication is required, requested, or not required.	none

Property	Description	Value(s)
	<p>none: no client authentication.</p> <p>required: client authentication is required.</p> <p>requested: client authentication is requested, but a client without certs can still connect.</p> <p>Note: If you set <code>ssl.client.auth</code> to <code>requested</code> or <code>required</code>, then you must provide a truststore for the Kafka broker. The truststore should contain all CA certificates that are used to sign clients' keys.</p>	
<code>ssl.cipher.suites</code>	Specify one or more cipher suites: named combinations of authentication, encryption, MAC and key exchange algorithms used to negotiate the security settings for a network connection using the TLS or SSL network protocol.	
<code>ssl.enabled.protocols</code>	Specify the SSL protocols that you will accept from clients. Note: SSL is deprecated; its use in production is not recommended.	TLSv1.2, TLSv1.1, TLSv1
<code>ssl.keystore.type</code>	Specify the SSL keystore type.	JKS
<code>ssl.truststore.type</code>	Specify the SSL truststore type.	JKS

Enabling SSL for Inter-Broker Communication

To enable SSL for inter-broker communication, add the following setting to the broker properties file (default is PLAINTEXT):

```
security.inter.broker.protocol = SSL
```

Enabling Additional Cipher Suites

To enable any cipher suites other than the defaults that come with JVM (see [Java Cryptography documentation](#)), you will need to install JCE Unlimited Strength Policy files ([download link](#)).

Validating the Configuration

After you start the broker, you should see the following information in the `server.log` file:

```
with addresses: PLAINTEXT -> EndPoint(192.168.64.1,9092,PLAINTEXT),SSL -> EndPoint(192.168.64.1,9093,SSL)
```

To make sure that the server keystore and truststore are set up properly, run the following command:

```
openssl s_client -debug -connect localhost:9093 -tls1
```

(Note: TLSv1 should be listed under `ssl.enabled.protocols`)

In the `openssl` output you should see the server certificate; for example:

```
Server certificate
```

```

-----BEGIN CERTIFICATE-----
MIID+DCCAuACCQCx2Rz1tXx3NTANBgkqhkiG9w0BAQsFADB6MQswCQYDVQQGEwJV
UzELMAkGA1UECAwCQ0ExFDASBgNVBACMC1NhbnRhIENsYXJhMQwwCgYDVQQKDANv
cmcxDDAKBgNVBAsMA29yZzEOMAwGA1UEAwFa2FmYXNwHDAAAgkqhkiG9w0BCQEW
DXRlc3RAdGVzdC5jb20wHhcNMTUwNzZzMDQyOTMwMwHcNMTYwNzI5MDQyOTMwMwJt
MQswCQYDVQQGEwJVUzELMAkGA1UECBMCQ0ExFDASBgNVBACTC1NhbnRhIENsYXJh
MQwwCgYDVQQKEwNvcmcxDDAKBgNVBAsTA29yZzEzZmB0GA1UEAxMwU3JpaGFyc2hh
IENoaW50YWxhcGFuaTCCAbcwggEsBgcqhkiG9w0AQBMIBHwKBgQD9f1OBHXUSKVLf
Spwu7OTn9hG3UjzvRADDHj+AtlEmaUVdQCJR+1k9jVj6v8X1uJd2y5tVbNeBO4Ad
NG/yZmC3a5lQpaSfn+gEexAiwk+7qdf+t8Yb+DtX58aophUPBPu9tPFHsMCNVQT
WhaRMvZl864rYdcq7/IiAxmd0UgBxwIVAjdGUI8VIwvMspK5gqLrhAvwWBz1AoGB
APfhoIXWmz3ey7yrXDa4V7l5lK+7+jrqgv1XTAs9B4JnUV1XjrrUWU/mcQcQgYC0
SRZxI+hMKBYTt88JMoZIpue8FngLVHyNKOCjrh4rs6ZlKw6jfwv6ITVi8ftiegEk
O8yk8b6oUZCJqIPf4VrlnwaSi2ZegHtVJWQBTdv+z0kqA4GEAAKBG+PdZ0306bq
TpUadb2FERMPLFsx06H0x+TULivcp7HbS5yrkV9bXZmv/FD98x76QxXr0q1WpQhY
YDeGdjH+XQk6ZxBVBNJDIPcnfQpfzXAvryQ+cm8oXUsKidtHf4pLMYViXX6BWX
Oc2hX4rG+lC8/NXW+1zVvCr9To9fngzjMA0GCSqGSIb3DQEBCwUAA4IBAQBfyVse
RJ+uginlWg5trZscqH0tlocbnek4UuV/xis2eAu9l4EFOM5krt5GmkGZRCm/zHF8
BRJwXbf0fytmQKSPFk8R4/NGDolzoK+F7uXeJ0S2u/T29xk0u2i4tjvleq6OCphE
i9vdjm0E0Whf9SHRhOXirOYFX3cL775XwKdzKKRkk+AszFR+mRu90rdoeapQtgGh
9Kfwr4+6AU/dPtdGuomtBQqMxCzlrLd8EYhVVQ97wHIz3sPvlM5PIhOJ/YHSBJIC
75eo/4acDxZ+j3sR5kcFulzYwFLgDYBaKH/w3mYcGTALeBlzUkX53NVizIvhUd69
XJO4lDSDtG0lfort
-----END CERTIFICATE-----
subject=/C=US/ST=CA/L=Santa Clara/O=org/OU=org/CN=JBrown
issuer=/C=US/ST=CA/L=Santa Clara/O=org/OU=org/CN=kafak/emailAddress=test@test.
com

```

If the certificate does not display, or if there are any other error messages, then your keystore is not set up properly.

4.12.2. Configuring Kafka Producer and Kafka Consumer

SSL is supported for new Kafka Producers and Consumer processes; the older API is not supported. Configuration settings for SSL are the same for producers and consumers.

If client authentication is not needed in the broker, then the following is a minimal configuration example:

```

security.protocol = SSL
ssl.truststore.location = /var/private/ssl/kafka.client.truststore.jks
ssl.truststore.password = test1234

```

If client authentication is required, first create a keystore (described earlier in this chapter). Next, specify the following settings:

```

ssl.keystore.location = /var/private/ssl/kafka.client.keystore.jks
ssl.keystore.password = test1234
ssl.key.password = test1234

```

One or more of the following optional settings might also be needed, depending on your requirements and the broker configuration:

Property	Description	Value(s)
<code>ssl.provider</code>	The name of the security provider used for SSL connections. Default value is the default security provider of the JVM.	

Property	Description	Value(s)
<code>ssl.cipher.suites</code>	Specify one or more cipher suites: named combinations of authentication, encryption, MAC and key exchange algorithms used to negotiate the security settings for a network connection using the TLS or SSL network protocol.	
<code>ssl.enabled.protocols</code>	List at least one of the protocols configured on the broker side.	TLSv1.2, TLSv1.1, TLSv1
<code>ssl.keystore.type</code>	Specify the SSL keystore type.	JKS
<code>ssl.truststore.type</code>	Specify the SSL truststore type.	JKS

The following two examples launch console-producer and console-consumer processes:

```
kafka-console-producer.sh --broker-list localhost:9093 --topic test --
producer.config client-ssl.properties

kafka-console-consumer.sh --bootstrap-server localhost:9093 --topic test --
new-consumer --consumer.config client-ssl.properties
```

4.13. Enable SSL for Accumulo

One of the major features added in Accumulo 1.6.0 was the ability to configure Accumulo so that the Thrift communications will run over SSL. [Apache Thrift](#) is the remote procedure call library that is leveraged for both intra-server and client communication with Accumulo. Issuing these calls over a secure socket ensures that unwanted actors cannot inspect the traffic sent across the wire. Given the sometimes sensitive nature of data stored in Accumulo and the authentication details for users, secure communications are critical.

Due to the complex and deployment-specific nature of the security model for some systems, Accumulo expects users to provide their own certificates, guaranteeing that they are, in fact, secure. However, for those who require security but do not already operate within the confines of an established security infrastructure, OpenSSL and the Java keytool command can be used to generate the necessary components to enable wire encryption.

To enable SSL with Accumulo, it is necessary to generate a certificate authority and certificates that are signed by that authority. Typically, each client and server has its own certificate, which provides the finest level of control over a secure cluster when the certificates are properly secured.

4.13.1. Generate a Certificate Authority

The certificate authority (CA) controls what certificates can be used to authenticate with each other. To create a secure connection with two certificates, each certificate must be signed by a certificate authority in the "truststore" (A Java KeyStore which contains at least one Certificate Authority's public key). When creating your own certificate authority, a single CA is typically sufficient (and would result in a single public key in the truststore). Alternatively, a third party can also act as a certificate authority (to add an additional layer of security); however, these are typically not a free service.

The following is an example of creating a certificate authority and adding its public key to a Java KeyStore to provide to Accumulo.

```
# Create a private key
openssl genrsa -des3 -out root.key 4096

# Create a certificate request using the private key
openssl req -x509 -new -key root.key -days 365 -out root.pem

# Generate a Base64-encoded version of the PEM just created
openssl x509 -outform der -in root.pem -out root.der

# Import the key into a Java KeyStore
keytool -import -alias root-key -keystore truststore.jks -file root.der

# Remove the DER formatted key file (as we don't need it anymore)
rm root.der
```

Remember to protect `root.key` and never distribute it, as the private key is the basis for your circle of trust. The `keytool` command will prompt you about whether or not the certificate should be trusted: enter "yes". The `truststore.jks` file, a "truststore", is meant to be shared with all parties communicating with one another. The password provided to the truststore verifies that the contents of the truststore have not been tampered with.

4.13.2. Generate a Certificate/Keystore Per Host

It is desirable to generate a certificate for each host in the system. Additionally, each client connecting to the Accumulo instance running with SSL should be issued its own certificate. Issuing individual certificates to each entity provides proper control to revoke/reissue certificates to clients as necessary, without widespread interruption.

The following commands create a private key for the server, generate a certificate signing request created from that private key, use the certificate authority to generate the certificate using the signing request. and then create a Java KeyStore with the certificate and the private key for our server.

```
# Create the private key for our server
openssl genrsa -out server.key 4096

# Generate a certificate signing request (CSR) with our private key
openssl req -new -key server.key -out server.csr

# Use the CSR and the CA to create a certificate for the server (a reply to
the CSR)
openssl x509 -req -in server.csr -CA root.pem -CAkey root.key -CAcreateserial
-out server.crt -days 365

# Use the certificate and the private key for our server to create PKCS12
file
openssl pkcs12 -export -in server.crt -inkey server.key -certfile server.crt -
name 'server-key' -out server.p12

# Create a Java KeyStore for the server using the PKCS12 file (private key)
keytool -importkeystore -srckeystore server.p12 -srcstoretype pkcs12 -
destkeystore server.jks -deststoretype JKS

# Remove the PKCS12 file as we don't need it
rm server.p12

# Import the CA-signed certificate to the keystore
```



```
keytool -import -trustcacerts -alias server-crt -file server.crt -keystore
server.jks
```

This, combined with the truststore, provides what is needed to configure Accumulo servers to run over SSL. The private key (`server.key`), the certificate signed by the CA (`server.pem`), and the keystore (`server.jks`) should be restricted to only be accessed by the user running Accumulo on the host it was generated for. Use `chown` and `chmod` to protect the files, and do not distribute them over non-secure networks.

4.13.3. Configure Accumulo Servers

Now that the Java KeyStores have been created with the necessary information, the Accumulo configuration must be updated so that Accumulo creates the Thrift server over SSL instead of a normal socket. Configure the following properties in `accumulo-site.xml`:

```
<property>
  <name>rpc.javax.net.ssl.keyStore</name>
  <value>/path/to/server.jks</value>
</property>
<property>
  <name>rpc.javax.net.ssl.keyStorePassword</name>
  <value>server_password</value>
</property>
<property>
  <name>rpc.javax.net.ssl.trustStore</name>
  <value>/path/to/truststore.jks</value>
</property>
<property>
  <name>rpc.javax.net.ssl.trustStorePassword</name>
  <value>truststore_password</value>
</property>
<property>
  <name>instance.rpc.ssl.enabled</name>
  <value>true</value>
</property>
```

The keystore and truststore paths are both absolute paths on the local file system (not HDFS). Remember that the server keystore should only be readable by the user running Accumulo and, if you place plain-text passwords in `accumulo-site.xml`, make sure that `accumulo-site.xml` is also not globally readable. To keep these passwords out of `accumulo-site.xml`, consider configuring your system with the new Hadoop `CredentialProvider` class. See [ACCUMULO-2464](#) for more information on what will be available in Accumulo-1.6.1.

Also, be aware that if unique passwords are used for each server when generating the certificate, this will result in different `accumulo-site.xml` files for each host. Unique configuration files for each host will add complexity to the configuration management of your instance. The use of a `CredentialProvider` (a feature from Hadoop which allows for acquisitions of passwords from alternate systems) can help alleviate the issues with unique `accumulo-site.xml` files on each host. A Java KeyStore can be created using the `CredentialProvider` tools, which eliminates the need for passwords to be stored in `accumulo-site.xml`, and can instead point to the `CredentialProvider` URI which is consistent across hosts.

4.13.4. Configure Accumulo Clients

To configure Accumulo clients, use `$HOME/.accumulo/config`. This is a simple [Java properties file](#): each line is a configuration, key, and value separated by a space, and lines beginning with a `#` symbol are ignored. For example, if we generated a certificate and placed it in a keystore (as described above), we would generate the following file for the Accumulo client.

```
instance.rpc.ssl.enabled true
rpc.javax.net.ssl.keyStore /path/to/client-keystore.jks
rpc.javax.net.ssl.keyStorePassword client-password
rpc.javax.net.ssl.trustStore /path/to/truststore.jks
rpc.javax.net.ssl.trustStorePassword truststore-password
```

When creating a `ZooKeeperInstance`, the implementation will automatically look for this configuration file and set up a connection with the methods defined in this file. The `ClientConfiguration` class also contains methods that can be used instead of a configuration file on the file system. Again, the paths to the keystore and truststore are on the local file system, not HDFS.

4.14. SPNEGO setup for WebHCat

To set up secure WebHCat, set the following properties in the `/etc/hcatalog/conf/webhcat-site.xml` file:

```
</property>
  <name>templeton.kerberos.principal</name>
  <value>HTTP/host1234.example.com@EXAMPLE.COM</value>
  <description/>
</property>
```

The `templeton.kerberos.principal` property must use the host name of the WebHCat Server.

```
<property>
  <name>templeton.kerberos.keytab</name>
  <value>/etc/security/keytabs/spnego.service.keytab</value>
  <description/>
</property>
```

```
<property>
  <name>templeton.kerberos.secret</name>
  <value>secret</value>
  <description/>
</property>
```

```
<property>
  <name>templeton.hive.properties</name>
  <value>hive.metastore.local=false,hive.metastore.uris=thrift://host1234.
example.com:9083,
                                hive.metastore.sasl.enabled=true,hive.metastore.execute.
setugi=true,
                                hive.exec.mode.local.auto=false,
                                hive.metastore.kerberos.principal=hive/_HOST@EXAMPLE.COM</
value>
  <description>Properties to set when running hive.</description>
</property>
```

Be sure to set the `templeton.hive.properties` property with the host name for your Thrift server.

4.15. Configure SSL for Hue

HTTPS is a simple HTTP in conjunction with SSL (Secure Sockets Layer) and used for establishing an encrypted link between the web browser and the web server. Using HTTPS enables you to prevent collection of sensitive information between your web browser and a web server.

4.15.1. Enabling SSL on Hue by Using a Private Key

If you have a private key, follow these steps to enable SSL on Hue:

1. Configure Hue to use your private key by adding the following syntax to the `/etc/hue/conf/hue.ini` file:

```
ssl_certificate=$PATH_TO_CERTIFICATE
ssl_private_key=$PATH_TO_KEY
ssl_cipher_list="DEFAULT:!aNULL:!eNULL:!LOW:!EXPORT:!SSLv2" (default)
```

2. Restart Hue:

```
/etc/init.d/hue restart
```

4.15.2. Enabling SSL on Hue Without Using a Private Key

If you do not have a private key and want to run tests, you can enable SSL on Hue by creating a self-signed certificate:

1. Create a key:

```
openssl genrsa 1024 > host.key
```

2. Create a self-signed certificate:

```
openssl req -new -x509 -nodes -sha1 -key host.key > host.cert
```

3. Move the `host.key` and `host.cert` files to the `ssl` directory:

```
mv host.key /etc/ssl
mv host.cert /etc/ssl
```

4. Configure Hue to use your private key by adding the following syntax to the `/etc/hue/conf/hue.ini` file:

```
ssl_certificate=$PATH_TO_CERTIFICATE
ssl_private_key=$PATH_TO_KEY
ssl_cipher_list="DEFAULT:!aNULL:!eNULL:!LOW:!EXPORT:!SSLv2" (default)
```

5. Restart Hue:

```
/etc/init.d/hue restart
```

4.16. Configure SSL for Knox

For the simplest of evaluation deployments, the initial startup of the Knox Gateway will generate a self-signed cert for use on the same machine as the gateway instance. These certificates are issued for "localhost" and will require specifically disabling hostname verification on client machines other than where the gateway is running.

4.16.1. Self-Signed Certificate with Specific Hostname for Evaluations

In order to continue to use self-signed certificates for larger evaluation deployments, a certificate can be generated for a specific hostname. This will allow clients to properly verify the hostname presented in the certificate as the host that they requested in the request URL.

To create a self-signed certificate:

1. Create a certificate: where `$gateway-hostname` is the FQDN of the Knox Gateway.

```
cd $gateway bin/knoxcli.cmd create-cert --hostname $gateway-hostname
```

2. Export the certificate in PEM format:

```
keytool -export -alias gateway-identity -rfc -file $certificate_path -  
keystore $gateway /data/security/keystores/gateway.jks
```



Note

cURL option accepts certificates in PEM format only.

3. Restart the gateway:

```
cd $gateway bin/gateway.sh stop bin/gateway.sh start
```

4. After copying the certificate to a client, use the following command to verify:

```
curl --cacert $certificate_path -u $username : $password https://  
$gateway-hostname : $gateway_port /gateway/ $cluster_name /webhdfs/v1?op=  
GETHOMEDIRECTORY
```

4.16.2. CA-Signed Certificates for Production

For production deployments or any deployment in which a certificate authority issued certificate is needed, the following steps are required.

1. Import the desired certificate/key pair into a java keystore using keytool and ensure the following:
 - The certificate alias is `gateway-identity`.
 - The store password matches the master secret created earlier.
 - Note the key password used - as we need to create an alias for this password.

2. Add a password alias for the key password:

```
cd $gateway bin/knoxcli.cmd create-cert create-alias gateway-identity-  
passphrase --value $actualpassphrase
```



Note

The password alias must be `gateway-identity-passphrase`.

4.16.3. Setting Up Trust for the Knox Gateway Clients

In order for clients to trust the certificates presented to them by the gateway, they will need to be present in the client's truststore as follows:

1. Export the `gateway-identity` cert from the `$gateway/data/security/keystores/gateway.jks` using `java keytool` or another key management tool.
2. Add the exported certificate to the `cacerts` or other client specific truststore or the `gateway.jks` file can be copied to the clients to be used as the truststore.



Note

If taking this approach be sure to change the password of the copy so that it no longer matches the master secret used to protect server side artifacts.

4.17. Securing Phoenix

To configure Phoenix to run in a secure Hadoop cluster, use the instructions on [this page](#).

4.18. Set Up SSL for Ambari

If you want to limit access to the Ambari Server to HTTPS connections, you need to provide a certificate. While it is possible to use a self-signed certificate for initial trials, they are not suitable for production environments. After your certificate is in place, you must run a special setup command.

Ambari Server should not be running when you do this. Either make these changes before you start Ambari the first time, or bring the server down before running the setup command.

1. Log into the Ambari Server host.
2. Locate your certificate. If you want to create a temporary self-signed certificate, use this as an example:

```
openssl genrsa -out $wserver.key 2048  
  
openssl req -new -key $wserver.key -out $wserver.csr  
  
openssl x509 -req -days 365 -in $wserver.csr -signkey  
$wserver.key -out $wserver.crt
```

Where `$wserver` is the Ambari Server host name.

The certificate you use must be PEM-encoded, not DER-encoded. If you attempt to use a DER-encoded certificate, you see the following error:

```
unable to load certificate 140109766494024:error:0906D06C:PEM
routines:PEM_read_bio:no start line:pem_lib.c :698:Expecting:
TRUSTED CERTIFICATE
```

You can convert a DER-encoded certificate to a PEM-encoded certificate using the following command:

```
openssl x509 -in cert.crt -inform der -outform pem -out cert.pem
```

where `cert.crt` is the DER-encoded certificate and `cert.pem` is the resulting PEM-encoded certificate.

3. Run the special setup command and answer the prompts.

```
ambari-server setup-security
```

- Select 1 for Enable HTTPS for Ambari server.
- Respond y to Do you want to configure HTTPS ?
- Select the port you want to use for SSL. The default port number is 8443.
- Provide the complete path to your certificate file (`$wserver.crt` from above) and private key file (`$wserver.key` from above).
- Provide the password for the private key.
- Start or restart the Server

```
ambari-server restart
```

4. Trust Store Setup - If you plan to use Ambari Views with your Ambari Server, after enabling SSL for Ambari using the instructions below, you must also [set up a truststore for the Ambari server](#).

4.18.1. Set Up Truststore for Ambari Server

If you plan to [set up SSL for Ambari](#) or to enable wire encryption for HDP, you must configure the Truststore for Ambari and add certificates.

Ambari Server should not be running when you do this. Either make these changes before you start Ambari the first time, or bring the server down before running the setup command.

1. On the Ambari Server, create a new keystore that will contain the Ambari Server's HTTPS certificate.

```
keytool -import -file <path_to_the_Ambari_Server's_SSL_Certificate> -alias
ambari-server -keystore ambari-server-truststore
```

When prompted to 'Trust this certificate?' type "yes".

2. Configure the ambari-server to use this new trust store:

```
ambari-server setup-security
Using python /usr/bin/python2.6
Security setup options...
=====
Choose one of the following options:
  [1] Enable HTTPS for Ambari server.
  [2] Encrypt passwords stored in ambari.properties file.
  [3] Setup Ambari kerberos JAAS configuration.
  [4] Setup truststore.
  [5] Import certificate to truststore.
=====
Enter choice, (1-5): *4*
Do you want to configure a truststore [y/n] (y)? *y*
TrustStore type [jks/jceks/pkcs12] (jks): *jks*
Path to TrustStore file : *<path to the ambari-server-truststore keystore>*
Password for TrustStore:
Re-enter password:
Ambari Server 'setup-security' completed successfully.
```

3. Once configured, the Ambari Server must be restarted for the change to take effect.

```
ambari-server restart
```

4.19. Configure Ambari Ranger SSL

4.19.1. Configuring Ambari Ranger SSL Using Public CA Certificates

If you have access to Public CA issued certificates, use the following steps to configure Ambari Ranger SSL.

4.19.1.1. Prerequisites

- Copy the keystore/truststore files into a different location (e.g. /etc/security/serverKeys) than the /etc/<component>/conf folder.
- Make sure that the JKS file names are unique.
- Make sure that the correct permissions are applied.
- Make sure that passwords are secured.

4.19.1.2. Configuring Ranger Admin

1. Stop Ranger by selecting **Service Actions > Stop**.


The screenshot shows the Ambari interface for the 'test_cluster'. The 'Services' tab is selected, and the 'Ranger' service is highlighted in the left-hand navigation pane. The 'Summary' tab for Ranger is active, displaying a list of services and their statuses:

Service Name	Status
Ranger Admin	Started
Ranger Usersync	Started
Ranger HDFS plugin	Disabled
Ranger YARN plugin	Disabled
Ranger Hive plugin	Disabled
Ranger HBase plugin	Disabled
Ranger Storm plugin	Disabled
Ranger Knox plugin	Disabled
Ranger Kafka plugin	Disabled


The 'Service Actions' dropdown menu is open, showing the following options:

- Start
- Stop** (highlighted in red)
- Restart All
- Enable Ranger Admin HA
- Run Service Check
- Turn On Maintenance Mode

2. Use the following steps to disable the HTTP port and enable the HTTPS port with the required keystore information.
 - a. Select **Configs > Advanced**. Under Ranger Settings, clear the **HTTP enabled** check box (this blocks all agent calls to the HTTP port even if the port is up and working).



b. Under Ranger Settings, provide the value in the **External URL** box in the format `https://<hostname of policy manager>:<https port>`.



c. Under Advanced ranger-admin-site, set the following properties:

- `ranger.https.attrib.keystore.file` – Provide the location of the Public CA issued keystore file.
- `ranger.service.https.attrib.keystore.pass` – Enter the password for the keystore.
- `ranger.service.https.attrib.keystore.keyalias` – Enter the alias name for the keystore private key.
- `ranger.service.https.attrib.clientAuth` – Enter `want` as the value. This validates the client cert from all agents, but not the requests from web applications. Setting this value to `want` requires the client to have a certificate to use to sign traffic. If you do not want to put certificates on the client machines to do two-way SSL, this parameter can be set to `false` to enable one-way SSL.
- `ranger.service.https.attrib.ssl.enabled` – set this property to `true`.
- `ranger.service.https.port` – Make sure that this port is available, or change the value to an available port number.

Advanced ranger-admin-site

ranger.audit.source.type	<input type="text" value="solr"/>	🔒	🟢	ⓘ
ranger.credential.provider.path	<input type="text" value="/etc/ranger/admin/rangeradmin.jceks"/>	🔒	🟢	ⓘ
ranger.https.attrib.keystore.file	<input type="text" value="/etc/ranger/admin/conf/ranger-admin-keystore.jks"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.credential.alias	<input type="text" value="rangeraudit"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.dialect	<input type="text" value="{{jdbc_dialect}}"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.driver	<input type="text" value="{{ranger_jdbc_driver}}"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.password	<input type="password" value="....."/> <input type="password" value="....."/>	🔒		
ranger.jpa.audit.jdbc.url	<input type="text" value="{{audit_jdbc_url}}"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.user	<input type="text" value="{{ranger_audit_db_user}}"/>	🔒	🟢	ⓘ
ranger.jpa.jdbc.credential.alias	<input type="text" value="rangeradmin"/>	🔒	🟢	ⓘ
ranger.jpa.jdbc.dialect	<input type="text" value="{{jdbc_dialect}}"/>	🔒	🟢	ⓘ
ranger.jpa.jdbc.password	<input type="password" value="....."/> <input type="password" value="....."/>	🔒		
ranger.jpa.jdbc.user	<input type="text" value="{{ranger_db_user}}"/>	🔒	🟢	ⓘ
Group Search Base	<input type="text" value="{{ranger_ug_ldap_group_searchbase}}"/>	🔒	🟢	ⓘ
Group Search Filter	<input type="text" value="{{ranger_ug_ldap_group_searchfilter}}"/>	🔒	🟢	ⓘ
ranger.service.host	<input type="text" value="{{ranger_host}}"/>	🔒	🟢	ⓘ
ranger.service.http.port	<input type="text" value="6080"/>	🔒	🟢	ⓘ
ranger.service.https.attrib.clientAuth	<input type="text" value="want"/>	🔒	🟢	ⓘ
ranger.service.https.attrib.keystore.keyalias	<input type="text" value="rangeradmin"/>	🔒	🟢	ⓘ
ranger.service.https.attrib.keystore.pass	<input type="password" value="....."/> <input type="password" value="....."/>	🔒		
ranger.service.https.attrib.ssl.enabled	<input type="text" value="true"/>	🔒	🟢	🟡 ⓘ
ranger.service.https.port	<input type="text" value="6182"/>	🔒	🟢	ⓘ

3. Under Custom ranger-admin-site, add the following properties:

- `ranger.service.https.attrib.keystore.file` – Specify the same value provided for the `ranger.https.attrib.keystore.file` property.


- `ranger.service.https.attrib.client.auth` – Specify the same value provided for the `ranger.service.https.attrib.clientAuth` property.

To add a Custom `ranger-admin-site` property:

- a. Select **Custom `ranger-admin-site`**, then click **Add Property**.

The screenshot displays a configuration interface for Ranger. It features a list of settings sections: AD Settings, LDAP Settings, Advanced ranger-admin-site, Advanced ranger-env, Advanced ranger-ugsync-site, Custom admin-properties, Custom ranger-admin-site, Custom ranger-site, Custom ranger-ugsync-site, and Custom usersync-properties. The 'Custom ranger-admin-site' section is expanded, and the 'Add Property ...' button is highlighted with a red rectangle. The 'AD Settings' section shows two properties: 'ranger.ldap.ad.domain' with the value 'localhost' and 'ranger.ldap.ad.url' with the value 'ldap://ad.xasecure.net:389'. Each property has a lock icon and a refresh icon.

- b. On the Add Property pop-up, type the property name in the **Key** box, type the property value in the **Value** box, then click **Add**.



Add Property

Type: ranger-admin-site.xml

Key: ranger.service.https.attrib.keystore.file

Value: /etc/ranger/admin/conf/ranger-admin-keystore.jks

Cancel Add

4. Save your changes and start Ranger Admin.

When you attempt to access the Ranger Admin UI with the HTTPS protocol on the port specified by the `ranger.service.https.port` property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

4.19.1.3. Configuring Ranger Usersync

1. Stop Ranger Usersync by selecting the **Ranger Usersync** link, then select **Started > Stop** next to Ranger Usersync.

The screenshot shows the Ambari web interface for a cluster named 'test_cluster'. The top navigation bar includes 'Dashboard', 'Services', 'Hosts 1', 'Alerts', and 'Admin'. The main header shows the cluster name 'c6403.ambari.apache.org' and a '16 alerts' notification. Below the header, there are tabs for 'Summary', 'Configs', 'Alerts 16', and 'Versions'. The 'Components' section lists various services with their status (Stopped or Started) and a dropdown menu for each. The 'ResourceManager / YARN' component is highlighted with a red box, and its dropdown menu is open, showing options: 'Restart', 'Stop', and 'Turn On Maintenance Mode'. The 'Host Metrics' section on the right shows various metrics like CPU Usage, Disk Usage, Load, Memory Usage, Network Usage, and Processes, all with 'No Data Available' placeholders.

Component	Status
Accumulo GC / Accumulo	Stopped
Accumulo Master / Accumulo	Stopped
Accumulo Monitor / Accumulo	Stopped
Accumulo Tracer / Accumulo	Stopped
App Timeline Server / YARN	Started
Atlas Metadata Server / Atlas	Started
DRPC Server / Storm	Started
Falcon Server / Falcon	Stopped
HBase Master / HBase	Stopped
History Server / MapReduce2	Started
Hive Metastore / Hive	Started
HiveServer2 / Hive	Started
SmartSense HST Server / SmartSense	Stopped
Kafka Broker / Kafka	Started
Knox Gateway / Knox	Started
Metrics Collector / Ambari Metrics	Stopped
MySQL Server / Hive	Started
NameNode / HDFS	Started
Nimbus / Storm	Started
Oozie Server / Oozie	Started
Ranger Admin / Ranger	Started
Ranger Usersync / Ranger	Started
ResourceManager / YARN	Started
SNameNode / HDFS	Started
Spark History Server / Spark	Started
Storm UI Server / Storm	Started

2. Navigate back to Ranger and select **Configs > Advanced**, then click **Advanced ranger-ugsync-site**. Set the following properties:

- `ranger.usersync.truststore.file` – Enter the path to the truststore file.
- `ranger.usersync.truststore.password` – Enter the truststore password.



The screenshot shows a configuration interface with two rows of properties. The first row is for 'ranger.usersync.truststore.file' with a text input field containing '/usr/hdp/current/ranger-usersync/conf/mytruststore.jks'. To the right of the input field are three icons: a lock, a green plus sign, and a blue 'C' icon. The second row is for 'ranger.usersync.truststore.password' with two text input fields, both containing a series of dots to mask the password. A lock icon is positioned to the right of the second input field.

3. Start Ranger Usersync by selecting the **Ranger Usersync** link on the Summary tab, then select **Stopped > Start** next to Ranger Usersync.

4.19.1.4. Configuring Ranger Plugins for SSL

The following section shows how to configure the Ranger HDFS plugin for SSL. You can use the same procedure for other Ranger components. Additional steps required to configure the Ranger KMS plugin and server are provided in subsequent sections.

4.19.1.4.1. Configuring the Ranger HDFS Plugin for SSL

The following steps show how to configure the Ranger HDFS plugin for SSL. You can use the same procedure for other Ranger components.

1. Stop HDFS by selecting **Service Actions > Stop**.

The screenshot shows the Ambari interface for a cluster named 'test_cluster'. The 'Services' tab is active, displaying the HDFS service. The 'Service Actions' dropdown menu is open, with the 'Stop' option highlighted in a red box. The main content area shows the HDFS Summary, including NameNode and SNameNode status (both Started), DataNodes (1/1 Started), and various metrics like NameNode Uptime (21.82 days) and Disk Usage (0.17% DFS used, 7.84% Non DFS used). The Metrics section shows several 'No Data Available' warnings and one 'Under Replicated Blocks' warning with a value of 481.

2. Under Ranger Settings, provide the value in the **External URL** box in the format `https://<hostname of policy manager>:<https port>`.
3. Select **Advanced ranger-hdfs-policymgr-ssl** and set the following properties:
 - `xasecure.policymgr.clientssl.keystore` – Enter the public CA signed keystore for the machine that is running the HDFS agent.
 - `xasecure.policymgr.clientssl.keystore.password` – Enter the keystore password.

▼ **Advanced ranger-hdfs-policymgr-ssl**

xasecure.policymgr. clientsssl.keystore	<input type="text" value="/usr/hdp/current/hadoop-client/conf/ranger-plugin-keystore.jks"/>	+	C
xasecure.policymgr. clientsssl.keystore. credential.file	<input type="text" value="jceks://file{{credential_file}}"/>	+	C
xasecure.policymgr. clientsssl.keystore. password	<input type="password" value="....."/>		
xasecure.policymgr. clientsssl.truststore	<input type="text" value="/usr/hdp/current/hadoop-client/conf/ranger-plugin-truststore.jk"/>	+	C
xasecure.policymgr. clientsssl.truststore. credential.file	<input type="text" value="jceks://file{{credential_file}}"/>	+	C
xasecure.policymgr. clientsssl.truststore. password	<input type="password" value="....."/>		

- 4. Select **Advanced ranger-hdfs-plugin-properties**, then select the **Enable Ranger for HDFS** check box.

▼ **Advanced ranger-hdfs-plugin-properties**

Enable Ranger for HDFS

Ranger repository config password	<input type="password" value="....."/>	<input type="password" value="....."/>	lock icon
Ranger repository config user	<input type="text" value="hadoop"/>		lock icon + + C
common.name.for. certificate	<input type="text"/>		lock icon +
hadoop.rpc.protection	<input type="text"/>		lock icon +
Policy user for HDFS	<input type="text" value="ambari-qa"/>		lock icon + C

5. Click **Save** to save your changes.
6. Start HDFS by selecting **Service Actions > Start**.
7. Restart Ranger Admin.
8. Log into the Ranger Policy Manager UI as the admin user. Click the **Edit** button of the HDFS repository and provide the CN name of the keystore as the value for **Common Name For Certificate**, then save your changes.
9. Start the HDFS service.
10. Select **Audit > Agents**. You should see an entry for your repo name with HTTP Response Code 200.



Note

This procedure assumes that the keystores provided for the Admin and agent are signed by a public CA.

Provide an identifiable string as the value for Common Name when generating certificates. Important note: In the case where multiple servers talking to ranger admin for downloading policies for the same service/repository (e.g. HBase Master and Region servers, multiple NameNodes or Hive servers in an HA environment, be sure to use the repo name or a common string across all of the nodes (such as HbasePlugin, HdfsPlugin etc). (Note this and enter the same value in Common Name For Certificate field in the edit repository page in the Policy Manager UI).



Note

Ranger Admin will use the JAVA truststore, so you need to add your plugin certificate inside the Java truststore. Alternatively, you can specify a custom truststore by editing `/usr/hdp/2.3.2.0-2950/ranger-admin/ews/ranger-admin-services.sh`. You will need to add the following after the `JAVA_OPTS` line:

```
-Djavax.net.ssl.trustStore=/etc/security/ssl/truststore.jks  
-Djavax.net.ssl.trustStorePassword=hadoop
```

For example:

```
JAVA_OPTS=" ${JAVA_OPTS} -XX:MaxPermSize=256m -Xmx1024m -Xms1024m  
-Djavax.net.ssl.trustStore=/etc/security/ssl/truststore.jks  
-Djavax.net.ssl.trustStorePassword=hadoop"
```

4.19.1.4.2. Configuring the Ranger KMS Plugin for SSL

To configure the Ranger KMS (Key Management Service) plugin for SSL, use the procedure described in the previous section for HDFS, then perform the following additional step.

Log into the Policy Manager UI (as the keyadmin user) and click the **Edit** button of your KMS repository. Provide the CN name of the keystore as the value for Common Name For Certificate and save your changes. This property is not provided by default, so it must be added.

The screenshot shows the Ranger web interface for creating a service. The page has a green header with 'Ranger', 'Access Manager', and 'Encryption' tabs. Below the header, there are navigation buttons for 'Service Manager' and 'Edit Service'. The main content area is titled 'Create Service' and is divided into two sections: 'Service Details' and 'Config Properties'.

Service Details:

- Service Name *:
- Description:
- Active Status: Enabled Disabled

Config Properties:

- KMS URL *:
- Username *:
- Password *:

Below the password field, there is a section for 'Add New Configurations' with a table:

Name	Value
<input type="text" value="commonNameForCertificate"/>	<input type="text" value="ip-172-31-26-219.ec2.internal"/> <input type="button" value="x"/>

There is a '+' button below the table to add more configurations. At the bottom of the form, there is a 'Test Connection' button and three action buttons: 'Save' (green), 'Cancel' (black), and 'Delete' (red).

4.19.1.4.3. Configuring the Ranger KMS Server for SSL

Use the following steps to configure Ranger KMS (Key Management Service) Server for SSL.

1. Stop Ranger KMS by selecting **Service Actions > Stop**.
2. Select **Custom ranger-kms-site**, then add the following properties as shown below:
 - ranger.https.attrib.keystore.file
 - ranger.service.https.attrib.keystore.file (duplicate of above – workaround for now)
 - ranger.service.https.attrib.clientAuth
 - ranger.service.https.attrib.client.auth (duplicate of above – workaround for now)
 - ranger.service.https.attrib.keystore.keyalias
 - ranger.service.https.attrib.keystore.pass

ranger.service.https.attrib.ssl.enabled

ranger.service.https.port

▼ Custom ranger-kms-site

ranger.https.attrib.keystore.file	<input type="text" value="/etc/ranger/kms/conf/ranger-kms-keystore.jks"/>	+ -
ranger.service.https.attrib.client.auth	<input type="text" value="want"/>	+ -
ranger.service.https.attrib.clientAuth	<input type="text" value="false"/>	+ -
ranger.service.https.attrib.keystore.file	<input type="text" value="/etc/ranger/kms/conf/ranger-kms-keystore.jks"/>	+ -
ranger.service.https.attrib.keystore.keyalias	<input type="text" value="rangerkms"/>	+ -
ranger.service.https.attrib.keystore.pass	<input type="text" value="rangerkms"/>	+ -
ranger.service.https.attrib.ssl.enabled	<input type="text" value="true"/>	+ -
ranger.service.https.port	<input type="text" value="9393"/>	+ -

[Add Property ...](#)

3. Under Advanced kms_env, update the value of kms_port to match the value of ranger.service.https.port.
4. Save your changes and restart Ranger KMS.

When you attempt to access the Ranger KMS UI with the HTTPS protocol on the port specified by the ranger.service.https.port property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

4.19.2. Configuring Ambari Ranger SSL Using a Self-Signed Certificate

If you do not have access to Public CA issued certificates, use the following steps to create a self-signed certificate and configure Ambari Ranger SSL.

4.19.2.1. Prerequisites

- Copy the keystore/truststore files into a different location (e.g. /etc/security/serverKeys) than the /etc/<component>/conf folder.
- Make sure that the JKS file names are unique.

- Make sure that the correct permissions are applied.
- Make sure that passwords are secured.

4.19.2.2. Configuring Ranger Admin

1. Stop Ranger by selecting **Service Actions > Stop**.

The screenshot shows the Ambari interface for the 'test_cluster' environment. The 'Services' tab is active, and the 'Ranger' service is selected in the left-hand navigation pane. The 'Summary' tab for Ranger is displayed, showing the status of various plugins. The 'Ranger Admin' and 'Ranger Usersync' services are listed as 'Started'. A 'Service Actions' dropdown menu is open over the Ranger Admin service, with the 'Stop' option highlighted in red. Other options in the menu include 'Start', 'Restart All', 'Enable Ranger Admin HA', 'Run Service Check', and 'Turn On Maintenance Mode'.

2. Use the following CLI commands to change to the Ranger Admin directory and create a self-signed certificate.

```
cd /etc/ranger/admin/conf
keytool -genkey -keyalg RSA -alias rangeradmin -keystore ranger-admin-keystore.jks -storepass xasecure -validity 360 -keysize 2048
chown ranger:ranger ranger-admin-keystore.jks
chmod 400 ranger-admin-keystore.jks
```

When prompted, provide the host name as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore.




Note

When prompted for your password, press the Enter key. This will not work for Java keytool version 1.5.

3. Use the following steps to disable the HTTP port and enable the HTTPS port with the required keystore information.
 - a. Select **Configs > Advanced**. Under Ranger Settings, clear the **HTTP enabled** check box (this blocks all agent calls to the HTTP port even if the port is up and working).

The screenshot shows the Ambari web interface for configuring Ranger. The left sidebar lists various services, with 'Ranger' selected and marked with a red '3'. The main content area is titled 'Configs' and shows a list of configuration groups (V1-V4) for 'admin' on 'HDP-2.3'. A notification bar indicates a configuration change on Jan 28, 2016. Below this, the 'Advanced' tab is selected under 'Ranger Settings'. The 'Admin Settings' section includes fields for 'Ranger Admin host', 'Ranger Admin username for Ambari' (set to 'amb_ranger_admin'), 'Ranger Admin user's password for Ambari', and 'Location of Sql Connector Jar'. The 'Ranger Settings' section includes 'External URL' (set to 'https://c6403.ambari.apache.org:8182') and 'Authentication method' (set to 'LDAP'). At the bottom of the 'Ranger Settings' section, the 'HTTP enabled' checkbox is checked and highlighted with a red rectangular box.

- b. Under Ranger Settings, provide the value in the **External URL** box in the format `https://<hostname of policy manager>:<https port>`.



c. Under Advanced ranger-admin-site, set the following properties:

- `ranger.https.attrib.keystore.file` – Provide the location of the keystore file created previously: `/etc/ranger/admin/conf/ranger-admin-keystore.jks`.
- `ranger.service.https.attrib.keystore.pass` – Enter the password for the keystore (in this case, `xasecure`).
- `ranger.service.https.attrib.keystore.keyalias` – Enter the alias name for the keystore private key (in this case, `rangeradmin`).
- `ranger.service.https.attrib.clientAuth` – Enter `want` as the value. This validates the client cert from all agents, but not the requests from web applications. Setting this value to `want` requires the client to have a certificate to use to sign traffic. If you do not want to put certificates on the client machines to do two-way SSL, this parameter can be set to `false` to enable one-way SSL.
- `ranger.service.https.attrib.ssl.enabled` – set this property to `true`.
- `ranger.service.https.port` – Make sure that this port is available, or change the value to an available port number.

Advanced ranger-admin-site

ranger.audit.source.type	<input type="text" value="solr"/>	🔒	🟢	ⓘ
ranger.credential.provider.path	<input type="text" value="/etc/ranger/admin/rangeradmin.jceks"/>	🔒	🟢	ⓘ
ranger.https.attrib.keystore.file	<input type="text" value="/etc/ranger/admin/conf/ranger-admin-keystore.jks"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.credential.alias	<input type="text" value="rangeraudit"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.dialect	<input type="text" value="{{jdbc_dialect}}"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.driver	<input type="text" value="{{ranger_jdbc_driver}}"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.password	<input type="password" value="....."/> <input type="password" value="....."/>	🔒		
ranger.jpa.audit.jdbc.url	<input type="text" value="{{audit_jdbc_url}}"/>	🔒	🟢	ⓘ
ranger.jpa.audit.jdbc.user	<input type="text" value="{{ranger_audit_db_user}}"/>	🔒	🟢	ⓘ
ranger.jpa.jdbc.credential.alias	<input type="text" value="rangeradmin"/>	🔒	🟢	ⓘ
ranger.jpa.jdbc.dialect	<input type="text" value="{{jdbc_dialect}}"/>	🔒	🟢	ⓘ
ranger.jpa.jdbc.password	<input type="password" value="....."/> <input type="password" value="....."/>	🔒		
ranger.jpa.jdbc.user	<input type="text" value="{{ranger_db_user}}"/>	🔒	🟢	ⓘ
Group Search Base	<input type="text" value="{{ranger_ug_ldap_group_searchbase}}"/>	🔒	🟢	ⓘ
Group Search Filter	<input type="text" value="{{ranger_ug_ldap_group_searchfilter}}"/>	🔒	🟢	ⓘ
ranger.service.host	<input type="text" value="{{ranger_host}}"/>	🔒	🟢	ⓘ
ranger.service.http.port	<input type="text" value="6080"/>	🔒	🟢	ⓘ
ranger.service.https.attrib.clientAuth	<input type="text" value="want"/>	🔒	🟢	ⓘ
ranger.service.https.attrib.keystore.keyalias	<input type="text" value="rangeradmin"/>	🔒	🟢	ⓘ
ranger.service.https.attrib.keystore.pass	<input type="password" value="....."/> <input type="password" value="....."/>	🔒		
ranger.service.https.attrib.ssl.enabled	<input type="text" value="true"/>	🔒	🟢	🟡 ⓘ
ranger.service.https.port	<input type="text" value="6182"/>	🔒	🟢	ⓘ

4. Under Custom ranger-admin-site, add the following properties:

- `ranger.service.https.attrib.keystore.file` – Specify the same value provided for the `ranger.https.attrib.keystore.file` property.


- `ranger.service.https.attrib.client.auth` – Specify the same value provided for the `ranger.service.https.attrib.clientAuth` property.

To add a Custom `ranger-admin-site` property:

- a. Select **Custom `ranger-admin-site`**, then click **Add Property**.

The screenshot displays the Ranger configuration interface. At the top, the 'AD Settings' section is expanded, showing two properties: 'ranger.ldap.ad.domain' with the value 'localhost' and 'ranger.ldap.ad.url' with the value 'ldap://ad.xasecure.net:389'. Below this, several other configuration sections are listed with expandable arrows: 'LDAP Settings', 'Advanced ranger-admin-site', 'Advanced ranger-env', 'Advanced ranger-ugsync-site', 'Custom admin-properties', 'Custom ranger-admin-site', 'Custom ranger-site', 'Custom ranger-ugsync-site', and 'Custom usersync-properties'. The 'Custom ranger-admin-site' section is expanded, and the 'Add Property ...' button is highlighted with a red rectangular box.

- b. On the Add Property pop-up, type the property name in the **Key** box, type the property value in the **Value** box, then click **Add**.



Add Property

Type: ranger-admin-site.xml

Key: ranger.service.https.attrib.keystore.file

Value: /etc/ranger/admin/conf/ranger-admin-keystore.jks

Cancel Add

5. Save your changes and start Ranger Admin.

When you attempt to access the Ranger Admin UI with the HTTPS protocol on the port specified by the `ranger.service.https.port` property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

4.19.2.3. Configuring Ranger Usersync

1. Stop Ranger Usersync by selecting the **Ranger Usersync** link, then select **Started > Stop** next to Ranger Usersync.

The screenshot shows the Ambari web interface for a cluster named 'test_cluster'. At the top, there are navigation tabs for 'Dashboard', 'Services', 'Hosts', 'Alerts', and 'Admin'. The 'Alerts' tab is active, showing '16 alerts'. Below the navigation, the page title is 'c6403.ambari.apache.org' with a 'Back' link. There are tabs for 'Summary', 'Configs', 'Alerts', and 'Versions'. The 'Alerts' tab is selected, and a 'Host Actions' dropdown is visible in the top right.

The main content area is divided into two panels. The left panel, titled 'Components', lists various services and their status. The right panel, titled 'Host Metrics', shows various performance metrics.

Component	Status
Accumulo GC / Accumulo	Stopped
Accumulo Master / Accumulo	Stopped
Accumulo Monitor / Accumulo	Stopped
Accumulo Tracer / Accumulo	Stopped
App Timeline Server / YARN	Started
Atlas Metadata Server / Atlas	Started
DRPC Server / Storm	Started
Falcon Server / Falcon	Stopped
HBase Master / HBase	Stopped
History Server / MapReduce2	Started
Hive Metastore / Hive	Started
HiveServer2 / Hive	Started
SmartSense HST Server / SmartSense	Stopped
Kafka Broker / Kafka	Started
Knox Gateway / Knox	Started
Metrics Collector / Ambari Metrics	Stopped
MySQL Server / Hive	Started
NameNode / HDFS	Started
Nimbus / Storm	Started
Oozie Server / Oozie	Started
Ranger Admin / Ranger	Started
Ranger Usersync / Ranger	Started
ResourceManager / YARN	Started
SNameNode / HDFS	Started
Spark History Server / Spark	Started
Storm UI Server / Storm	Started

The 'ResourceManager / YARN' component is highlighted with a red box, and its dropdown menu is open, showing the following options:

- Restart
- Stop
- Turn On Maintenance Mode

2. Check to see if `unixauthservice.jks` is in the `/etc/ranger/usersync/conf/` directory. If not, run the following commands in the CLI:

```
cd /etc/ranger/usersync/conf/
mkdir cert
keytool -genkeypair -keyalg RSA -alias selfsigned -keystore /etc/ranger/
usersync/conf/cert/unixauthservice.jks -keypass UnIx529p -storepass UnIx529p
-validity 3600 -keysize 2048 -dname 'cn=unixauthservice,ou=authenticator,o=
mycompany,c=US'
chown -R ranger:ranger /etc/ranger/usersync/conf/cert
chmod -R 400 /etc/ranger/usersync/conf/cert
```

3. Use the following CLI commands to create a truststore for the Ranger Admin's self-signed keystore. When prompted for a password, press the Enter key.

```
cd /etc/ranger/usersync/conf/
keytool -export -keystore /etc/ranger/admin/conf/ranger-admin-keystore.jks -
alias rangeradmin -file ranger-admin-trust.cerchown -R ranger:ranger /etc/
ranger/usersync/conf/cert
keytool -import -file ranger-admin-trust.cer -alias rangeradmintrust -
keystore mytruststore.jks -storepass changeit
chown ranger:ranger mytruststore.jks
```

4. Navigate back to Ranger and select **Configs > Advanced**, then click **Advanced ranger-usersync-site**. Set the following properties:

- `ranger.usersync.truststore.file` – Enter the path to the truststore file.
- `ranger.usersync.truststore.password` – Enter the truststore password.

The screenshot shows a configuration interface with two rows of properties:

- The first row is labeled `ranger.usersync.truststore.file` and has a text input field containing the path `/usr/hdp/current/ranger-usersync/conf/mytruststore.jks`. To the right of the input field are three small icons: a lock, a green plus sign, and a blue refresh icon.
- The second row is labeled `ranger.usersync.truststore.password` and has two text input fields, both of which are filled with dots to indicate that the password is masked. A lock icon is visible to the right of the second input field.

5. Start Ranger Usersync by selecting the **Ranger Usersync** link on the Summary tab, then select **Stopped > Start** next to Ranger Usersync.

4.19.2.4. Configuring Ranger Plugins

The following section shows how to configure the Ranger HDFS plugin for SSL with a self-signed certificate. You can use the same procedure for other Ranger components. Additional steps required to configure the Ranger KMS plugin and server are provided in subsequent sections.



Note

- To ensure a successful connection after SSL is enabled, self-signed certificates should be imported to the Ranger Admin's trust store (typically `JDK cacerts`).
- The `ranger.plugin.<service>.policy.rest.ssl.config.file` property should be verified, for example:

```
ranger.plugin.hive.policy.rest.ssl.config.file ==> /etc/
hive/conf/conf.server/ranger-policymgr-ssl.xml
```

4.19.2.4.1. Configuring the Ranger HDFS Plugin for SSL

The following steps show how to configure the Ranger HDFS plugin for SSL. You can use the same procedure for other Ranger components.

1. Stop HDFS by selecting **Service Actions > Stop**.

The screenshot displays the Ambari interface for the HDFS service. The top navigation bar includes 'Ambari test_cluster', '0 ops', '13 alerts', and navigation tabs for 'Dashboard', 'Services', 'Hosts', 'Alerts', and 'Admin'. The left sidebar lists various services, with HDFS selected. The main content area is divided into 'Summary', 'Heatmaps', 'Configs', and 'Quick Links'. The 'Summary' section shows the status of NameNode (Started), SNameNode (Started), and DataNodes (1/1 Started). Below this, there are metrics for NameNode Uptime, NameNode Heap, and Disk Usage. The 'Metrics' section at the bottom displays various performance indicators, including NameNode GC count, NameNode GC time, NN Connection Load, NameNode Heap, NameNode Host Load, NameNode RPC, Failed disk volumes, Corrupted Blocks, Under Replicated Blocks, and HDFS Space Utilization. The 'Under Replicated Blocks' metric is highlighted in red with the value 481.

2. Use the following CLI commands to change to the Ranger HDFS plugin directory and create a self-signed certificate.

```
cd /etc/hadoop/conf
keytool -genkey -keyalg RSA -alias rangerHdfsAgent -keystore ranger-plugin-
keystore.jks -storepass myKeyFilePassword -validity 360 -keysize 2048
chown hdfs:hdfs ranger-plugin-keystore.jks
chmod 400 ranger-plugin-keystore.jks
```

When prompted, provide an identifiable string as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore. When prompted for a password, press the Enter key.



Note

Important note: In the case where multiple servers talking to ranger admin for downloading policies for the same service/repository (e.g. HBase Master and Region servers, multiple NameNodes or Hive servers in an HA environment, be sure to use the repo name or a common string across all of the nodes (such as HbasePlugin, HdfsPlugin etc). (Note this and enter the same value in Common Name For Certificate field in the edit repository page in the Policy Manager UI).

3. Use the following CLI commands to create a truststore for the agent and add the Admin public key as a trusted entry. When prompted for a password, press the Enter key.

```
cd /etc/hadoop/conf
keytool -export -keystore /etc/ranger/admin/conf/ranger-admin-keystore.jks -
alias rangeradmin -file ranger-admin-trust.cer
keytool -import -file ranger-admin-trust.cer -alias rangeradmintrust -
keystore ranger-plugin-truststore.jks -storepass changeit
chown hdfs:hdfs ranger-plugin-truststore.jks
chmod 400 ranger-plugin-truststore.jks
```

4. Under Ranger Settings, provide the value in the **External URL** box in the format `https://<hostname of policy manager>:<https port>`.
5. Select **Advanced ranger-hdfs-policymgr-ssl** and set the following properties:
 - `xasecure.policymgr.clientssl.keystore` – Enter the location of the keystore created in the previous step.
 - `xasecure.policymgr.clientssl.keystore.password` – Enter the keystore password.
 - `xasecure.policymgr.clientssl.truststore` – Enter the location of the truststore created in the previous step.
 - `xasecure.policymgr.clientssl.truststore.password` – Enter the truststore password.

Advanced ranger-hdfs-policymgr-ssl

xasecure.policymgr. clientssl.keystore	<input type="text" value="/etc/hadoop/conf/ranger-plugin-keystore.jks"/>			
xasecure.policymgr. clientssl.keystore. credential.file	<input type="text" value="jceks://file{{credential_file}}"/>			
xasecure.policymgr. clientssl.keystore. password	<input type="password"/>	<input type="password"/>		
xasecure.policymgr. clientssl.truststore	<input type="text" value="/etc/hadoop/conf/ranger-plugin-truststore.jks"/>			
xasecure.policymgr. clientssl.truststore. credential.file	<input type="text" value="jceks://file{{credential_file}}"/>			
xasecure.policymgr. clientssl.truststore. password	<input type="password"/>	<input type="password"/>		

- 6. Select **Advanced ranger-hdfs-plugin-properties**, then select the **Enable Ranger for HDFS** check box.

Advanced ranger-hdfs-plugin-properties

Enable Ranger for HDFS	<input checked="" type="checkbox"/>			
Ranger repository config password	<input type="password"/>	<input type="password"/>		
Ranger repository config user	<input type="text" value="hadoop"/>			
common.name.for. certificate	<input type="text"/>			
hadoop.rpc.protection	<input type="text"/>			
Policy user for HDFS	<input type="text" value="ambari-qa"/>			

7. Click **Save** to save your changes.
8. Start HDFS by selecting **Service Actions > Start**.
9. Stop Ranger Admin by selecting **Service Actions > Stop**.
10. Use the following CLI commands to add the agent's self-signed cert to the Admin's trustedCACerts.

```
cd /etc/ranger/admin/conf
keytool -export -keystore /etc/hadoop/conf/ranger-plugin-keystore.jks
        -alias rangerHdfsAgent -file ranger-hdfsAgent-trust.cer -storepass
        myKeyFilePassword
keytool -import -file ranger-hdfsAgent-trust.cer -alias rangerHdfsAgentTrust
        -keystore <Truststore file used by Ranger Admin - can be the JDK cacerts> -
        storepass changeit
```

11. Restart Ranger Admin.
12. Log into the Ranger Policy Manager UI as the admin user. Click the **Edit** button of your repository (in this case, hadoopdev) and provide the CN name of the keystore as the value for **Common Name For Certificate**, then save your changes.
13. Start the HDFS service.
14. In the Policy Manager UI, select **Audit > Plugins**. You should see an entry for your repo name with HTTP Response Code 200.

4.19.2.4.2. Configuring the Ranger KMS Plugin for SSL

To configure the Ranger KMS (Key Management Service) plugin for SSL, use the procedure described in the previous section for HDFS, then perform the following additional step.

Log into the Policy Manager UI (as the keyadmin user) and click the **Edit** button of your KMS repository. Provide the CN name of the keystore as the value for Common Name For Certificate and save your changes. This property is not provided by default, so it must be added.

Ranger Access Manager Encryption

Service Manager > Edit Service

Create Service

Service Details :

Service Name *

Description

Active Status Enabled Disabled

Config Properties :

KMS URL *

Username *

Password *

Add New Configurations

Name	Value
<input type="text" value="commonNameForCertificate"/>	<input type="text" value="ip-172-31-26-219.ec2.internal"/> <input type="button" value="x"/>

4.19.2.4.3. Configuring the Ranger KMS Server for SSL

Use the following steps to configure Ranger KMS (Key Management Service) Server for SSL.

1. Stop Ranger KMS by selecting **Service Actions > Stop**.
2. Use the following CLI commands to change to the Ranger KMS configuration directory and create a self-signed certificate.

```
cd /etc/ranger/kms/conf
keytool -genkey -keyalg RSA -alias rangerkms -keystore ranger-kms-keystore.
jks -storepass rangerkms -validity 360 -keysize 2048
chown kms:kms ranger-kms-keystore.jks
chmod 400 ranger-kms-keystore.jks
```

When prompted, provide an identifiable string as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore. When prompted for a password, press the Enter key.

3. Select **Custom ranger-kms-site**, then add the following properties as shown below:

ranger.https.attrib.keystore.file

ranger.service.https.attrib.keystore.file (duplicate of above – workaround for now)

ranger.service.https.attrib.clientAuth

ranger.service.https.attrib.client.auth (duplicate of above – workaround for now)

ranger.service.https.attrib.keystore.keyalias

ranger.service.https.attrib.keystore.pass

ranger.service.https.attrib.ssl.enabled

ranger.service.https.port

Custom ranger-kms-site		
ranger.https.attrib.keystore.file	<input type="text" value="/etc/ranger/kms/conf/ranger-kms-keystore.jks"/>	+ -
ranger.service.https.attrib.client.auth	<input type="text" value="want"/>	+ -
ranger.service.https.attrib.clientAuth	<input type="text" value="false"/>	+ -
ranger.service.https.attrib.keystore.file	<input type="text" value="/etc/ranger/kms/conf/ranger-kms-keystore.jks"/>	+ -
ranger.service.https.attrib.keystore.keyalias	<input type="text" value="rangerkms"/>	+ -
ranger.service.https.attrib.keystore.pass	<input type="text" value="rangerkms"/>	+ -
ranger.service.https.attrib.ssl.enabled	<input type="text" value="true"/>	+ -
ranger.service.https.port	<input type="text" value="9393"/>	+ -
Add Property ...		

4. Under Advanced kms_env, update the value of kms_port to match the value of ranger.service.https.port.
5. Save your changes and restart Ranger KMS.

When you attempt to access the Ranger KMS UI with the HTTPS protocol on the port specified by the ranger.service.https.port property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

6. Use the following CLI commands to export the Ranger KMS certificate.

```
cd /usr/hdp/<version>/ranger-kms/conf
keytool -export -keystore ranger-kms-keystore.jks -alias rangerkms -file
ranger-kms-trust.cer
```

7. Use the following CLI command to import the Ranger KMS certificate into the Ranger Admin truststore.

```
keytool -import -file ranger-kms-trust.cer -alias rangerkms -keystore
<Truststore file used by Ranger Admin - can be the JDK cacerts> -storepass
changeit
```

8. Use the following CLI command to import the Ranger KMS certificate into the Hadoop client truststore.

```
keytool -import -file ranger-kms-trust.cer -alias rangerkms -keystore /etc/
security/clientKeys/all.jks -storepass bigdata
```

9. Restart Ranger Admin and HDFS.

4.20. Configure Non-Ambari Ranger SSL

4.20.1. Configuring Non-Ambari Ranger SSL Using Public CA Certificates

If you have access to Public CA issued certificates, use the following steps to configure non-Ambari Ranger SSL.

4.20.1.1. Configuring Ranger Admin

1. Use the following CLI command to stop Ranger Admin.

```
ranger-admin stop
```

2. Open the `ranger-admin-site.xml` file in a text editor.

```
vi /usr/hdp/current/ranger-admin/ews/webapp/WEB-INF/classes/conf/ranger-
admin-site.xml
```

3. Update `ranger-admin-site.xml` as follows:

- `ranger.service.http.port` – Comment out the value for this property.
- `ranger.service.http.enabled` – Set the value of this property to `false`.
- `ranger.service.https.attrib.ssl.enabled` – Set the value of this property to `true`.
- `ranger.service.https.port` – Make sure that this port is available, or change the value to an available port number.
- `ranger.https.attrib.keystore.file` – Provide the location of the Public CA issued keystore file.

- `ranger.service.https.attrib.keystore.pass` – Enter the password for the keystore.
- `ranger.service.https.attrib.keystore.keyalias` – Enter the alias name for the keystore private key.
- `ranger.externalurl` – Set the value of this property in the format: `https://<hostname of policy manager>:<https port>`.
- Add or update the following properties with the values shown below:

```
<property>
  <name>ranger.service.https.attrib.clientAuth</name>
  <value>want</value>
</property>

<property>
  <name>ranger.service.https.attrib.client.auth</name>
  <value>want</value>
</property>

<property>
  <name>ranger.https.attrib.keystore.file</name>
  <value>/etc/ranger/admin/conf/ranger-admin-keystore.jks</value>
</property>

<property>
  <name>ranger.service.https.attrib.keystore.file</name>
  <value>/etc/ranger/admin/conf/ranger-admin-keystore.jks</value>
</property>
```

4. Save the changes to `ranger-admin-site.xml`, then use the following command to start Ranger Admin.

```
ranger-admin start
```

When you attempt to access the Ranger Admin UI with the HTTPS protocol on the port specified by the `ranger.service.https.port` property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

4.20.1.2. Configuring Ranger Usersync

1. Use the following CLI command to stop the Ranger Usersync service.

```
ranger-usersync stop
```

2. Use the following commands to change to the Usersync install directory and open the `install.properties` file in a text editor.

```
cd /usr/hdp/current/ranger-usersync/
vi install.properties
```

3. Set the value of `POLICY_MGR_URL` in the format: `https://<hostname of policy manager>:<https port>` and save your changes.
4. Run the following commands to install the new settings.

```
cd /usr/hdp/current/ranger-usersync/  
./setup.sh
```

5. Use the following command to start the Ranger Usersync service.

```
ranger-usersync start
```

4.20.1.3. Configuring Ranger Plugins

This section shows how to configure the Ranger HDFS plugin for SSL. You can use the same procedure for other Ranger components.

1. Use the following CLI command to stop the NameNode.

```
su -l hdfs -c "/usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh stop  
namenode"
```

2. Open the HDFS `install.properties` file in a text editor.

```
vi /usr/hdp/<version>/ranger-hdfs-plugin/install.properties
```

3. Update `install.properties` as follows:

- `POLICY_MGR_URL` – Set this value in the format: `https://<hostname of policy manager>:<https port>`
 - `SSL_KEYSTORE_FILE_PATH` – The path to the location of the Public CA issued keystore file.
 - `SSL_KEYSTORE_PASSWORD` – The keystore password.
 - `SSL_TRUSTSTORE_FILE_PATH` – The truststore file path.
 - `SSL_TRUSTSTORE_PASSWORD` – The truststore password.
- Save the changes to the `install.properties` file.

4. Use the following command to see if `JAVA_HOME` is available.

```
echo $JAVA_HOME
```

5. If `JAVA_HOME` is not available, use the following command to set `JAVA_HOME` (Note that Ranger requires Java 1.7).

```
export JAVA_HOME=<path for java 1.7>
```

6. Run the following commands to switch to the HDFS plugin install directory and run the `install agent` to update the plugin with the new configuration settings.

```
cd /usr/hdp/<version>/ranger-hdfs-plugin/  
./enable-hdfs-plugin.sh
```

7. Log into the Ranger Policy Manager UI as the admin user. Click the **Edit** button of your repository (in this case, `hadoopdev`) and provide the CN name of the keystore as the value for **Common Name For Certificate**, then save your changes.

8. Use the following command to start the NameNode.

```
su -l hdfs -c "/usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh start namenode"
```

9. In the Policy Manager UI, select **Audit > Plugins**. You should see an entry for your repo name with HTTP Response Code 200.

4.20.2. Configuring Non-Ambari Ranger SSL Using a Self Signed Certificate

If you do not have access to Public CA issued certificates, use the following steps to create a self-signed certificate and configure Non-Ambari Ranger SSL.

4.20.2.1. Configuring Ranger Admin

1. Use the following CLI command to stop Ranger Admin.

```
ranger-admin stop
```

2. Use the following commands to change to the Ranger Admin directory and create a self-signed certificate.

```
cd /etc/ranger/admin/conf
keytool -genkey -keyalg RSA -alias rangeradmin -keystore ranger-admin-keystore.jks -storepass xasecure -validity 360 -keysize 2048
chown ranger:ranger ranger-admin-keystore.jks
chmod 400 ranger-admin-keystore.jks
```

When prompted, provide the host name as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore.



Note

When prompted for your password, press the Enter key. This will not work for Java keytool version 1.5.

3. Open the `ranger-admin-site.xml` file in a text editor.

```
vi /usr/hdp/current/ranger-admin/ews/webapp/WEB-INF/classes/conf/ranger-admin-site.xml
```

4. Update `ranger-admin-site.xml` as follows:

- `ranger.service.http.port` – Comment out the value for this property.
- `ranger.service.http.enabled` – Set the value of this property to `false`.
- `ranger.service.https.attrib.ssl.enabled` – Set the value of this property to `true`.
- `ranger.service.https.port` – Make sure that this port is available, or change the value to an available port number.

- `ranger.https.attrib.keystore.file` – Provide the location of the keystore file created previously: `/etc/ranger/admin/conf/ranger-admin-keystore.jks`.
- `ranger.service.https.attrib.keystore.pass` – Enter the password for the keystore (in this case, `xasecure`).
- `ranger.service.https.attrib.keystore.keyalias` – Enter the alias name for the keystore private key (in this case, `rangeradmin`).
- `ranger.externalurl` – Set the value of this property in the format: `https://<hostname of policy manager>:<https port>`.
- Add or update the following properties with the values shown below:

```
<property>
  <name>ranger.service.https.attrib.clientAuth</name>
  <value>want</value>
</property>

<property>
  <name>ranger.service.https.attrib.client.auth</name>
  <value>want</value>
</property>

<property>
  <name>ranger.https.attrib.keystore.file</name>
  <value>/etc/ranger/admin/conf/ranger-admin-keystore.jks</value>
</property>

<property>
  <name>ranger.service.https.attrib.keystore.file</name>
  <value>/etc/ranger/admin/conf/ranger-admin-keystore.jks</value>
</property>
```

5. Save the changes to `ranger-admin-site.xml`, then use the following command to start Ranger Admin.

```
ranger-admin start
```

When you attempt to access the Ranger Admin UI with the HTTPS protocol on the port specified by the `ranger.service.https.port` property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS with the self-signed cert you just created.

4.20.2.2. Configuring Ranger Usersync

1. Use the following CLI command to stop the Ranger Usersync service.

```
ranger-usersync stop
```

2. Check to see if `unixauthservice.jks` is in the `/etc/ranger/usersync/conf/` directory. If not, run the following commands in the CLI:

```
cd /etc/ranger/usersync/conf/
mkdir cert
keytool -genkeypair -keyalg RSA -alias selfsigned -keystore /etc/ranger/
usersync/conf/cert/unixauthservice.jks -keypass UnIx529p -storepass UnIx529p
-validity 3600 -keysize 2048 -dname 'cn=unixauthservice,ou=authenticator,o=
mycompany,c=US'
chown -R ranger:ranger /etc/ranger/usersync/conf/cert
chmod -R 400 /etc/ranger/usersync/conf/cert
```

3. Use the following commands to change to the Usersync install directory and open the `install.properties` file in a text editor.

```
cd /usr/hdp/current/ranger-usersync/
vi install.properties
```

4. Set the value of `POLICY_MGR_URL` in the format: `https://<hostname of policy manager>:<https port>` and save your changes.
5. Use the following commands to create a truststore for the Ranger Admin's self-signed keystore. When prompted for a password, press the Enter key.

```
cd /etc/ranger/usersync/conf/
keytool -export -keystore /etc/ranger/admin/conf/ranger-admin-keystore.jks -
alias rangeradmin -file ranger-admin-trust.cerchown -R ranger:ranger /etc/
ranger/usersync/conf/cert
keytool -import -file ranger-admin-trust.cer -alias rangeradmintrust -
keystore mytruststore.jks -storepass changeit
chown ranger:ranger mytruststore.jks
```

6. Use the following commands to change to the Usersync conf directory and open the `ranger-ugsync-site.xml` file in a text editor.

```
cd /usr/hdp/current/ranger-usersync/conf/
vi ranger-ugsync-site.xml
```

Edit the following properties, then save your changes:

- `ranger.usersync.truststore.file` – Enter the path to the truststore file.
- `ranger.usersync.truststore.password` – Enter the truststore password.

7. Run the following commands to install the new settings.

```
cd /usr/hdp/current/ranger-usersync/
./setup.sh
```

8. Use the following command to start the Ranger Usersync service.

```
ranger-usersync start
```

4.20.2.3. Configuring Ranger Plugins

The following steps describe how to configure the Ranger HDFS plugin for SSL with a self-signed certificate in a non-Ambari cluster. You can use the same procedure for other Ranger components.

1. Use the following CLI command to stop the NameNode.


```
su -l hdfs -c "/usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh stop
namenode"
```

2. Use the following commands to change to the Ranger HDFS plugin directory and create a self-signed certificate.

```
3. cd /etc/hadoop/conf
keytool -genkey -keyalg RSA -alias rangerHdfsAgent -keystore ranger-plugin-
keystore.jks -storepass myKeyFilePassword -validity 360 -keysize 2048
chown hdfs:hdfs ranger-plugin-keystore.jks
chmod 400 ranger-plugin-keystore.jks
```

When prompted, provide an identifiable string as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore. When prompted for a password, press the Enter key.



Note

Important note: In the case where multiple servers talking to ranger admin for downloading policies for the same service/repository (e.g. HBase Master and Region servers, multiple NameNodes or Hive servers in an HA environment, be sure to use the repo name or a common string across all of the nodes (such as HbasePlugin, HdfsPlugin etc). (Note this and enter the same value in Common Name For Certificate field in the edit repository page in the Policy Manager UI).

4. Use the following CLI commands to create a truststore for the agent and add the Admin public key as a trusted entry. When prompted for a password, press the Enter key.

```
cd /etc/hadoop/conf
keytool -export -keystore /etc/ranger/admin/conf/ranger-admin-keystore.jks -
alias rangeradmin -file ranger-admin-trust.cer
keytool -import -file ranger-admin-trust.cer -alias rangeradmintrust -
keystore ranger-plugin-truststore.jks -storepass changeit
chown hdfs:hdfs ranger-plugin-truststore.jks
chmod 400 ranger-plugin-truststore.jks
```

5. Open the HDFS `install.properties` file in a text editor.

```
vi /usr/hdp/<version>/ranger-hdfs-plugin/install.properties
```

6. Update `install.properties` as follows:

- `POLICY_MGR_URL` – Set this value in the format: `https://<hostname of policy manager>:<https port>`
 - `SSL_KEYSTORE_FILE_PATH` – The path to the location of the keystore file.
 - `SSL_KEYSTORE_PASSWORD` – The keystore password.
 - `SSL_TRUSTSTORE_FILE_PATH` – The truststore file path.
 - `SSL_TRUSTSTORE_PASSWORD` – The truststore password.
- Save the changes to the `install.properties` file.

7. Use the following command to see if `JAVA_HOME` is available.

```
echo $JAVA_HOME
```

8. If `JAVA_HOME` is not available, use the following command to set `JAVA_HOME` (Note that Ranger requires Java 1.7).

```
export JAVA_HOME=<path for java 1.7>
```

9. Run the following commands to switch to the HDFS plugin install directory and run the install agent to update the plugin with the new configuration settings.

```
cd /usr/hdp/<version>/ranger-hdfs-plugin/  
./enable-hdfs-plugin.sh
```

10. Use the following command to stop Ranger Admin.

```
ranger-admin stop
```

11. Use the following commands to add the agent's self-signed cert to the Admin's trustedCACerts.

```
cd /etc/ranger/admin/conf  
keytool -export -keystore /etc/hadoop/conf/ranger-plugin-keystore.jks  
-alias rangerHdfsAgent -file ranger-hdfsAgent-trust.cer -storepass  
myKeyFilePassword  
keytool -import -file ranger-hdfsAgent-trust.cer -alias rangerHdfsAgentTrust  
-keystore <Truststore file used by Ranger Admin - can be the JDK cacerts> -  
storepass changeit
```

12. Use the following command to start Ranger Admin.

```
ranger-admin start
```

13. Log into the Ranger Policy Manager UI as the admin user. Click the **Edit** button of your repository (in this case, `hadoopdev`) and provide the CN name of the keystore as the value for **Common Name For Certificate**, then save your changes.

14. Use the following command to start the NameNode.

```
su -l hdfs -c "/usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh start  
namenode"
```

15. In the Policy Manager UI, select **Audit > Plugins**. You should see an entry for your repository name with HTTP Response Code 200.

4.21. Connecting to SSL-Enabled Components

This section explains how to connect to SSL enabled HDP Components.



Note

In order to access SSL enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Apache Knox Gateway Administrator Guide](#), [Gateway Security](#), [Configure Wire Encryption](#).

4.21.1. Connect to SSL Enabled HiveServer2 using JDBC

HiveServer2 implemented encryption with the Java SASL protocol's quality of protection (QOP) setting that allows data moving between a HiveServer2 over JDBC and a JDBC client to be encrypted.

From the JDBC client specify `sasl.sop` as part of the JDBC-Hive connection string, for example `jdbc:hive://hostname/dbname;sasl.qop=auth-int`. For more information on connecting to Hive, see [Data Integration Services with HDP, Moving Data into Hive: Hive ODBC and JDBC Drivers](#).



Tip

See [HIVE-4911](#) for more details on this enhancement.

4.21.2. Connect to SSL Enabled Oozie Server

On every Oozie client system, follow the instructions for the type of certificate used in your environment.

4.21.2.1. Use a Self-signed Certificate from Oozie Java Clients

When using a self-signed certificate, you must first install the certificate before the Oozie client can connect to the server.

1. Install the certificate in the keychain:
 - a. Copy or download the `.cert` file onto the client machine.
 - b. Run the following command (as root) to import the certificate into the JRE's keystore:

```
sudo keytool -import -alias tomcat -file path/to/certificate.cert -  
keystore <JRE_cacerts>
```

Where `$JRE_cacerts` is the path to the JRE's certs file. It's location may differ depending on the Operating System, but its typically called `cacerts` and located at `$JAVA_HOME/lib/security/cacerts`. It can be under a different directory in `$JAVA_HOME`. The default password is `changeit`.

Java programs, including the Oozie client, can now connect to the Oozie Server using the self-signed certificate.

2. In the connection strings change HTTP to HTTPS, for example, replace `http://oozie.server.hostname:11000/oozie` with `https://oozie.server.hostname:11443/oozie`.

Java does not automatically redirect HTTP addresses to HTTPS.

4.21.2.2. Connect to Oozie from Java Clients

In the connection strings change HTTP to HTTPS and adjust the port, for example, replace `http://oozie.server.hostname:11000/oozie` with `https://oozie.server.hostname:11443/oozie`.

Java does not automatically redirect HTTP addresses to HTTPS.

4.21.2.3. Connect to Oozie from a Web Browser

Use `https://oozie.server.hostname:11443/oozie` though most browsers should automatically redirect you if you use `http://oozie.server.hostname:11000/oozie`.

When using a Self-Signed Certificate, your browser warns you that it can't verify the certificate. Add the certificate as an exception.

5. Auditing in Hadoop

5.1. Using Apache Solr for Ranger Audits

Apache Solr is an open-source enterprise search platform. Apache Ranger can use Apache Solr to store audit logs, and Solr can also to provide a search capability of the audit logs through the Ranger Admin UI.



Important

Solr must be installed and configured before installing RangerAdmin or any of the Ranger component plugins.

It is recommended that Ranger audits be written to both Solr and HDFS. Audits to Solr are primarily used to enable search queries from the Ranger Admin UI. HDFS is a long-term destination for audits – audits stored in HDFS can be exported to any SIEM system, or to another audit store.

Configuration Options

- Solr Standalone – Solr Standalone is only recommended for testing and evaluation. Solr Standalone is a single instance of Solr that does not require ZooKeeper.
- SolrCloud – This is the recommended configuration for Ranger. [SolrCloud](#) is a scalable architecture that can run as single node or as a multi-node cluster. It includes features such as replication and sharding, which are useful for high availability (HA) and scalability. With SolrCloud, you need to plan the deployment based on the cluster size.

The following sections describe how to install and configure Apache Solr for Ranger Audits:

- [Prerequisites \[356\]](#)
- [Installing Solr \[357\]](#)
- [Configuring Solr Standalone \[357\]](#)
- [Configuring SolrCloud \[358\]](#)

5.1.1. Prerequisites

Solr Prerequisites

- Ranger supports Apache Solr 5.2 or higher.
- Apache Solr requires the Java Runtime Environment (JRE) version 1.7 or higher.
- 1 TB free space in the volume where Solr will store the index data.
- 32 GB RAM.

SolrCloud Prerequisites

- SolrCloud supports replication and sharding. It is highly recommended that you use SolrCloud with at least two Solr nodes running on different servers with replication enabled.
- SolrCloud requires Apache ZooKeeper.

5.1.2. Installing Solr

Use the following command to install Solr:

```
yum install lucidworks-hdpsearch
```

5.1.3. Configuring Solr Standalone

Use the following procedure to configure Solr Standalone.

1. Download the `solr_for_audit_setup_v3` file to the `/usr/local/` directory:

```
wget https://issues.apache.org/jira/secure/attachment/12761323/solr_for_audit_setup_v3.tgz -O /usr/local/solr_for_audit_setup_v3.tgz
```

2. Use the following commands to switch to the `/usr/local/` directory and extract the `solr_for_audit_setup_v3` file.

```
cd /usr/local
tar xvf solr_for_audit_setup_v3.tgz
```

The contents of the `.tgz` file will be extracted into a `/usr/local/solr_for_audit_setup` directory.

3. Use the following command to switch to the `/usr/local/solr_for_audit_setup` directory.

```
cd /usr/local/solr_for_audit_setup
```

4. Use the following command to open the `install.properties` file in the `vi` text editor.

```
vi install.properties
```

Set the following property values, then save the changes to the `install.properties` file.

Table 5.1. Solr `install.properties` Values

Property Name	Value	Description
JAVA_HOME	<path_to_jdk>, for example: <code>/usr/jdk64/jdk1.8.0_60</code>	Provide the path to the JDK install folder. For Hadoop, you can check <code>/etc/hadoop/conf/hadoop-env.sh</code> for the value of <code>JAVA_HOME</code> . As noted previously, Solr only supports JDK 1.7 and higher.
SOLR_USER	<code>solr</code>	The Linux user used to run Solr.
SOLR_INSTALL_FOLDER	<code>/opt/lucidworks-hdpsearch/solr</code>	The Solr installation directory.

Property Name	Value	Description
SOLR_RANGER_HOME	/opt/solr/ranger_audit_server	The location where the Ranger-related configuration and schema files will be copied.
SOLR_RANGER_PORT	6083	The Solr port for Ranger.
SOLR_DEPLOYMENT	standalone	The deployment type.
SOLR_RANGER_DATA_FOLDER	/opt/solr/ranger_audit_server/data	The folder where the index data will be stored. The volume for this folder should have at least 1 TB free space for the index data, and should be backed up regularly.
SOLR_LOG_FOLDER	/var/log/solr/ranger_audits	The folder for the Solr log files.
SOLR_MAX_MEM	2g	The memory allocation for Solr.

- Use the following command to run the Solr for Ranger setup script.

```
./setup.sh
```

- To start Solr, log in as the `solr` or `root` user and run the following command.

```
/opt/solr/ranger_audit_server/scripts/start_solr.sh
```

When Solr starts, a confirmation message appears.

```
Started Solr server on port 6083 (pid=). Happy searching!
```

- You can use a web browser to open the Solr Admin Console at the following address:

```
http:<solr_host>:6083/solr
```



Note

You can use the following command to stop Solr:

```
/opt/solr/ranger_audit_server/scripts/stop_solr.sh
```

5.1.4. Configuring SolrCloud

Use the following procedure to configure SolrCloud.

- Download the `solr_for_audit_setup_v3` file to the `/usr/local/` directory:

```
wget https://issues.apache.org/jira/secure/attachment/12761323/solr_for_audit_setup_v3.tgz -O /usr/local/solr_for_audit_setup_v3.tgz
```

- Use the following commands to switch to the `/usr/local/` directory and extract the `solr_for_audit_setup_v3` file.

```
cd /usr/local
tar xvf solr_for_audit_setup_v3.tgz
```

The contents of the `.tgz` file will be extracted into a `/usr/local/solr_for_audit_setup` directory.

- Use the following command to switch to the `/usr/local/solr_for_audit_setup` directory.

```
cd /usr/local/solr_for_audit_setup
```

- Use the following command to open the `install.properties` file in the vi text editor.

```
vi install.properties
```

Set the following property values, then save the changes to the `install.properties` file.

Table 5.2. Solr install.properties Values

Property Name	Value	Description
JAVA_HOME	<path_to_jdk>, for example: <code>/usr/jdk64/jdk1.8.0_40</code>	Provide the path to the JDK install folder. For Hadoop, you can check <code>/etc/hadoop/conf/hadoop-env.sh</code> for the value of JAVA_HOME. As noted previously, Solr only supports JDK 1.7 and higher.
SOLR_USER	<code>solr</code>	The Linux user used to run Solr.
SOLR_INSTALL_FOLDER	<code>/opt/lucidworks-hdpsearch/solr</code>	The Solr installation directory.
SOLR_RANGER_HOME	<code>/opt/solr/ranger_audit_server</code>	The location where the Ranger-related configuration and schema files will be copied.
SOLR_RANGER_PORT	<code>6083</code>	The Solr port for Ranger.
SOLR_DEPLOYMENT	<code>solrcloud</code>	The deployment type.
SOLR_ZK	<ZooKeeper_host>:2181/ <code>ranger_audits</code>	The Solr ZooKeeper host and port. It is recommended to provide a sub-folder to create the Ranger Audit related configurations so you can also use ZooKeeper for other Solr instances. Due to a Solr bug, if you are using a path (sub-folder), you can only specify one ZooKeeper host.
SOLR_SHARDS	<code>1</code>	If you want to distribute your audit logs, you can use multiple shards. Make sure the number of shards is equal or less than the number of Solr nodes you will be running.
SOLR_REPLICATION	<code>1</code>	It is highly recommend that you set up at least two nodes and replicate the indexes. This gives redundancy to index data, and also provides load balancing of Solr queries.
SOLR_LOG_FOLDER	<code>/var/log/solr/ranger_audits</code>	The folder for the Solr log files.
SOLR_MAX_MEM	<code>2g</code>	The memory allocation for Solr.

- Use the following command to run the set up script.

```
./setup.sh
```

- Run the following command **only once** from any node. This command adds the Ranger Audit configuration (including `schema.xml`) to ZooKeeper.

```
/opt/solr/ranger_audit_server/scripts/add_ranger_audits_conf_to_zk.sh
```

- Log in as the `solr` or `root` user and run the following command to start Solr on each node.

```
/opt/solr/ranger_audit_server/scripts/start_solr.sh
```


When Solr starts, a confirmation message appears.

```
Started Solr server on port 6083 (pid=). Happy searching!
```

8. Run the following command **only once** from any node. This command creates the Ranger Audit collection.

```
/opt/solr/ranger_audit_server/scripts/create_ranger_audits_collection.sh
```

9. You can use a web browser to open the Solr Admin Console at the following address:

```
http:<solr_host>:6083/solr
```



Note

You can use the following command to stop Solr:

```
/opt/solr/ranger_audit_server/scripts/stop_solr.sh
```

5.2. Manually Enabling Audit Settings in Ambari Clusters

It is recommended that Ranger audits be written to both Solr and HDFS. Audits to Solr are primarily used to enable queries from the Ranger Admin UI. HDFS is a long-term destination for audits; audits stored in HDFS can be exported to any SIEM system, or to another audit store.

Solr and HDFS audits are generally enabled as part of the standard Ambari installation procedure. This section describes how to manually update Ambari audit settings for Solr and HDFS.

5.2.1. Manually Updating Ambari Solr Audit Settings

You can save and store Ranger audits to Solr if you have installed and configured the Solr service in your cluster.



Note

If you enabled Solr Audits as part of the standard Ambari installation procedure, audits to Solr are activated automatically when Ranger is enabled for a plugin.

To save Ranger audits to Solr:

1. From the Ambari dashboard, select the Ranger service. Select **Configs > Advanced**, then scroll down and select **Advanced ranger-admin-site**. Set the following property value:
 - `ranger.audit.source.type = solr`
2. On the Ranger Configs tab, select **Ranger Audit**. The SolrCloud button should be set to ON. The SolrCloud configuration settings are loaded automatically when the SolrCloud button is set from OFF to ON, but you can also manually update the settings.



Note

Audits to Solr requires that you have already [installed Solr](#) and [configured SolrCloud](#).

3. Restart the Ranger service.
4. After the Ranger service has been restarted, you will then need to make specific configuration changes for each plugin to ensure that the plugin's data is captured in Solr.
5. For example, if you would like to configure HBase for audits to Solr, perform the following steps:
 - Select the Audit to Solr checkbox in Advanced ranger-hbase-audit.
 - Enable the Ranger plugin for HBase.
 - Restart the HBase component.
6. Verify that the Ranger audit logs are being passed to Solr by opening one of the following URLs in a web browser:

`http://{RANGER_HOST_NAME}:6080/index.html#!/reports/audit/bigData`

`http://{SOLR_HOST}:6083/solr/ranger_audits`

5.2.2. Manually Updating Ambari HDFS Audit Settings



Note

HDFS audits are enabled by default in the standard Ranger Ambari installation procedure, and are activated automatically when Ranger is enabled for a plugin.

The following steps show how to save Ranger audits to HDFS for HBase. You can use the same procedure for other components.

1. From the Ambari dashboard, select the HBase service. On the Configs tab, scroll down and select **Advanced ranger-hbase-audit**. Select the **Audit to HDFS** check box.
2. Set the HDFS path where you want to store audits in HDFS:

```
xasecure.audit.destination.hdfs.dir = hdfs://  
$NAMENODE_FQDN:8020/ranger/audit
```

Refer to the `fs.defaultFS` property in the **Advanced core-site** settings.



Note

For NameNode HA, `NAMENODE_FQDN` is the cluster name. In order for this to work, `/etc/hadoop/conf/hdfs-site.xml` needs to be linked under `/etc/<component_name>/conf`.

3. Enable the Ranger plugin for HBase.
4. Make sure that the plugin sudo user should has permission on the HDFS Path:

```
hdfs://NAMENODE_FQDN:8020/ranger/audit
```

For example, we need to create a Policy for Resource : `/ranger/audit`, all permissions to user hbase.

5. Save the configuration updates and restart HBase.
6. Generate some audit logs for the HBase component.
7. Check the HFDS component logs on the NameNode:

```
hdfs://NAMENODE_FQDN:8020/ranger/audit
```



Note

For a secure cluster, use the following steps to enable audit to HDFS for Storm, Kafka, and Knox:

- In `core-site.xml` set the `hadoop.proxyuser.<component>.groups` property with value `" * "` or service user.
- For the Knox plugin there is one additional property to add to `core-site.xml`. Add `hadoop.proxyuser.<component>.users` property with value `" * "` or service user (i.e Knox).
- For Kafka and Knox, link to `/etc/hadoop/conf/core-site.xml` under `/etc/<component_name>/conf`. For Storm, link to `/etc/hadoop/conf/core-site.xml` under `/usr/hdp/<version>/storm/extlib-daemon/ranger-storm-plugin-impl/conf`.
- Verify the service user principal.
- Make sure that the component user has permissions on HDFS.

5.3. Enabling Audit Logging in Non-Ambari Clusters

It is recommended that Ranger audits be written to both Solr and HDFS. Audits to Solr are primarily used to enable queries from the Ranger Admin UI. HDFS is a long-term destination for audits; audits stored in HDFS can be exported to any SIEM system, or to another audit store.

To enable auditing for HDFS, perform the steps listed below.

1. Set the `XAAUDIT.HDFS.ENABLE` value to "true" for the component plug-in in the `install.properties` file, which can be found here:

```
/usr/hdp/<version>/ranger-<component>=plugin
```

2. Configure the NameNode host in the `XAAUDIT.HDFS.HDFS_DIR` field.

3. Create a policy in the HDFS service from the Ranger Admin for individual component users (`hive/hbase/knox/storm/yarn/kafka/kms`) to provide READ and WRITE permissions for the audit folder (i.e., for enabling Hive component to log Audits to HDFS, you need to create a policy for the hive user with Read and WRITE permissions for the audit directory).
4. Set the Audit to HDFS caches logs in the local directory, which can be specified in `XAAUDIT.HDFS.LOCAL_BUFFER_DIRECTORY` (this can be like `/var/log/<component>/**`), which is the path where the audit is stored for a short time. This is similar for archive logs that need to be updated.

To enable auditing reporting from the Solr database, perform the steps listed below.

1. Modify the following properties in the Ranger service `install.properties` to enable auditing to the Solr database in Ranger:

- `audit_store=solr`
- `audit_solr_urls=http://solr_host:6083/solr/ranger_audits`
- `audit_solr_user=ranger_solr`
- `audit_solr_password=NONE`

2. Restart Ranger.

To enable auditing to the Solr database for a plug-in (e.g., HBase), perform the steps listed below.

1. Set the following properties in `install.properties` of the plug-in to begin audit logging to the Solr database:

- `XAAUDIT.SOLR.IS.ENABLED=true`
- `XAAUDIT.SOLR.ENABLE=true`
- `XAAUDIT.SOLR.URL=http://solr_host:6083/solr/ranger_audits`
- `XAAUDIT.SOLR.USER=ranger_solr`
- `XAAUDIT.SOLR.PASSWORD=NONE`
- `XAAUDIT.SOLR.FILE_SPOOL_DIR=/var/log/hadoop/hdfs/audit/solr/spool`

2. Enable the Ranger HBase plug-in.

3. Restart the HBase component.

5.4. Managing Auditing in Ranger

To explore options for auditing policies in Ranger, [access the Ranger console](#), then click **Audit** in the top menu.



There are four tabs on the Audit page:

- [Access \[365\]](#)
- [Admin \[366\]](#)
- [Login Sessions \[367\]](#)
- [Plugins \[368\]](#)



Note

To access audit logs from the Ranger Audit UI, enable XAAUDIT.DB.IS_ENABLED in your Ranger plug-in configuration.

5.4.1. View Operation Details

To view details on a particular operation, click the Policy ID, Operation name, or Session ID.

Operation : update ×

Policy ID : 2
 Added Deleted

Policy Name : hbase-test-1-20160202224128
 Repository Type : hbase
 Updated Date : 02/16/2016 09:51:42 AM PST
 Updated By : Mal

Policy Details :

Fields	Old Value	New Value
table	*	*.y

OK

Operation : create ×

Policy ID : 13

Policy Name : New-Service-1-20160211205602
 Repository Type :
 Created Date : 02/11/2016 12:56:02 PM PST
 Created By : Admin


Policy Details :

Fields	New Value
Policy Name	New-Service-1-20160211205602
Policy Description	Default Policy for Service: New-Service
Policy Status	enabled

Users/Groups Permissions :

New Value
Groups: <empty>
Users: admin

OK



5.4.2. Access

Provides Service activity data for all Policies that have Audit set to **On**. The default service Policy is configured to log all user activity within the Service. This default policy does not contain user and group access rules.

You can filter the data based on the following criteria:

Table 5.3. Search Criteria

Search Criteria	Description
Access Enforcer	Access enforcer indicates who made the decision to allow or deny. In case of HDFS, the enforcer would XA (Ranger) or Hadoop.
Access Type	Type of access user attempted (E.G., REVOKE, GRANT, OPEN, USE).
Client IP	IP address of the user system that tried to access the resource.
Result	Shows whether the operation was successful or not.
Service Name	The name of the service that the user tried to access.
Service Type	The type of the service that the user tried to access.
Start Date, End Date	Filters results for a particular date range.
User	Name of the user which tried to access the resource.

Policy ID	Event Time	User	Service Name / Type	Resource Name	Access Type	Result	Access Enforcer	Client IP	Event Count
4	07/30/2015 05:43:27 PM	hbase	hbasedev hbase	testtable2/*	revoke	Allowed	ranger-ad	172.22.115.226	1
4	07/30/2015 05:14:59 PM	hbase	hbasedev hbase	testtable2/*	grant	Allowed	ranger-ad	172.22.115.226	1
4	07/30/2015 05:14:03 PM	hbase	hbasedev hbase	testtable2	open	Allowed	ranger-ad		1
4	07/30/2015 04:56:30 PM	hbase	hbasedev hbase	icwgr/*	grant	Allowed	ranger-ad	172.22.115.207	1
4	07/30/2015 04:51:24 PM	hbase	hbasedev hbase	icwgr	open	Allowed	ranger-ad		1
5	07/30/2015 03:24:26 PM	hive	hivedev hive		USE	Allowed	ranger-ad	172.22.115.226	1
5	07/30/2015 03:23:51 PM	hive	hivedev hive		USE	Allowed	ranger-ad	172.22.115.226	1
-	07/30/2015 11:41:26 AM	hbase	d1_hadoop hdfs	/apps/hbase/data/oldWRLLS	READ_EXECUTE	Allowed	hadoop-ad	172.22.115.226	1

5.4.3. Admin

The Admin tab contains all events for the HDP Security Administration Web UI, including Service, Service Manager, Log in, etc. (actions like create, update, delete, password change).

Operation	Audit Type	User	Date (PST)	Actions	Session Id
Policy updated hbase-test-1-20160202224128	Ranger Policy	Mal	02/16/2016 09:51:42 AM	update	52509
Policy updated Example-Service-1-20160211205602	Ranger Policy	admin	02/11/2016 12:56:48 PM	update	52478
Service updated Example-Service	Ranger Service	admin	02/11/2016 12:56:34 PM	update	52478
Policy created New-Service-1-20160211205602	Ranger Policy	admin	02/11/2016 12:56:02 PM	create	52478
Service created New-Service	Ranger Service	admin	02/11/2016 12:56:02 PM	create	52478
Policy updated hbase-test-1-20160202224128	Ranger Policy	admin	02/11/2016 10:27:15 AM	update	52461
User updated Mal	XA User	admin	02/11/2016 10:26:06 AM	update	52461
Group created UX	XA Group	admin	02/11/2016 10:25:21 AM	create	52461
Policy created test-storm-1-20160211010740	Ranger Policy	admin	02/15/2016 05:07:40 PM	create	52391

You can filter the data based on the following criteria:

Table 5.4. Search Criteria

Search Criteria	Description
Action	These are operations performed on resources (actions like create, update, delete, password change).
Audit Type	There are three values Resource,asset and xa user according to operations performed on Service,policy and users.
End Date	Login time and date is stored for each session. A date range is used to filter the results for that particular date range.
Session ID	The session count increments each time you try to login to the system

Search Criteria	Description
Start Date	Login time and date is stored for each session. A date range is used to filter the results for that particular date range.
User	Username who has performed create,update,delete operation.

5.4.4. Login Sessions

The Login Sessions tab logs the information related to the sessions for each login.

You can filter the data based on the following criteria:

Table 5.5. Search Criteria

Search Criteria	Description
Login ID	The username through which someone logs in to the system.
Session-id	The session count increments each time the user tries to log into the system.
Start Date, End Date	Specifies that results should be filtered based on a particular start date and end date.
Login Type	The mode through which the user tries to login (by entering username and password).
IP	The IP address of the system through which the user logged in.
User Agent	The login time and date for each session.
Login time	Logs whether or not the login was successful. Possible results can be Success, Wrong Password, Account Disabled, Locked, Password Expired or User Not Found.

The screenshot shows the Ranger web interface with the 'Login Sessions' tab selected. The interface includes a search bar and a table of login sessions. The table has the following columns: Session Id, Login Id, Result, Login Type, IP, User Agent, and Login Time (PST). The data in the table is as follows:

Session Id	Login Id	Result	Login Type	IP	User Agent	Login Time (PST)
52329	amb_ranger_admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 12:50:32 PM
52328	admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 12:50:32 PM
52327	admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 12:50:32 PM
52326	admin	Success	Username/Password	192.168.64.1	Mozilla/5.0 (Macintosh; Intel ...	02/09/2016 12:39:38 PM
52325	amb_ranger_admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 10:50:32 AM
52324	admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 10:50:32 AM
52323	admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 10:50:32 AM
52322	rangerusersync	Success	Username/Password	192.168.64.101	java/1.8.0_60	02/09/2016 10:21:22 AM
52321	rangerusersync	Success	Username/Password	192.168.64.101	java/1.8.0_60	02/09/2016 10:21:21 AM
52320	rangerusersync	Success	Username/Password	192.168.64.101	java/1.8.0_60	02/09/2016 10:21:21 AM
52319	rangerusersync	Success	Username/Password	192.168.64.101	java/1.8.0_60	02/09/2016 10:21:21 AM

5.4.5. Plugins

This tab shows the upload history of the Security Agents. This module displays all of the services exported from the system. You can filter the data based on the following criteria:

Table 5.6. Agents Search Criteria

Search Criteria	Description
Plugin IP	IP Address of the agent that tried to export the service.
Plugin ID	Name of the agent that tried to export the service.
HTTP Response Code	The HTTP code returned when trying to export the service.
Start Date, End Date	Export time and date is stored for each agent. A date range is used to filter the results for that particular date range.
Service Name	The service name we are trying to export.

6. Data Protection: HDFS Encryption

6.1. Ranger KMS Administration Guide

The Ranger Key Management Service (Ranger KMS) is an open source, scalable cryptographic key management service supporting HDFS "data at rest" encryption.

Ranger KMS is based on the Hadoop KMS originally developed by the Apache community. The Hadoop KMS stores keys in a file-based Java keystore by default. Ranger extends the native Hadoop KMS functionality by allowing you to store keys in a secure database.

Ranger provides centralized administration of the key management server through the Ranger admin portal.

There are three main functions within the Ranger KMS:

1. **Key management.** Ranger admin provides the ability to create, update or delete keys using the Web UI or REST APIs. All [Hadoop KMS APIs](#) work with Ranger KMS using the keyadmin username and password.
2. **Access control policies.** Ranger admin also provides the ability to manage access control policies within Ranger KMS. The access policies control permissions to generate or manage keys, adding another layer of security for data encrypted in Hadoop.
3. **Audit.** Ranger provides full audit trace of all actions performed by Ranger KMS.

Ranger KMS along with HDFS encryption are recommended for use in all environments. In addition to secure key storage using a database, Ranger KMS is also scalable, and multiple versions of Ranger KMS can be run behind a load balancer.

For more information about HDFS encryption, see [HDFS "Data at Rest" Encryption](#).

6.1.1. Installing the Ranger Key Management Service

This section describes how to install the Ranger Key Management Service (KMS) using Ambari on a Kerberized cluster.

Prerequisites

Ranger KMS requires HDFS and Ranger to be installed and running on the cluster.

To install Ranger using Ambari, refer to the [Ranger Installation Guide](#). (For more information about the Ambari Add Service Wizard, see [Adding a Service](#) in the *Ambari User's Guide*.)

To use 256-bit keys, install the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on all hosts in the cluster. For installation information, see [Install the JCE](#). Make sure that the Java location is specified in the \$PATH environment variable.



Note

If you use the OpenJDK package, the JCE file is already built into the package.

6.1.1.1. Install Ranger KMS using Ambari (Kerberized Cluster)

To install Ranger KMS on a Kerberized cluster, complete the following steps.

1. Go to the Ambari Web UI, `http://<gateway-URL>:8080`.
2. From the Ambari dashboard, go to the **Actions** menu. Choose **Add Service**.
3. On the next screen, check the box next to **Ranger KMS**:

Add Service Wizard x

<input checked="" type="checkbox"/>	HBase	1.1.1.2.3	A Non-relational distributed database, plus Phoenix, a high performance SQL layer for low latency applications.
<input checked="" type="checkbox"/>	Pig	0.15.0.2.3	Scripting platform for analyzing large datasets
<input type="checkbox"/>	Sqoop	1.4.6.2.3	Tool for transferring bulk data between Apache Hadoop and structured data stores such as relational databases
<input checked="" type="checkbox"/>	Oozie	4.2.0.2.3	System for workflow coordination and execution of Apache Hadoop jobs. This also includes the installation of the optional Oozie Web Console which relies on and will install the ExtJS Library.
<input checked="" type="checkbox"/>	ZooKeeper	3.4.6.2.3	Centralized service which provides highly reliable distributed coordination
<input type="checkbox"/>	Faloon	0.6.1.2.3	Data management and processing platform
<input checked="" type="checkbox"/>	Storm	0.10.0	Apache Hadoop Stream processing framework
<input type="checkbox"/>	Flume	1.5.2.2.3	A distributed service for collecting, aggregating, and moving large amounts of streaming data into HDFS
<input type="checkbox"/>	Accumulo	1.7.0.2.3	Robust, scalable, high performance distributed key/value store.
<input checked="" type="checkbox"/>	Ambari Metrics	0.1.0	A system for metrics collection that provides storage and retrieval capability for metrics collected from the cluster
<input type="checkbox"/>	Atlas	0.5.0.2.3	Atlas Metadata and Governance platform
<input checked="" type="checkbox"/>	Kafka	0.8.2.2.3	A high-throughput distributed messaging system
<input checked="" type="checkbox"/>	Knox	0.6.0.2.3	Provides a single point of authentication and access for Apache Hadoop services in a cluster
<input type="checkbox"/>	Mahout	0.9.0.2.3	Project of the Apache Software Foundation to produce free implementations of distributed or otherwise scalable machine learning algorithms focused primarily in the areas of collaborative filtering, clustering and classification
<input checked="" type="checkbox"/>	Ranger	0.5.0.2.3	Comprehensive security for Hadoop
<input checked="" type="checkbox"/>	Ranger KMS	0.5.0.2.3	Key Management Server
<input type="checkbox"/>	Slider	0.80.0.2.3	A framework for deploying, managing and monitoring existing distributed applications on YARN.
<input type="checkbox"/>	Spark	1.3.1.2.3	Apache Spark is a fast and general engine for large-scale data processing.

Next →

4. Then, choose **Next**.
5. (Optional) In **Assign Masters**, if you wish to override the default host setting, specify the Ranger KMS host address. For example:

Add Service Wizard

The screenshot shows the 'Add Service Wizard' configuration page. On the left, a list of services is shown with dropdown menus for their configurations. On the right, two server configuration panels are visible. The 'Ranger KMS Server' dropdown menu is open, showing several options with red boxes around them. The 'Next' button is highlighted in green.

Service	Configuration
HiveServer2:	vp-os-rh6-my-sec-nokms-1507
HBase Master:	vp-os-rh6-my-sec-nokms-1507
Oozie Server:	vp-os-rh6-my-sec-nokms-1507
ZooKeeper Server:	vp-os-rh6-my-sec-nokms-1507
ZooKeeper Server:	vp-os-rh6-my-sec-nokms-1507
ZooKeeper Server:	vp-os-rh6-my-sec-nokms-1507
Nimbus:	vp-os-rh6-my-sec-nokms-1507
DRPC Server:	vp-os-rh6-my-sec-nokms-1507
Storm UI Server:	vp-os-rh6-my-sec-nokms-1507
Kafka Broker:	vp-os-rh6-my-sec-nokms-1507
Kafka Broker:	vp-os-rh6-my-sec-nokms-1507
Kafka Broker:	vp-os-rh6-my-sec-nokms-1507
Kafka Broker:	vp-os-rh6-my-sec-nokms-1507
Metrics Collector:	vp-os-rh6-my-sec-nokms-1507
Ranger KMS Server:	vp-os-rh6-my-sec-nokms-1507
Knox Gateway:	vp-os-rh6-my-sec-nokms-1507
Ranger Admin:	vp-os-rh6-my-sec-nokms-1507
Ranger Usersync:	vp-os-rh6-my-sec-nokms-1507

Server configurations on the right:

- vp-os-rh6-my-sec-nokms-150727-1736-4.openstacklocal (15.6 GB, 2 cores)
 - NameNode
 - History Server
 - App Timeline Server
 - HBase Master
 - ZooKeeper Server
 - DRPC Server
 - Storm UI Server
 - Kafka Broker
- vp-os-rh6-my-sec-nokms-150727-1736-5.openstacklocal (15.6 GB, 2 cores)
 - Kafka Broker
 - Ranger Admin
 - Ranger Usersync

6. In **Customize Services**, set required values (marked in red). Review other configuration settings, and determine whether you'd like to change any of the default values. (For more information about these properties, see [Ranger KMS Properties](#).)

a. Set the following required settings, marked in red in the "Advanced kms-properties" section:

- KMS_MASTER_KEY_PASSWD
- db_password
- db_root_password



Note

If do not wish to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the `dba_script.py` Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger installer. For more information, see [Setting up Database Users Without Sharing DBA Credentials](#).

Add Service Wizard

Choose Services
Assign Masters
Assign Slaves and Clients
Customize Services
Configure Identities
Review
Install, Start and Test
Summary

Customize Services

We have come up with recommended configurations for the services you selected. Customize them as you see fit.

HDFS MapReduce2 YARN Tez Hive HBase Pig Oozie ZooKeeper Storm Ambari Metrics Kafka
Knox Ranger **Ranger KMS** Misc

Group: Ranger KMS Default (4) Manage Config Groups Filter...

- Advanced dbks-site
- Advanced kms-env
- Advanced kms-log4j
- Advanced kms-properties**

DB_FLAVOR	MYSQL	<input type="checkbox"/>	<input type="checkbox"/>
KMS_MASTER_KEY_PASSWORD	Type password	Retype Password	This is required
REPOSITORY_CONFIG_PASSWORD	*****	*****	
REPOSITORY_CONFIG_USERNAME	keyadmin	<input type="checkbox"/>	<input type="checkbox"/>
SQL_CONNECTOR_JAR	/usr/share/java/mysql-connector-java.jar	<input type="checkbox"/>	<input type="checkbox"/>
db_host	vp-os-rh6-my-sec-nokms-150727-1736-5.openstacklocal	<input type="checkbox"/>	<input type="checkbox"/>
db_name	rangerkms	<input type="checkbox"/>	<input type="checkbox"/>
db_password	Type password	Retype Password	This is required
db_root_password	Type password	Retype Password	This is required
db_root_user	root	<input type="checkbox"/>	<input type="checkbox"/>
db_user	rangerkms	<input type="checkbox"/>	<input type="checkbox"/>

Also specify the username for REPOSITORY_CONFIG_USERNAME, so that Ranger will be able to connect to the Ranger KMS Server and look up keys for creating access policies. This user will need to be set to proxy into Ranger KMS in a Kerberos mode (steps included below).

- b. Add values for the following properties in the "Custom kms-site" section. These properties allow the specified system users (hive, oozie, and others) to proxy on behalf of other users when communicating with Ranger KMS. This helps individual services (such as Hive) use their own keytabs, but retain the ability to access Ranger KMS as the end user (use access policies associated with the end user).


- `hadoop.kms.proxyuser.hive.users`
- `hadoop.kms.proxyuser.oozie.users`
- `hadoop.kms.proxyuser.HTTP.users`
- `hadoop.kms.proxyuser.ambari.users`
- `hadoop.kms.proxyuser.yarn.users`
- `hadoop.kms.proxyuser.hive.hosts`

- `hadoop.kms.proxyuser.oozie.hosts`
- `hadoop.kms.proxyuser.HTTP.hosts`
- `hadoop.kms.proxyuser.ambari.hosts`
- `hadoop.kms.proxyuser.yarn.hosts`

- c. Add the following properties to the Custom KMS-site section of the configuration. These properties use the `REPOSITORY_CONFIG_USERNAME` specified in the first step in this section.

If you are using an account other than `keyadmin` to access Ranger KMS, replace "keyadmin" with the configured user for the Ranger KMS repository in Ranger admin:

- `hadoop.kms.proxyuser.keyadmin.groups=*`
- `hadoop.kms.proxyuser.keyadmin.hosts=*`
- `hadoop.kms.proxyuser.keyadmin.users=*`



- d. Confirm settings of the following values in the "advanced kms-site" group:

- `hadoop.kms.authentication.type=kerberos`
- `hadoop.kms.authentication.kerberos.keytab=/etc/security/keytabs/spnego.service.keytab`
- `hadoop.kms.authentication.kerberos.principal=*`

7. Then, choose **Next**.

8. Review the default values on the **Configure Identities** screen. Determine whether you'd like to change any of the default values. Then, choose **Next**.

9. In **Review**, make sure the configuration values are correct. Ranger KMS will be listed under **Services**.

10. Then, choose **Deploy**.

11. Monitor the progress of installing, starting, and testing the service. When the service installs and starts successfully, choose **Next**.

12. The Summary screen displays the results. Choose **Complete**.

13. Restart the Ranger and Ranger KMS services.

6.1.1.1.1. Setting up Database Users Without Sharing DBA Credentials

If do not wish to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the `dba_script.py` Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger installer. You can then run the normal Ambari Ranger installation without specifying a DBA user name and password.

To create Ranger DB users using the `dba_script.py` script:

1. Download the Ranger rpm using the yum install command.

```
yum install ranger-kms
```

2. You should see one file named `dba_script.py` in the `/usr/hdp/current/ranger-admin` directory.
3. Get the script reviewed internally and verify that your DBA is authorized to run the script.
4. Execute the script by running the following command:

```
python dba_script.py
```

5. Pass all values required in the argument. These should include `db flavor`, `JDBC jar`, `db host`, `db name`, `db user`, and other parameters.

- If you would prefer not to pass runtime arguments via the command prompt, you can update the `/usr/hdp/current/ranger-admin/install.properties` file and then run:

```
python dba_script.py -q
```

When you specify the `-q` option, the script will read all required information from the `install.properties` file

- You can use the `-d` option to run the script in "dry" mode. Running the script in dry mode causes the script to generate a database script.

```
python dba_script.py -d /tmp/generated-script.sql
```

Anyone can run the script, but it is recommended that the system DBA run the script in dry mode. In either case, the system DBA should review the generated script, but should only make minor adjustments to the script, for example, change the location of a particular database file. No major changes should be made that substantially alter the script – otherwise the Ranger install may fail.

The system DBA must then run the generated script.

6. Log in to the host where KMS is to be installed. Run the following commands to back up files:

```
cp /var/lib/ambari-agent/cache/common-services/RANGER_KMS/0.5.0.2.3/package/scripts/kms.py /var/lib/ambari-agent/cache/common-services/RANGER_KMS/0.5.0.2.3/package/scripts/kms.py.bak
cp /var/lib/ambari-server/resources/common-services/RANGER_KMS/0.5.0.2.3/package/scripts/kms.py /var/lib/ambari-server/resources/common-services/RANGER_KMS/0.5.0.2.3/package/scripts/kms.py.bak
```

7. In both of the `kms.py` files copied in the previous step, find and comment out the following line (shown here commented out).

```
#Execute(dba_setup, environment=env_dict, logoutput=True, user=params.kms_user)
```

8. Run the Ranger Ambari install procedure, but set **Setup Database and Database User** to **No** in the Ranger Admin section of the Customize Services screen.

6.1.1.1.2. Configure HDFS Encryption to use Ranger KMS Access

At this point, Ranger KMS should be installed and running. If you plan to use Ranger KMS for HDFS data at rest encryption, complete the following steps:

1. Create a link to `/etc/hadoop/conf/core-site.xml` under `/etc/ranger/kms/conf`:

```
sudo ln -s /etc/hadoop/conf/core-site.xml /etc/ranger/kms/conf/core-site.xml
```

2. Configure HDFS to access Ranger KMS.
 - a. In the left panel of the Ambari main menu, choose HDFS.
 - b. Choose the **Configs** tab at the top of the page, and then choose the **Advanced** tab partway down the page.
 - c. Specify the provider path (the URL where the Ranger KMS server is running) in the following two properties, if the path is not already specified:
 - In "Advanced core-site", specify `hadoop.security.key.provider.path`
 - In "Advanced hdfs-site", specify `dfs.encrypted.key.provider.uri`

The screenshot displays the Ambari Services page for HDFS. The top navigation bar includes 'Dashboard', 'Services', 'Hosts', 'Alerts', and 'Admin'. The left sidebar lists various services like MapReduce2, YARN, Tez, Hive, HBase, Pig, Oozie, ZooKeeper, Storm, Ambari Metrics, Kafka, Kerberos, Knox, Ranger, and Ranger KMS. The main content area shows a 'Summary' tab with a 'Restart Required' banner. Below this, there's a 'Manage Config Groups' section for 'HDFS Default (4)' with a search for 'key.provider'. A list of hosts (V4-V9) is shown with their last update times. A configuration editor is open for 'key.provider', showing the value 'kms://http@vp-os-rh:9292/kms'. The 'Advanced' settings section is expanded, showing 'hadoop.security.key.provider.path' and 'dfs.encryption.key.provider.uri' both set to the same KMS URI.

The Ranger KMS host is where Ranger KMS is installed. The Ranger KMS host name should have the following format:

```
kms://http@<kms>:9292/kms
```

3. Under Custom core-site.xml, set the value of the `hadoop.proxyuser.kms.groups` property to `*` or service user.
4. Restart the Ranger KMS service and the HDFS service.

6.1.1.1.3. Use a Kerberos Principal for the Ranger KMS Repository

In Ranger, all access policies are configured within a repository for each service. For more information, refer to the [Ranger User Guide](#).

To manage access policies for Ranger KMS, a repository is needed with Ranger for the Ranger KMS service. Ambari creates the repository automatically using the repository config user and password provided.

The repository config user also needs to be created as a principal in Kerberos with a password. Use the following steps to use a Kerberos principal for the Ranger KMS repository.

1. Create system user `keyadmin` which should be sync in User Tabs in Ranger Admin.
2. Create principal `keyadmin@EXAMPLE.COM` with password `keyadmin`:

```
kadmind.local -q 'addprinc -pw keyadmin keyadmin'
```

3. On the Add Service wizard Customize Services page, set the required values (marked in red).
4. Under ranger-kms-properties, set the principal and password in the REPOSITORY_CONFIG_USERNAME and REPOSITORY_CONFIG_PASSWORD fields.
5. To check logs, select **Audit to DB** under Advanced ranger-kms-audit.
6. Click **Next** to continue with the Ranger KMS Add Service wizard.

The screenshot shows the 'Advanced kms-properties' configuration page in the Ambari UI. The page contains the following configuration fields:

- REPOSITORY_CONFIG_USERNAME:** keyadmin@EXAMPLE.COM (Status: Green, Orange, Blue)
- SQL_CONNECTOR_JAR:** /usr/share/java/mysql-connector-java.jar (Status: Green, Blue)
- db_host:** mp-secranger-2406-3.openstacklocal (Status: Green, Blue)
- db_user:** rangerkms (Status: Green, Blue)
- db_password:** (Two masked password fields)
- DB_FLAVOR:** MYSQL (Status: Green, Blue)
- db_root_user:** root (Status: Green, Blue)
- db_root_password:** (Two masked password fields)
- db_name:** rangerkms (Status: Green, Blue)
- KMS_MASTER_KEY_PASSWORD:** (Two masked password fields)
- REPOSITORY_CONFIG_PASSWORD:** (Two masked password fields)

6.1.2. Enable Ranger KMS Audit

Ranger KMS supports audit to DB, HDFS, and Solr. Solr is well-suited for short-term auditing and UI access (for example, one month of data accessible via quick queries in the Web UI). HDFS is typically used for archival auditing. They are not mutually exclusive; we recommend configuring audit to both Solr and HDFS.

First, make sure Ranger KMS logs are enabled:

1. Go to the Ambari UI: `http://<gateway>:8080`
2. Select `ranger-kms` from the service.
3. Click the Configs tab, and go to the accordion menu.
4. In the Advanced ranger-kms-audit list, set `xasecure.audit.is.enabled` to `true`.
5. Select "Audit to Solr" and/or "Audit to HDFS", depending on which database(s) you plan to use:

6. Save the configuration and restart the Ranger KMS service.

Next, check to see if the Ranger KMS Plugin is enabled:

1. Go to the Ranger UI: `http://<gateway>:6080`
2. Login with your keyadmin user ID and password (the defaults are `keyadmin`, `keyadmin`). The default repository will be added under KMS service.
3. Run a test connection for the service. You should see a 'connected successfully' popup message. If the connection is not successful, make sure that the configured user exists (in KDC for a secure cluster).
4. Choose the Audit > Plugin tab.
5. Check whether plugins are communicating. The UI should display `Http Response code 200` for the respective plugin.

The next two subsections describe how to save audit to Solr and HDFS.

6.1.2.1. Save Audits to Solr



Note

Saving audits to Solr requires that you have already [installed Solr](#) and [configured SolrCloud](#).

To save audits to Solr:

1. From the Ambari dashboard, select the Ranger service. Select **Configs > Advanced**, then scroll down and select **Advanced ranger-admin-site**. Set the following property value:
 - `ranger.audit.source.type = solr`

2. On the Ranger Configs tab, select **Ranger Audit**. The SolrCloud button should be set to ON. The SolrCloud configuration settings are loaded automatically when the SolrCloud button is set from OFF to ON, but you can also manually update the settings.
3. Restart the Ranger service.
4. Next, to enable Ranger KMS auditing to Solr, set the following properties in the Advanced ranger-kms-audit list:
 - a. Check the box next to `Enable audit to solr` in the Ranger KMS component.
 - b. Check the `Audit provider summary enabled` box, and make sure that `xasecure.audit.is.enabled` is set to true.
 - c. Restart Ranger KMS.



Note

Check audit logs on Ranger UI, to make sure that they are getting through Solr: `http://RANGER_HOST_NAME:6080/index.html#!/reports/audit/bigData` or `http://solr_host:6083/solr/ranger_audits`.

6.1.2.2. Save Audits to HDFS

There are no configuration changes needed for Ranger properties.

To save Ranger KMS audits to HDFS, set the following properties in the Advanced ranger-kms-audit list.

Note: the following configuration settings must be changed in each Plugin.

1. Check the box next to `Enable Audit to HDFS` in the Ranger KMS component.
2. Set the HDFS path to the path of the location in HDFS where you want to store audits:

```
xasecure.audit.destination.hdfs.dir = hdfs://NAMENODE_FQDN:8020/ranger/audit
```
3. Check the `Audit provider summary enabled` box, and make sure that `xasecure.audit.is.enabled` is set to true.
4. Make sure that the plugin's root user (`kms`) has permission to access HDFS Path `hdfs://NAMENODE_FQDN:8020/ranger/audit`
5. Restart Ranger KMS.
6. Generate audit logs for the Ranger KMS.
7. **(Optional)** To verify audit to HDFS without waiting for the default sync delay (approximately 24 hours), restart Ranger KMS. Ranger KMS will start writing to HDFS after the changes are saved post-restart.

To check for audit data:

```
hdfs dfs -ls /ranger/audit/
```

To test Ranger KMS audit to HDFS, complete the following steps:

1. Under custom `core-site.xml`, set `hadoop.proxyuser.kms.groups` to "*" or to the service user.
2. In the custom `kms-site` file, add `hadoop.kms.proxyuser.keyadmin.users` and set its value to "*". (If you are not using `keyadmin` to access Ranger KMS Admin, replace "keyadmin" with the user account used for authentication.)
3. In the custom `kms-site` file, add `hadoop.kms.proxyuser.keyadmin.hosts` and set its value to "*". (If you are not using `keyadmin` to access Ranger KMS Admin, replace "keyadmin" with the user account used for authentication.)
4. Copy the `core-site.xml` to the component's class path (`/etc/ranger/kms/conf`)

OR

link to `/etc/hadoop/conf/core-site.xml` under `/etc/ranger/kms/conf`
(`ln -s /etc/hadoop/conf/core-site.xml /etc/ranger/kms/conf/core-site.xml`)

5. Verify the service user principal. (For Ranger KMS it will be the `http` user.)
6. Make sure that the component user has permission to access HDFS. (For Ranger KMS the `http` user should also have permission.)

6.1.3. Enabling SSL for Ranger KMS

If you do not have access to Public CA-issued certificates, complete the following steps to create and configure self-signed certificates.



Note

The following examples contain sample values (folder locations, passwords, and filenames). Change these values according to your environment.

Considerations:

- Copy `keystore/truststore` files into a different location (e.g. `/etc/security/serverKeys`) than the `/etc/<component>/conf` folders.
- Make sure JKS file names are different from each other.
- Make sure correct permissions are applied.
- Make sure all passwords are secured.
- For the test connection to be successful after enabling SSL, self-signed certificates should be imported to the Ranger admin's trust store (typically `JDK cacerts`).
- Property `ranger.plugin.service.policy.rest.ssl.config.file` should be verified; for example:

```
ranger.plugin.kms.policy.rest.ssl.config.file ==> /etc/ranger/kms/conf/ranger-policymgr-ssl.xml
```

To enable SSL:

1. Stop the Ranger KMS service:



2. Go to the Ranger KMS (and plugin) installation location, and create a self-signed certificate:

```
cd /etc/ranger/kms/conf/
```

```
keytool -genkey -keyalg RSA -alias rangerKMSAgent -keystore
<ranger-kms-ks> -storepass myKeyFilePassword -validity 360 -
keysize 2048
```

```
chown kms:kms <ranger-kms-ks>
```

```
chmod 400 <ranger-kms-ks>
```

where

<ranger-kms-ks> is the name of the Ranger KMS keystore (for example, ranger-plugin-keystore.jks)

3. Provide an identifiable string in response to the question "What is your first and last name?"

Important: In case multiple servers need to communicate with Ranger admin for downloading policies for the same service/repository, make sure to use the repo name or a common string across all nodes. Remember exactly what you entered, because this value will be required for the Common Name for Certificate field on the edit repository page in the policy manager UI.

To create the keystore, provide answers to the subsequent questions. **Note:** Press enter when prompted for a password.

4. Create a truststore for the Ranger KMS plugin, and add the public key of admin as a trusted entry into the truststore:

```
cd /etc/ranger/kms/conf/
```

```
keytool -export -keystore <ranger-admin-ks> -alias rangeradmin -
file <cert-filename>
```

```
keytool -import -file <cert-filename> -alias rangeradmintrust -
keystore <ranger-kms-ts> -storepass changeit
```

```
chown kms:kms <ranger-kms-ts>
```

```
chmod 400 <ranger-kms-ts>
```

where

<ranger-admin-ks> is the location of the Ranger Admin keystore (for example, /etc/ranger/admin/conf/ranger-admin-keystore.jks)

<ranger-kms-ts> is the name of the Ranger KMS plugin truststore (for example, ranger-plugin-truststore.jks)

<cert-filename> is the name of the Ranger Admin certificate file (for example, ranger-admin-trust.cer)

Note: Press enter when prompted for a password.

5. Change the policy manager URL to point to HTTPS, and specify the keystore & truststore in `ews/webapp/WEB-INF/classes/conf/ranger-policymgr-ssl.xml`.
 - a. In `xasecure.policymgr.clientssl.keystore`, provide the location for the keystore that you created in the previous step.
 - b. In `xasecure.policymgr.clientssl.keystore.password`, provide the password for the keystore (`myKeyFilePassword`).
 - c. In `xasecure.policymgr.clientssl.truststore`, provide the location for the truststore that you created in the previous step.
 - d. In `xasecure.policymgr.clientssl.truststore.password`, provide the password for the truststore (`changeit`).

6. Add the plugin's self-signed cert into Admin's trustedCACerts:

```
cd /etc/ranger/admin/conf
```

```
keytool -export -keystore <ranger-kms-ks> -alias rangerKMSAgent  
-file <cert-filename> -storepass myKeyFilePassword
```

```
keytool -import -file <cert-filename> -alias rangerkmsAgentTrust  
-keystore <ranger-admin-ts> -storepass changeit
```

where

<ranger-kms-ks> is the path to the Ranger KMS keystore (for example, /etc/ranger/kms/conf/ranger-plugin-keystore.jks)

<cert-filename> is the name of the certificate file (for example, `ranger-kmsAgent-trust.cer`)

<ranger-admin-ts> is the name of the Ranger Admin truststore file (for example, the `JDK cacerts` file)

7. Log into the Policy Manager UI (as `keyadmin` user) and click on the Edit button of your KMS repository. Provide the CN name of the keystore for **Common Name For Certificate** (`commonNameForCertificate`), and save it. This property is not added by default.

The screenshot shows the Ranger web interface for configuring a KMS server. The page title is 'Ranger Access Manager Encryption'. The breadcrumb trail is 'Service Manager > Edit Service'. The main heading is 'Create Service'.

Service Details :

- Service Name * : cl1_kms
- Description : kms repo
- Active Status : Enabled Disabled

Config Properties :

- KMS URL * : kms/https@ip-172-31-26-219.ec2
- Username * : keyadmin
- Password * : ****

Below the password field, there is a section for 'Add New Configurations' with a table:

Name	Value
commonNameForCertificate	ip-172-31-26-219.ec2.internal

There is a '+' button below the table and a 'Test Connection' button at the bottom left. At the bottom right, there are 'Save', 'Cancel', and 'Delete' buttons.

Configuring the Ranger KMS Server

1. Go to the Ranger KMS config location and create a self-signed certificate:

```
cd /etc/ranger/kms/conf
```

```
keytool -genkey -keyalg RSA -alias rangerkms -keystore <ranger-kms-ks> -storepass rangerkms -validity 360 -keysize 2048
```

```
chown kms:kms ranger-kms-keystore.jks
```

```
chmod 400 ranger-kms-keystore.jks
```

where

<ranger-kms-ks> is the name of the Ranger KMS keystore (for example, ranger-plugin-keystore.jks)

Provide an identifiable string in response to the question "What is your first and last name?" To create the keystore, provide answers to all subsequent questions to create the keystore **Note:** Press enter when prompted for a password.

2. Add the following properties and values to the Custom ranger-kms-site list:

Property Name	Value	Status
ranger.service.https.keystore.file	/etc/ranger/kms/conf/ranger-kms-keystore.jks	OK
ranger.service.https.attr.client.auth	want	OK
ranger.service.https.attr.clientAuth	false	OK
ranger.service.https.attr.keystore.file	/etc/ranger/kms/conf/ranger-kms-keystore.jks	OK
ranger.service.https.attr.keystore.keyalias	rangerkms	OK
ranger.service.https.attr.keystore.pass	rangerkms	OK
ranger.service.https.attr.ssl.enabled	true	OK
ranger.service.https.port	9393	OK

[Add Property ...](#)

- Update the value of `kms_port` (in Advanced `kms_env`) to the `ranger.service.https.port` value.
- Save your changes and start Ranger KMS.
- In your browser (or from Curl) when you access the Ranger KMS UI using the HTTPS protocol on the `ranger.service.https.port` listed in Ambari, the browser should respond that it does not trust the site. Proceed, and you should be able to access Ranger KMS on HTTPS with the self-signed cert that you just created.
- Export the Ranger KMS certificate:

```
cd /usr/hdp/<version>/ranger-kms/conf
```

```
keytool -export -keystore <ranger-kms-ks> -alias rangerkms -file <cert-filename>
```

where

`<ranger-kms-ks>` is the name of the Ranger KMS keystore (for example, `ranger-kms-keystore.jks`)

`<cert-filename>` is the name of the certificate file (for example, `ranger-kms-trust.cer`)

- Import the Ranger KMS certificate into the Ranger admin truststore:

```
keytool -import -file <cert-filename> -alias rangerkms -keystore <ranger-admin-ts> -storepass changeit
```

where

<cert-filename> is the name of the certificate file (for example, ranger-kms-trust.cer)

<ranger-admin-ts> is the name of the Ranger Admin truststore file (for example, JDK cacerts)

8. Import the Ranger KMS certificate into the Hadoop client truststore:

```
keytool -import -file <cert-filename> -alias rangerkms -keystore <ts-filename> -storepass bigdata
```

where

<cert-filename> is the name of the certificate file (for example, ranger-kms-trust.cer)

<ts-filename> is the name of Hadoop client truststore file (for example, /etc/security/clientKeys/all.jks)

9. Restart Ranger Admin and Ranger KMS.

10. Now in the Policy Manager UI, Audit → Plugin tab, you should see an entry for your service name with HTTP Response Code = 200.

6.1.4. Install Multiple Ranger KMS

Multiple services can be set up for high availability of Ranger KMS. HDFS interacts with the active process.

Prerequisite: an instance with more than one node.

To install Ranger KMS on multiple nodes:


1. First install Ranger KMS on a single node (see [Installing the Ranger Key Management Service](#)).
2. Next, add the Ranger KMS service to another node.

In the Ambari Web UI for the additional node, go to Ranger KMS service # Summary # Service Actions # Add Ranger KMS server.



3. After adding Ranger KMS server, Ambari will show a pop-up message.
4. Press OK. Ambari will modify two HDFS properties, `hadoop.security.key.provider.path` and `dfs.encrypted.key.provider.uri`.

- Restart the HDFS service:



- For the Ranger KMS service, go to the Advanced kms-site list and change the following property values:

```
hadoop.kms.cache.enable=false
```

```
hadoop.kms.cache.timeout.ms=0
```

```
hadoop.kms.current.key.cache.timeout.ms=0
```

```
hadoop.kms.authentication.signer.secret.provider=zookeeper
```

```
hadoop.kms.authentication.signer.secret.provider.zookeeper.connection.string={ip of first node}:2181,{internal ip of second node}:2181, ...
```

```
hadoop.kms.authentication.signer.secret.provider.zookeeper.auth.type=none
```

- Save your configuration changes and restart the Ranger KMS service.

Next, check connectivity from Ranger admin for the newly-added Ranger KMS server:

- Go to the Ranger UI: `http://<gateway>:6080`
- Login with your keyadmin user ID and password (the defaults are `keyadmin`, `keyadmin`; these should be changed as soon as possible after installation). The default repository will be added under Ranger KMS service.
- Under Config properties of the Ranger KMS URL, add the newly added Ranger KMS server FQDN. For example:

 Previous Ranger KMS URL = `kms://http@<internal host name>:9292/kms`

 New Ranger KMS URL = `kms://http@<internal host name1>;<internal host name2>;...:9292/kms`
- Run a test connection for the service. You should see a 'connected successfully' message.
- Choose the Audit > Plugin tab.
- Check whether plugins are communicating. The UI should display HTTP Response Code = 200 for the respective plugin.

6.1.5. Using the Ranger Key Management Service

Ranger KMS can be accessed at the Ranger admin URL, `http://<hostname>:6080`. Note, however, that the login user for Ranger KMS is different than that for Ranger. Logging on as the Ranger KMS admin user leads to a different set of screens.

Role Separation

By default, Ranger admin uses a different admin user (`keyadmin`) to manage access policies and keys for Ranger KMS.

The person accessing Ranger KMS via the `keyadmin` user should be a different person than the administrator who works with regular Ranger access policies. This approach separates encryption work (encryption keys and policies) from Hadoop cluster management and access policy management.

6.1.5.1. Accessing the Ranger KMS Web UI


To access Ranger KMS, log in as user `keyadmin`, password `keyadmin`.



Important

Change the password after you log in.

After logging in, you will see the Service Manager screen. To view or edit Ranger KMS repository properties, click on the edit button next to the repository name:



You will see a list of service details and config properties for the repository:

The screenshot shows the Ranger web interface for creating a service. The top navigation bar includes 'Ranger', 'Access Manager', and 'Encryption', with a user profile 'keyadmin'. The breadcrumb trail shows 'Service Manager' > 'Edit Service'. The main heading is 'Create Service'.

Service Details :

- Service Name *
- Description
- Active Status Enabled Disabled

Config Properties :

- KMS URL *
- Username *
- Password *

Add New Configurations

Name	Value	
<input type="text"/>	<input type="text"/>	<input type="button" value="✖"/>

6.1.5.2. Listing and Creating Keys

To list existing keys:

1. Choose the Encryption tab at the top of the Ranger Web UI screen.
2. Select the Ranger KMS service from the drop-down list.

The screenshot shows the Ranger Key Management interface. At the top, there is a navigation bar with 'Ranger', 'Access Manager', and 'Encryption' tabs, and a user profile 'keyadmin'. Below this, a breadcrumb trail shows 'KMS' and 'Key Management'. A search bar is present with 'Select Service : cl1_kms' and a search icon. Below the search bar is a table of keys with columns: Key Name, Cipher, Version, Attributes, Length, Created Date, and Action. The table contains six rows of key information. An 'Add New Key' button is located to the right of the search bar.

Key Name	Cipher	Version	Attributes	Length	Created Date	Action
sensitivefolder	AES/CTR/NoPadding	1	key.acl.name → SensitiveFolder	128	08/06/2015 01:30:44 PM	[Edit] [Delete]
test	AES/CTR/NoPadding	1	key.acl.name → test	128	08/13/2015 01:49:35 PM	[Edit] [Delete]
testkeyfromcli	AES/CTR/NoPadding	1	key.acl.name → testkeyfromcli	128	07/24/2015 06:04:36 PM	[Edit] [Delete]
testkeyfromui	AES/CTR/NoPadding	1	key.acl.name → testkeyfromui	128	07/24/2015 06:04:16 PM	[Edit] [Delete]
testkeygmi	AES/CTR/NoPadding	1	key.acl.name → testkeyGMI	128	08/06/2015 02:02:40 PM	[Edit] [Delete]
tk1	AES/CTR/NoPadding	1	key.acl.name → tk1	128	08/25/2015 12:22:23 PM	[Edit] [Delete]

To create a new key:

1. Click on "Add New Key".
2. Add a valid key name.
3. Select the cipher name. Ranger supports AES/CTR/NoPadding as the cipher suite.
4. Specify the key length, 128 or 256 bits.
5. Add other attributes as needed, and then save the key.


The screenshot shows the 'Key Create' form in the Ranger interface. The breadcrumb trail is 'KMS > cl1_kms > Key Create'. The form is titled 'Key Detail' and contains several input fields: 'Key Name *' (required), 'Cipher' (set to AES/CTR/NoPadding), 'Length' (set to 128), and 'Description'. Below these is an 'Attributes' section with a table for 'Name' and 'Value', and a '+ ' button to add more attributes. At the bottom, there are 'Save' and 'Cancel' buttons.

6.1.5.3. Rolling Over an Existing Key



Rolling over (or "rotating") a key retains the same key name, but the key will have a different version. This operation re-encrypts existing file keys, but does not re-encrypt the actual file. Keys can be rolled over at any time.

After a key is rotated in Ranger KMS, new files will have the file key encrypted by the new master key for the encryption zone.

To rotate a key, click the edit button next to the key name in the list of keys, as shown in the following screenshot:




The screenshot shows the Ranger web interface. At the top, there's a green header with 'Ranger', 'Access Manager', and 'Encryption' tabs. Below that, a breadcrumb trail shows 'Service Manager' > 'c1_kms Policies'. The main content area is titled 'List of Policies : c1_kms'. It features a search bar with the placeholder 'Search for your policy...' and an 'Add New Policy' button. Below the search bar is a table with the following data:

Policy ID	Policy Name	Status	Audit Logging	Groups	Users	Action
1	c1_kms-1-20150724233747	Enabled	Enabled	public	keyadmin	 

Edit the key information, and then press Save.

When asked to confirm the rollover, click "OK":



6.1.5.4. Deleting a Key



Warning

Deleting a key associated with an existing encryption zone will result in data loss.

To delete an existing key:

1. Choose the Encryption tab at the top of the Ranger Web UI screen.
2. Select Ranger KMS service from the drop-down list.
3. Click on the delete symbol next to the key.
4. You will see a confirmation popup window; confirm or cancel.

6.1.6. Ranger KMS Properties

This chapter describes configuration properties for the Ranger Key Management Service (KMS).

Table 6.1. Properties in Advanced dbks-site Menu (dbks-site.xml)

Property Name	Default Value	Description
ranger.ks.masterkey.credential.alias	ranger.ks.masterkey.password	Credential alias used for masterkey.
ranger.ks.jpa.jdbc.user	rangerkms	Database username used for operation.
ranger.ks.jpa.jdbc.url	jdbc:log4jdbc:mysql://localhost:3306/rangerkms	JDBC connection URL for database.
ranger.ks.jpa.jdbc.password	_ (default it's encrypted)	Database user's password.
ranger.ks.jpa.jdbc.driver	net.sf.log4jdbc.DriverSpy	Driver used for database.
ranger.ks.jpa.jdbc.dialect	org.eclipse.persistence.platform.database.MySQLPlatform	Dialect used for database.
ranger.ks.jpa.jdbc.credential.provider.path	/etc/ranger/kms/rangerkms.jceks	Credential provider path.
ranger.ks.jpa.jdbc.credential.alias	ranger.ks.jdbc.password	Credential alias used for password.
ranger.ks.jdbc.sqlconnectorjar	/usr/share/java/mysql-connector-java.jar	Driver jar used for database.
ranger.db.encrypt.key.password	_ (Default; it's encrypted)	Password used for encrypting the Master Key.
hadoop.kms.blacklist.DECRYPT_EEK	hdfs	Blacklist for decrypt EncryptedKey CryptoExtension operations. This can have multiple user IDs in a comma separated list. e.g stormuser , yarn , hdfs.

Table 6.2. Properties in Advanced kms-env

Property Name	Default Value	Description
Kms User	kms	Ranger KMS process will be started using this user.
Kms Group	kms	Ranger KMS process will be started using this group.
LD library path		LD library path (basically used when the db flavor is SQLA). Example: /opt/sqlanywhere17/lib64
kms_port	9292	Port used by Ranger KMS.
kms_log_dir	/var/log/ranger/kms	Directory where the Ranger KMS log will be generated.

Table 6.3. Properties in Advanced kms-properties (install.properties)

Property Name	Default Value	Description
db_user	rangerkms	Database username used for the operation.
db_root_user		Database root username. Default is blank. Specify the root user.
db_root_password		Database root user's password. Default is blank. Specify the root user password.

Property Name	Default Value	Description
db_password		Database user's password for the operation. Default is blank. Specify the Ranger KMS database password.
db_name	rangerkms	Database name for Ranger KMS.
db_host	<FQDN of instance where the Ranger KMS is installed>	Hostname where the database is installed. Note: Check the hostname for DB and change it accordingly.
SQL_CONNECTOR_JAR	/usr/share/java/mysql-connector.jar	Location of DB client library.
REPOSITORY_CONFIG_USERNAME	keyadmin	User used in default repo for Ranger KMS.
REPOSITORY_CONFIG_PASSWORD	keyadmin	Password for user used in default repo for Ranger KMS.
KMS_MASTER_KEY_PASSWD		Password used for encrypting the Master Key. Default value is blank. Set the master key to any string.
DB_FLAVOR	MYSQL	Database flavor used for Ranger KMS. Supported values: MYSQL, SQLA, ORACLE, POSTGRES, MSSQL

Table 6.4. Properties in Advanced kms-site (kms-site.xml)

Property Name	Default Value	Description
hadoop.security.keystore. JavaKeyStoreProvider.password	none	If using the JavaKeyStoreProvide, the password for the keystore file.
hadoop.kms.security. authorization.manager	org.apache.ranger. authorization.kms. authorizer.RangerKmsAuthorizer	Ranger KMS security authorizer.
hadoop.kms.key.provider.uri	dbks://http@localhost:9292/kms	URI of the backing KeyProvider for the KMS.
hadoop.kms.current.key. cache.timeout.ms	30000	Expiry time for the KMS current key cache, in milliseconds. This affects getCurrentKey operations.
hadoop.kms.cache.timeout.ms	600000	Expiry time for the KMS key version and key metadata cache, in milliseconds. This affects getKeyVersion and getMetadata.
hadoop.kms.cache.enable	true	Whether the KMS will act as a cache for the backing KeyProvider. When the cache is enabled, operations like getKeyVersion, getMetadata, and getCurrentKey will sometimes return cached data without consulting the backing KeyProvider. Cached values are flushed when keys are deleted or modified. Note: This setting is beneficial if Single KMS and single mode are used. If this is set to true when multiple KMSs are used, or when the key operations are from different modes (Ranger UI, CURL, or hadoop command), it might cause inconsistency.
hadoop.kms.authentication.type	simple	Authentication type for the Ranger KMS. Can be either "simple" or "kerberos".

Property Name	Default Value	Description
hadoop.kms.authentication.signer.secret.provider.zookeeper.path	/hadoop-kms/hadoop-auth-signature-secret	The ZooKeeper ZNode path where the Ranger KMS instances will store and retrieve the secret from.
hadoop.kms.authentication.signer.secret.provider.zookeeper.kerberos.principal	kms/#HOSTNAME#	The Kerberos service principal used to connect to ZooKeeper
hadoop.kms.authentication.signer.secret.provider.zookeeper.kerberos.keytab	/etc/hadoop/conf/kms.keytab	The absolute path for the Kerberos keytab with the credentials to connect to ZooKeeper.
hadoop.kms.authentication.signer.secret.provider.zookeeper.connection.string	#HOSTNAME#:#PORT#,...	The ZooKeeper connection string, a list of hostnames and port comma separated. For example: <FQDN for first instance>:2181,<FQDN for second instance>:2181
hadoop.kms.authentication.signer.secret.provider.zookeeper.auth.type	kerberos	ZooKeeper authentication type: 'none' or 'sasl' (Kerberos)
hadoop.kms.authentication.signer.secret.provider	random	Indicates how the secret to sign authentication cookies will be stored. Options are 'random' (default), 'string', and 'zookeeper'. If you have multiple Ranger KMS instances, specify 'zookeeper'.
hadoop.kms.authentication.kerberos.principal	HTTP/localhost	The Kerberos principal to use for the HTTP endpoint. The principal must start with 'HTTP/' as per the Kerberos HTTP SPNEGO specification.
hadoop.kms.authentication.kerberos.name.rules	DEFAULT	Rules used to resolve Kerberos principal names.
hadoop.kms.authentication.kerberos.keytab	\${user.home}/kms.keytab	Path to the keytab with credentials for the configured Kerberos principal.
hadoop.kms.audit.aggregation.window.ms	10000	Specified in ms. Duplicate audit log events within this aggregation window are quashed to reduce log traffic. A single message for aggregated events is printed at the end of the window, along with a count of the number of aggregated events.

Table 6.5. Properties in Advanced ranger-kms-audit (ranger-kms-audit.xml)

Property Name	Default Value	Description
Audit provider summary enabled		Enable audit provider summary.
xasecure.audit.is.enabled	true	Enable audit.
xasecure.audit.destination.solr.zookeepers	none	Specify solr zookeeper string.
xasecure.audit.destination.solr.urls	{{ranger_audit_solr_urls}}	Specify solr URL. Note: In Ambari this value is populated from the Ranger Admin by default.
xasecure.audit.destination.solr.batch.filespool.dir	/var/log/ranger/kms/audit/solr/spool	Directory for solr audit spool.
Audit to SOLR		Enable audit to solr.
xasecure.audit.destination.hdfs.dir	hdfs://NAMENODE_HOST:8020/ranger/audit	HDFS directory to write audit.

Property Name	Default Value	Description
		Note: Make sure the service user has required permissions.
xasecure.audit.destination.hdfs.batch.filespool.dir	/var/log/ranger/kms/audit/hdfs/spool	Directory for HDFS audit spool.
Audit to HDFS		Enable hdfs audit.
xasecure.audit.destination.db.user	{{xa_audit_db_user}}	xa audit db user Note: In Ambari this value is populated from the Ranger Admin by default.
xasecure.audit.destination.db.password	encrypted (it's in encrypted format)	xa audit db user password Note: In Ambari this value is populated from the Ranger Admin by default.
xasecure.audit.destination.db.jdbc.url	{{audit_jdbc_url}}	Database JDBC URL for xa audit. Note: In Ambari the value for this is populated from the Ranger Admin by default.
xasecure.audit.destination.db.jdbc.driver	{{jdbc_driver}}	Database JDBC driver. Note: In Ambari this value is populated from the Ranger Admin by default.
xasecure.audit.destination.db.batch.filespool.dir	/var/log/ranger/kms/audit/db/spool	Directory for database audit spool.
Audit to DB		Enable audit to database.
xasecure.audit.credential.provider.file	jceks://file{{credential_file}}	Credential provider file.

Table 6.6. Properties in Advanced ranger-kms-policymgr-ssl

Property Name	Default Value	Description
xasecure.policymgr.clientssl.truststore.password	changeit	Password for the truststore.
xasecure.policymgr.clientssl.truststore	/usr/hdp/current/ranger-kms/conf/ranger-plugin-truststore.jks	jks file for truststore
xasecure.policymgr.clientssl.keystore.password	myKeyFilePassword	Password for keystore.
xasecure.policymgr.clientssl.keystore.credential.file	jceks://file{{credential_file}}	Java keystore credential file.
xasecure.policymgr.clientssl.keystore	/usr/hdp/current/ranger-kms/conf/ranger-plugin-keystore.jks	Java keystore file.
xasecure.policymgr.clientssl.truststore.credential.file	jceks://file{{credential_file}}	Java truststore file.

Table 6.7. Properties in Advanced ranger-kms-security

Property Name	Default Value	Description
ranger.plugin.kms.service.name	<default name for Ranger KMS Repo>	Name of the Ranger service containing policies for the KMS instance. Note: In Ambari the default value is <clusterName>_kms.
ranger.plugin.kms.policy.source.impl	org.apache.ranger.admin.client.RangerAdminRESTClient	Class to retrieve policies from the source.
ranger.plugin.kms.policy.rest.url	{{policymgr_mgr_url}}	URL for Ranger Admin.

Property Name	Default Value	Description
ranger.plugin.kms.policy.rest.ssl.config.file	/etc/ranger/kms/conf/ranger-policymgr-ssl.xml	Path to the file containing SSL details for contacting the Ranger Admin.
ranger.plugin.kms.policy.pollIntervalMs	30000	Time interval to poll for changes in policies.
ranger.plugin.kms.policy.cache.dir	/etc/ranger/{{repo_name}}/policycache	Directory where Ranger policies are cached after successful retrieval from the source.

6.1.7. Troubleshooting Ranger KMS

Table 6.8. Troubleshooting Suggestions

Issue	Action
Not able to install Ranger KMS	Check to see if ranger admin is running, verify DB.
Not able to start Ranger KMS	Check the Ranger KMS log. If there is a message about illegal key size, make sure unlimited strength JCE is available.
Hadoop key commands fail	Make sure Ranger KMS client properties are updated in hdfs config.
Not able to create keys from Ranger UI	Make sure that the <code>keyadmin</code> user (or any custom user) configured in the KMS repository is added to proxy properties in the custom <code>kms-site.xml</code> file.

6.2. HDFS "Data at Rest" Encryption

Encryption is a form of data security that is required in industries such as healthcare and the payment card industry. Hadoop provides several ways to encrypt stored data.

- The lowest level of encryption is volume encryption, which protects data after physical theft or accidental loss of a disk volume. The entire volume is encrypted; this approach does not support finer-grained encryption of specific files or directories. In addition, volume encryption does not protect against viruses or other attacks that occur while a system is running.
- Application level encryption (encryption within an application running on top of Hadoop) supports a higher level of granularity and prevents "rogue admin" access, but adds a layer of complexity to the application architecture.
- A third approach, HDFS data at rest encryption, encrypts selected files and directories stored ("at rest") in HDFS. This approach uses specially designated HDFS directories known as "encryption zones."

This chapter focuses on the third approach, HDFS data at rest encryption. The chapter is intended as an introductory quick start to HDFS data at rest encryption. Content will be updated regularly.

6.2.1. HDFS Encryption Overview

HDFS data at rest encryption implements end-to-end encryption of data read from and written to HDFS. End-to-end encryption means that data is encrypted and decrypted only by the client. HDFS does not have access to unencrypted data or keys.

HDFS encryption involves several elements:


- **Encryption key:** A new level of permission-based access protection, in addition to standard HDFS permissions.
- **HDFS encryption zone:** A special HDFS directory within which all data is encrypted upon write, and decrypted upon read.
 - Each encryption zone is associated with an encryption key that is specified when the zone is created.
 - Each file within an encryption zone has a unique encryption key, called the "data encryption key" (DEK).
 - HDFS does not have access to DEKs. HDFS DataNodes only see a stream of encrypted bytes. HDFS stores "encrypted data encryption keys" (EDEKs) as part of the file's metadata on the NameNode.
 - Clients decrypt an EDEK and use the associated DEK to encrypt and decrypt data during write and read operations.
- **Ranger Key Management Service (Ranger KMS):** An open source key management service based on Hadoop's `KeyProvider` API.

For HDFS encryption, the Ranger KMS has three basic responsibilities:

- Provide access to stored encryption zone keys.
- Generate and manage encryption zone keys, and create encrypted data keys to be stored in Hadoop.
- Audit all access events in Ranger KMS.

Note: This chapter is intended for security administrators who are interested in configuring and using HDFS encryption. For more information about Ranger KMS, see the [Ranger KMS Administration Guide](#).

Figure 6.1. HDFS Encryption Components



Role Separation

Access to the key encryption/decryption process is typically restricted to end users. This means that encrypted keys can be safely stored and handled by HDFS, because the HDFS admin user does not have access to them.

This role separation requires two types of HDFS administrator accounts:

- HDFS service user: the system-level account associated with HDFS (`hdfs` by default).
- HDFS admin user: an account in the `hdfs` supergroup, which is used by HDFS administrators to configure and manage HDFS.



Important

For clear segregation of duties, we recommend that you restrict use of the `hdfs` account to system/interprocess use. Do not provide its password to physical users. A (human) user who administers HDFS should only access HDFS through an admin user account created specifically for that purpose. For more information about creating an HDFS admin user, see [Creating an HDFS Admin User](#).

Other services may require a separate admin account for clusters with HDFS encryption zones. For service-specific information, see [Configuring HDP Services for HDFS Encryption](#).

6.2.2. Configuring and Starting the Ranger Key Management Service (Ranger KMS)

In a typical environment, a security administrator will set up the Ranger Key Management Service. For information about installing and configuring the Ranger KMS, see the [Ranger KMS Administration Guide](#).

6.2.3. Configuring and Using HDFS Data at Rest Encryption

After the Ranger KMS has been set up and the NameNode and HDFS clients have been configured, an HDFS administrator can use the `hadoop key` and `hdfs crypto` command-line tools to create encryption keys and set up new encryption zones.

The overall workflow is as follows:

1. Create an HDFS encryption zone key that will be used to encrypt the file-level data encryption key for every file in the encryption zone. This key is stored and managed by Ranger KMS.
2. Create a new HDFS folder. Specify required permissions, owner, and group for the folder.
3. Using the new encryption zone key, designate the folder as an encryption zone.
4. Configure client access. The user associated with the client application needs sufficient permission to access encrypted data. In an encryption zone, the user needs file/directory access (through Posix permissions or Ranger access control), as well as access for certain key operations. To set up ACLs for key-related operations, see the [Ranger KMS Administration Guide](#).

After permissions are set, Java API clients and HDFS applications with sufficient HDFS and Ranger KMS access privileges can write and read to/from files in the encryption zone.

6.2.3.1. Prepare the Environment

HDP supports hardware acceleration with Advanced Encryption Standard New Instructions (AES-NI). Compared with the software implementation of AES, hardware acceleration offers an order of magnitude faster encryption/decryption.

To use AES-NI optimization you need CPU and library support, described in the following subsections.

6.2.3.1.1. CPU Support for AES-NI optimization

AES-NI optimization requires an extended CPU instruction set for AES hardware acceleration.

There are several ways to check for this; for example:

```
$ cat /proc/cpuinfo | grep aes
```

Look for output with flags and 'aes'.

6.2.3.1.2. Library Support for AES-NI optimization

You will need a version of the `libcrypto.so` library that supports hardware acceleration, such as OpenSSL 1.0.1e. (Many OS versions have an older version of the library that does not support AES-NI.)

A version of the `libcrypto.so` library with AES-NI support must be installed on HDFS cluster nodes and MapReduce client hosts – that is, any host from which you issue HDFS or MapReduce requests. The following instructions describe how to install and configure the `libcrypto.so` library.

RHEL/CentOS 6.5 or later

On HDP cluster nodes, the installed version of `libcrypto.so` supports AES-NI, but you will need to make sure that the symbolic link exists:

```
$ sudo ln -s /usr/lib64/libcrypto.so.1.0.1e /usr/lib64/  
libcrypto.so
```

On MapReduce client hosts, install the `openssl-devel` package:

```
$ sudo yum install openssl-devel
```

6.2.3.1.3. Verifying AES-NI Support

To verify that a client host is ready to use the AES-NI instruction set optimization for HDFS encryption, use the following command:

```
hadoop checknative
```

You should see a response similar to the following:

```
15/08/12 13:48:39 INFO bzip2.Bzip2Factory: Successfully loaded & initialized  
native-bzip2 library system-native  
14/12/12 13:48:39 INFO zlib.ZlibFactory: Successfully loaded & initialized  
native-zlib library  
Native library checking:  
hadoop: true /usr/lib/hadoop/lib/native/libhadoop.so.1.0.0  
zlib: true /lib64/libz.so.1  
snappy: true /usr/lib64/libsnappy.so.1  
lz4: true revision:99  
bzip2: true /lib64/libbz2.so.1  
openssl: true /usr/lib64/libcrypto.so
```

If you see `true` in the `openssl` row, Hadoop has detected the right version of `libcrypto.so` and optimization will work.

If you see `false` in this row, you do not have the correct version.

6.2.3.2. Create an Encryption Key

Create a "master" encryption key for the new encryption zone. Each key will be specific to an encryption zone.

Ranger supports AES/CTR/NoPadding as the cipher suite. (The associated property is listed under HDFS -> Configs in the Advanced `hdfs-site` list.)

Key size can be 128 or 256 bits.


Recommendation: create a new superuser for key management. In the following examples, superuser `encr` creates the key. This separates the data access role from the encryption role, strengthening security.

Create an Encryption Key using Ranger KMS (Recommended)

In the Ranger Web UI screen:


1. Choose the Encryption tab at the top of the screen.

2. Select the KMS service from the drop-down list.



To create a new key:

1. Click on "Add New Key":
2. Add a valid key name.
3. Select the cipher name. Ranger supports AES/CTR/NoPadding as the cipher suite.
4. Specify the key length, 128 or 256 bits.
5. Add other attributes as needed, and then save the key.



For information about rolling over and deleting keys, see [Using the Ranger Key Management Service](#) in the *Ranger KMS Administration Guide*.



Warning

Do not delete an encryption key while it is in use for an encryption zone. This will result in loss of access to data in that zone.

Create an Encryption Key using the CLI

The full syntax of the `hadoop key create` command is as follows:

```
[create <keyname> [-cipher <cipher>]
[-size <size>]
[-description <description>]
[-attr <attribute=value>]
[-provider <provider>]
[-help]]
```

Example:

```
# su - encr
```

```
# hadoop key create <key_name> [-size <number-of-bits>]
```

The default key size is 128 bits. The optional `-size` parameter supports 256-bit keys, and requires the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on all hosts in the cluster. For installation information, see [Installing the JCE](#).

Example:

```
# su - encr
```

```
# hadoop key create key1
```

To verify creation of the key, list the metadata associated with the current user:

```
# hadoop key list -metadata
```

For information about rolling over and deleting keys, see [Using the Ranger Key Management Service](#) in the *Ranger KMS Administration Guide*.



Warning

Do not delete an encryption key while it is in use for an encryption zone. This will result in loss of access to data in that zone.

6.2.3.3. Create an Encryption Zone

Each encryption zone must be defined using an empty directory and an existing encryption key. An encryption zone cannot be created on top of a directory that already contains data.

Recommendation: use one unique key for each encryption zone.

Use the `crypto createZone` command to create a new encryption zone. The syntax is:

```
-createZone -keyName <keyName> -path <path>
```

where:

- `-keyName`: specifies the name of the key to use for the encryption zone.
- `-path` specifies the path of the encryption zone to be created. It must be an empty directory.



Note

The `hdfs` service account can create zones, but cannot write data unless the account has sufficient permission.

Recommendation: Define a separate user account for the HDFS administrator, and do not provide access to keys for this user in Ranger KMS.

Steps:

1. As HDFS administrator, create a new empty directory. For example:

```
# hdfs dfs -mkdir /zone_encr
```

2. Using the encryption key, make the directory an encryption zone. For example:

```
# hdfs crypto -createZone -keyName key1 -path /zone_encr
```

When finished, the NameNode will recognize the folder as an HDFS encryption zone.

3. To verify creation of the new encryption zone, run the `crypto -listZones` command as an HDFS administrator:

```
-listZones
```

You should see the encryption zone and its key. For example:

```
$ hdfs crypto -listZones  
/zone-encr key1
```



Note

The following property (in the `hdfs-default.xml` file) causes `listZone` requests to be batched. This improves NameNode performance. The property specifies the maximum number of zones that will be returned in a batch.

```
dfs.namenode.list.encryption.zones.num.responses
```

The default is 100.

To remove an encryption zone, delete the root directory of the zone. For example:

```
hdfs dfs -rm -R /zone_encr
```

6.2.3.4. Copy Files from/to an Encryption Zone

To copy existing files into an encryption zone, use a tool like `distcp`.

Note: for separation of administrative roles, do not use the `hdfs` user to create encryption zones. Instead, designate another administrative account for creating encryption keys and zones. See [Creating an HDFS Admin User](#) for more information.

The files will be encrypted using a file-level key generated by the Ranger Key Management Service.

DistCp Considerations

`DistCp` is commonly used to replicate data between clusters for backup and disaster recovery purposes. This operation is typically performed by the cluster administrator, via an HDFS superuser account.

To retain this workflow when using HDFS encryption, a new virtual path prefix has been introduced, `/.reserved/raw/`. This virtual path gives super users direct access to the underlying encrypted block data in the file system, allowing super users to `distcp` data without requiring access to encryption keys. This also avoids the overhead of decrypting and re-encrypting data. The source and destination data will be byte-for-byte identical, which would not be true if the data were re-encrypted with a new EDEK.



Warning

When using `/.reserved/raw/` to `distcp` encrypted data, make sure you preserve extended attributes with the `-px` flag. This is necessary because encrypted attributes such as the EDEK are exposed through extended attributes; they *must* be preserved to be able to decrypt the file. For example:

```
sudo -u encr hadoop distcp -px hdfs://cluster1-  
namenode:50070/.reserved/raw/apps/enczone hdfs://cluster2-  
namenode:50070/.reserved/raw/apps/enczone
```

This means that if the `distcp` operation is initiated at or above the encryption zone root, it will automatically create a new encryption zone at the destination (if one does not already exist).

Recommendation: To avoid potential mishaps, first create identical encryption zones on the destination cluster.

Copying between encrypted and unencrypted locations

By default, `distcp` compares file system checksums to verify that data was successfully copied to the destination.

When copying between an unencrypted and encrypted location, file system checksums will not match because the underlying block data is different. In this case, specify the `-skipcrccheck` and `-update` flags to avoid verifying checksums.

6.2.3.5. Read and Write Files from/to an Encryption Zone

Clients and HDFS applications with sufficient HDFS and Ranger KMS permissions can read and write files from/to an encryption zone.

Overview of the client write process:

1. The client writes to the encryption zone.
2. The NameNode checks to make sure that the client has sufficient write access permissions. If so, the NameNode asks Ranger KMS to create a file-level key, encrypted with the encryption zone master key.
3. The Namenode stores the file-level encrypted data encryption key (EDEK) generated by Ranger KMS as part of the file's metadata, and returns the EDEK to the client.
4. The client asks Ranger KMS to decode the EDEK (to DEK), and uses the DEK to write encrypted data. Ranger KMS checks for permissions for the user before decrypting EDEK and producing the DEK for the client.

Overview of the client read process:

1. The client issues a read request for a file in an encryption zone.
2. The NameNode checks to make sure that the client has sufficient read access permissions. If so, the NameNode returns the file's EDEK and the encryption zone key version that was used to encrypt the EDEK.
3. The client asks Ranger KMS to decrypt the EDEK. Ranger KMS checks for permissions to decrypt EDEK for the end user.
4. Ranger KMS decrypts and returns the (unencrypted) data encryption key (DEK).
5. The client uses the DEK to decrypt and read the file.

The preceding steps take place through internal interactions between the DFSClient, the NameNode, and Ranger KMS.

In the following example, the `/zone_encr` directory is an encrypted zone in HDFS.

To verify this, use the `crypto -listZones` command (as an HDFS administrator). This command lists the root path and the zone key for the encryption zone. For example:

```
# hdfs crypto -listZones
/zone_encr key1
```

Additionally, the `/zone_encr` directory has been set up for read/write access by the `hive` user:

```
# hdfs dfs -ls /
...
drwxr-x--- - hive hive 0 2015-01-11 23:12 /zone_encr
```

The `hive` user can, therefore, write data to the directory.

The following examples use the `copyFromLocal` command to move a local file into HDFS.

```
[hive@blue ~]# hdfs dfs -copyFromLocal web.log /zone_encr
[hive@blue ~]# hdfs dfs -ls /zone_encr
Found 1 items
-rw-r--r--  1 hive hive          1310 2015-01-11 23:28 /zone_encr/web.log
```

The `hive` user can read data from the directory, and can verify that the file loaded into HDFS is readable in its unencrypted form.

```
[hive@blue ~]# hdfs dfs -copyToLocal /zone_encr/web.log read.log
[hive@blue ~]# diff web.log read.log
```



Note

For more information about accessing encrypted files from Hive and other components, see [Configuring HDP Services for HDFS Encryption](#).

Users without access to KMS keys will be able to see file names (via the `-ls` command), but they will not be able to write data or read from the encrypted zone. For example, the `hdfs` user lacks sufficient permissions, and cannot access the data in `/zone_encr`:

```
[hdfs@blue ~]# hdfs dfs -copyFromLocal install.log /zone_encr
copyFromLocal: Permission denied: user=hdfs, access=EXECUTE, inode="/
zone_encr":hive:hive:drwxr-x---
```

```
[hdfs@blue ~]# hdfs dfs -copyToLocal /zone_encr/web.log read.log
copyToLocal: Permission denied: user=hdfs, access=EXECUTE, inode="/
zone_encr":hive:hive:drwxr-x---
```

6.2.3.6. Delete Files from an Encryption Zone with Trash Enabled

The trash location for encrypted HDFS files is different than the default trash location for unencrypted files (`/user/$USER/.Trash/Current/OriginalPathToDeletedFile`).

When trash is enabled and an encrypted file is deleted, the file is moved to the `.Trash` subdirectory under the root of the encryption zone as `/EncryptionZoneRoot/.Trash/$USER/Current/OriginalPathToDeletedFile`. The file remains encrypted without additional decryption/re-encryption overhead during the move to trash. The move operation preserves the name of the user who executes the deletion, and the full path of the deleted file.

For example, if user `hdp-admin` deletes file `/zone_name/file1` using the following command:

```
hdfs dfs -rm /zone_name/file1
```

`file1` will remain encrypted, and it will be moved to the following location within the encryption zone:

```
/zone_name/.Trash/hdp-admin/Current/zone_name/file1
```

A trash checkpoint will be created for the `.Trash` subdirectory in each encryption zone. Checkpoints will be deleted/created according to the value of `fs.trash.checkpoint.interval` (number of minutes between trash checkpoints). A checkpoint for this example would be:

```
/zone_name/.Trash/hdp-admin/<CheckPointTimeStamp>/zone_name/  
file1
```

For additional information, see Apache [HDFS-8831](#).

6.2.4. Configuring HDP Services for HDFS Encryption

HDFS data at rest encryption is supported on the following HDP components:

- Hive
- Hive on Tez
- HBase
- Sqoop
- YARN
- MapReduce
- Oozie
- WebHDFS

HDFS data at rest encryption is not supported on the following components:

- Spark
- HDP Search
- Storm
- Accumulo
- Falcon

The remainder of this section describes scenarios and access considerations for accessing HDFS-encrypted files from supporting HDP components.

6.2.4.1. Hive

Recommendation: Store Hive data in an HDFS path called `/apps/hive`.

6.2.4.1.1. Configuring Hive Tables for HDFS Encryption

Before enabling encryption zones, decide whether to store your Hive tables across one zone or multiple encryption zones.

Single Encryption Zone

To configure a single encryption zone for your entire Hive warehouse:

1. Rename `/apps/hive` to `/apps/hive-old`

2. Create an encryption zone at `/apps/hive`
3. `distcp` all of the data from `/apps/hive-old` to `/apps/hive`.

To configure the Hive scratch directory (`hive.exec.scratchdir`) so that it resides inside the encryption zone:

1. Set the directory to `/apps/hive/tmp`.
2. Make sure that the permissions for `/apps/hive/tmp` are set to `1777`.

Multiple Encryption Zones

To access encrypted databases and tables with different encryption keys, configure multiple encryption zones.

For example, to configure two encrypted tables, `ez1.db` and `ez2.db`, in two different encryption zones:

1. Create two new encryption zones, `/apps/hive/warehouse/ez1.db` and `/apps/hive/warehouse/ez2.db`.
2. Load data into Hive tables `ez1.db` and `ez2.db` as usual, using `LOAD` statements. (For additional considerations, see "Loading Data into an Encrypted Table.")

6.2.4.1.2. Loading Data into an Encrypted Table

By design, HDFS-encrypted files cannot be moved or loaded from one encryption zone into another encryption zone, or from an encryption zone into an unencrypted directory. Encrypted files can only be copied.

Within an encryption zone, files can be copied, moved, loaded, and renamed.

Recommendations:

- When loading unencrypted data into encrypted tables (e.g., `LOAD DATA INPATH`), we recommend placing the source data (to be encrypted) into a landing zone within the destination encryption zone.
- An attempt to load data from one encryption zone into another will result in a copy operation. `Distcp` will be used to speed up the process if the size of the files being copied is higher than the value specified by the `hive.exec.copyfile.maxsize` property. The default limit is 32 MB.

Here are two approaches for loading unencrypted data into an encrypted table:

- To load unencrypted data into an encrypted table, use the `LOAD DATA ...` statement.

If the source data does not reside inside the encryption zone, the `LOAD` statement will result in a copy. If your data is already inside HDFS, though, you can use `distcp` to speed up the copying process.

- If the data is already inside a Hive table, create a new table with a `LOCATION` inside an encryption zone, as follows:


```
CREATE TABLE encrypted_table [STORED AS] LOCATION ... AS SELECT *
FROM <unencrypted_table>
```



Note

The location specified in the `CREATE TABLE` statement must be within an encryption zone. If you create a table that points `LOCATION` to an unencrypted directory, your data will not be encrypted. You must copy your data to an encryption zone, and then point `LOCATION` to that encryption zone.

If your source data is already encrypted, use the `CREATE TABLE` statement. Point `LOCATION` to the encrypted source directory where your data resides:

```
CREATE TABLE encrypted_table [STORED AS] LOCATION ... AS SELECT *
FROM <encrypted_source_directory>
```

This is the fastest way to create encrypted tables.

6.2.4.1.3. Encrypting Other Hive Directories

- **LOCALSCRATCHDIR** : The MapJoin optimization in Hive writes HDFS tables to a local directory and then uploads them to distributed cache. To enable encryption, either disable MapJoin (set `hive.auto.convert.join` to `false`) or encrypt the local Hive Scratch directory (`hive.exec.local.scratchdir`). **Performance note:** disabling MapJoin will result in slower join performance.
- **DOWNLOADED_RESOURCES_DIR**: Jars that are added to a user session and stored in HDFS are downloaded to `hive.downloaded.resources.dir`. If you want these Jar files to be encrypted, configure `hive.downloaded.resources.dir` to be part of an encryption zone. This directory needs to be accessible to the HiveServer2.
- **NodeManager Local Directory List**: Hive stores Jars and MapJoin files in the distributed cache, so if you'd like to use MapJoin or encrypt Jars and other resource files, the YARN configuration property NodeManager Local Directory List (`yarn.nodemanager.local-dirs`) must be configured to a set of encrypted local directories on all nodes.

Alternatively, to disable MapJoin, set `hive.auto.convert.join` to `false`.

6.2.4.1.4. Additional Changes in Behavior with HDFS-Encrypted Tables

- Users reading data from read-only encrypted tables must have access to a temp directory that is encrypted with at least as strong encryption as the table.
- By default, temp datas related to HDFS encryption is written to a staging directory identified by the `hive-exec.stagingdir` property created in the `hive-site.xml` file? associated with the table folder.
- Previously, an `INSERT OVERWRITE` on a partitioned table inherited permissions for new data from the existing partition directory. With encryption enabled, permissions are inherited from the table.

- When using encryption with Trash enabled, table deletion operates differently than the default trash mechanism. For more information see [Delete Files from an Encryption Zone](#).

6.2.4.2. HBase

HBase stores all of its data under its root directory in HDFS, configured with `hbase.rootdir`. The only other directory that the HBase service will read or write is `hbase.bulkload.staging.dir`.

On HDP clusters, `hbase.rootdir` is typically configured as `/apps/hbase/data`, and `hbase.bulkload.staging.dir` is configured as `/apps/hbase/staging`. HBase data, including the root directory and staging directory, can reside in an encryption zone on HDFS.

The HBase service user needs to be granted access to the encryption key in the Ranger KMS, because it performs tasks that require access to HBase data (unlike Hive or HDFS).

By design, HDFS-encrypted files cannot be bulk-loaded from one encryption zone into another encryption zone, or from an encryption zone into an unencrypted directory. Encrypted files can only be copied. An attempt to load data from one encryption zone into another will result in a copy operation. Within an encryption zone, files can be copied, moved, bulk-loaded, and renamed.

6.2.4.2.1. Recommendations

- Make the parent directory for the HBase root directory and bulk load staging directory an encryption zone, instead of just the HBase root directory. This is because HBase bulk load operations need to move files from the staging directory into the root directory.
- In typical deployments, `/apps/hbase` can be made an encryption zone.
- Do not create encryption zones as subdirectories under `/apps/hbase`, because HBase may need to rename files across those subdirectories.
- The landing zone for unencrypted data should always be within the destination encryption zone.

6.2.4.2.2. Steps

On a cluster without HBase currently installed:

1. Create the `/apps/hbase` directory, and make it an encryption zone.
2. Configure `hbase.rootdir=/apps/hbase/data`.
3. Configure `hbase.bulkload.staging.dir=/apps/hbase/staging`.

On a cluster with HBase already installed, perform the following steps:

1. Stop the HBase service.
2. Rename the `/apps/hbase` directory to `/apps/hbase-tmp`.
3. Create an empty `/apps/hbase` directory, and make it an encryption zone.

4. `DistCp -skipcrccheck -update` all data from `/apps/hbase-tmp` to `/apps/hbase`, preserving user-group permissions and extended attributes.
5. Start the HBase service and verify that it is working as expected.
6. Remove the `/apps/hbase-tmp` directory.

6.2.4.2.3. Changes in Behavior after HDFS Encryption is Enabled

The HBase bulk load process is a MapReduce job that typically runs under the user who owns the source data. HBase data files created as a result of the job are then bulk loaded in to HBase RegionServers. During this process, HBase RegionServers move the bulk-loaded files from the user's directory and move (rename) the files into the HBase root directory (`/apps/hbase/data`). When data at rest encryption is used, HDFS cannot do a rename across encryption zones with different keys.

Workaround: run the MapReduce job as the `hbase` user, and specify an output directory that resides in the same encryption zone as the HBase root directory.

6.2.4.3. Sqoop

Following are considerations for using Sqoop to import or export HDFS-encrypted data.

6.2.4.3.1. Recommendations

- **For Hive:**

Make sure that you are using Sqoop with the `--target-dir` parameter set to a directory that is inside the Hive encryption zone. Specify the `-D` option after `sqoop import`.

For example:

```
sqoop import \  
-D sqoop.test.import.rootDir=<root-directory> \  
--target-dir <directory-inside-encryption-zone> \  
<additional-arguments>
```

- **For append or incremental import:**

Make sure that the `sqoop.test.import.rootDir` property points to the encryption zone specified in the `--target-dir` argument.

- **For HCatalog:**

No special configuration is required.

6.2.4.4. MapReduce on YARN

Recommendation: Make `/apps/history` a single encryption zone. History files are moved between the `intermediate` and `done` directories, and HDFS encryption will not allow you to move encrypted files across encryption zones.

6.2.4.4.1. Steps

On a cluster with MapReduce over YARN installed, create the `/apps/history` directory and make it an encryption zone.

If `/apps/history` already exists and is not empty:

1. Create an empty `/apps/history-tmp` directory
2. Make `/apps/history-tmp` an encryption zone
3. Copy (`distcp`) all data from `/apps/history` into `/apps/history-tmp`
4. Remove `/apps/history`
5. Rename `/apps/history-tmp` to `/apps/history`

6.2.4.5. Oozie

6.2.4.5.1. Recommendations

A new Oozie administrator role (`oozie-admin`) has been created in HDP 2.3.

This role enables role separation between the Oozie daemon and administrative tasks. Both the `oozie-admin` role and the `oozie` role must be specified in the `adminusers.txt` file. This file is installed in HDP 2.3 with both roles specified. Both are also defined in Ambari 2.1 as well. Modification is only required if administrators choose to change the default administrative roles for Oozie.

If `oozie-admin` is used as the Oozie administrator user in your cluster, then the role is automatically managed by ambari.

If you plan to create an Oozie admin user other than `oozie-admin`, add the chosen username to `adminusers.txt` under the `$OOZIE_HOME/conf` directory.

Here is a sample `adminusers.txt` file:

```
#
# Licensed to the Apache Software Foundation (ASF) under one
# or more contributor license agreements. See the NOTICE file
# distributed with this work for additional information
# regarding copyright ownership. The ASF licenses this file
# to you under the Apache License, Version 2.0 (the
# "License"); you may not use this file except in compliance
# with the License. You may obtain a copy of the License at
#
# http://www.apache.org/licenses/LICENSE-2.0
#
# Unless required by applicable law or agreed to in writing, software
# distributed under the License is distributed on an "AS IS" BASIS,
# WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
# See the License for the specific language governing permissions and
# limitations under the License.
#
# Users should be set using following rules:
#
# One user name per line
```

```
# Empty lines and lines starting with '#' are ignored
oozie
oozie-admin
```

6.2.4.6. WebHDFS

6.2.4.6.1. Recommendations

WebHDFS is supported for writing and reading files to and from encryption zones.

6.2.4.6.1.1. Steps

To access encrypted files via WebHDFS, complete the following steps:

1. To enable WebHDFS in `hdfs-site.xml`, set the `dfs.webhdfs.enabled` property to true:

```
<property>
  <name>dfs.webhdfs.enabled</name>
  <value>true</value>
</property>
```

2. Make sure that you have separate HDFS administrative and service users, as described in [Creating an HDFS Admin User](#).
3. KMS supports a blacklist and a whitelist for key access (through `kms-acls.xml`).

By default the `hdfs` service user is included in the blacklist for `decrypt_eeek` operations. To support WebHDFS, the HDFS service user must not be on the key access blacklist. Remove the HDFS service user from the blacklist:

- a. To edit the blacklist using Ambari, go to Ranger KMS -> Configs, and search for "blacklist" or open the Advanced `dbks-site` list.
- b. Remove `hdfs` from the `hadoop.kms.blacklist.DECRYPT_EEK` property:

- c. Restart Ranger KMS.
4. The HDFS service user must have `GENERATE_EEK` and `DECRYPT_EEK` permissions. To add the permissions using the Ranger Web UI, select the Access Manager tab-> Resource Based Policies (the default Access Manager view). Select the key store, select the policy, and click the edit icon. In the Permissions column click the edit icon and check the boxes for `GenerateEEK` and `DecryptEEK`. Then click Save.

The screenshot shows the Ranger Web UI interface for creating a policy. The breadcrumb navigation is Service Manager > cl1_krms Policies > Create Policy. The page title is 'Create Policy'. Under 'Policy Details', the 'Policy Name' is 'hdfs-svc', 'Key Name' is 'hdfs', and 'Audit Logging' is set to 'YES'. The 'User and Group Permissions' section shows a table with columns for 'Select Group', 'Select User', 'Permissions', and 'Delegate Admin'. The 'Permissions' column has 'Decrypt EEK' and 'Generate EEK' checked. The 'Add' button is highlighted in green.

5. Because the HDFS service user will have access to all keys, the HDFS service user should not be the administrative user. Specify a different administrative user in `hdfs-site.xml` for the administrative user.

For more information about operational tasks using Ranger KMS, see the [Ranger KMS Administration Guide](#).

6.2.5. Appendix: Creating an HDFS Admin User

To capitalize on the capabilities of HDFS data at rest encryption, you will need two separate types of HDFS administrative accounts:

- HDFS administrative user: an account in the `hdfs` supergroup that is used to manage encryption keys and encryption zones. Examples in this chapter use an administrative user account named `encr`.
- HDFS service user: the system-level account traditionally associated with HDFS. By default this is user `hdfs` in HDP. This account owns the HDFS DataNode and NameNode processes.



Important

This is a system-only account. Physical users should not be given access to this account.

Complete the following steps to create a new HDFS administrative user.

Note: These steps use sample values for group (`operator`) and user account (`opt1`).

1. Create a new group called `operator`.
2. Add a new user (for example, `opt1`) to the group.
3. Add principal `opt1@EXAMPLE.COM` and create a keytab.
4. Login as `opt1`, and do a `kinit` operation.
5. In Ambari, replace the current value of `dfs.permissions.superusergroup` with the group name "operator".



Note

You can assign only one administrator group for the `dfs.permissions.superusergroup` parameter.

6. In Ambari, add `hdfs,operator` to `dfs.cluster.administrators`:



7. Add `opt1` to the KMS blacklist. Set the corresponding property in Ambari:

```
hadoop.kms.blacklist.DECRYPT_EEK=opt1
```

8. Restart HDFS.

Validation

Make sure the `opt1` account has HDFS administrative access:

```
hdfs dfsadmin -report
```

Make sure the `opt1` account cannot access encrypted files. For example, if `/data/test/file.txt` is in an encryption zone, the following command should return an error:

```
hdfs dfs -cat /data/test/file.txt
```

Additional Administrative User Accounts

If you plan to use HDFS data at rest encryption with YARN, we recommend that you create a separate administrative user account for YARN administration.

If you plan to use HDFS data at rest encryption with Oozie, refer to the [Oozie](#) section of this chapter.